

# MY FOOD

## Installer Guide

### with pictures

How to connect the tills, printers, kitchen screens and customer display at **Chefelisha Restaurant**.

#### You need:


- Internet in the restaurant (Wi-Fi or cable)
- The owner or a manager, signed in to MY FOOD on their phone or laptop
- Each till / screen with **Google Chrome** or **Microsoft Edge**
- One Windows PC at the counter for printing (it can be a till)
- Printers switched on, with paper

Address: **[www.chefelisha.cc](http://www.chefelisha.cc)**

Follow the pages in order. Red boxes and arrows show exactly what to press.  
Pictures are from the MY FOOD test system: names and numbers on your screen will be slightly different.

## BEFORE YOU START


# How it fits together



**Use these names.** Each device already has a row with its name in MY FOOD → **Devices & printing**. Stick a label with the name on each device so you always pair the right one.

# 1 On the till: open the pairing page

Open Chrome on the till and go to **www.chefelisha.cc/pair**. The till shows a code. Leave it on the screen.



The code works for 10 minutes. **Do not press “Show a new code”.**

## 2

## On the manager's phone: find the till's row

Open MY FOOD → **Devices & printing**. Find the row with this till's name (e.g. POS-01) and press **Enter code from device** on that row.

**Chefelisha Restaurant (test)**  
Main

**OPERATIONS**

- Dashboard
- POS
- Orders
- Cash register
- Customers
- Kitchen
- Supervisor
- Customer display

**INVENTORY**

- Stock
- Stock taking

**MENU & SETUP**

- Menu & recipes
- Stations & routing
- Floor & tables
- Devices & printing**

**Devices & printing**

Tills, kitchen screens, customer display and printers. Hardware can be connected at any time.

**Device status (from heartbeats and printer reports)** ● Live

**Printing is not running yet.** A browser cannot send to receipt printers by itself: one PC in the restaurant runs **MY FOOD Printing** and prints for everyone.

1. On a Windows PC at the counter that stays on during service, download and install [MY FOOD Printing](#).
2. It shows a code. Press **Enter code from device** on **PRINT-AGENT-01** and type it.
3. In MY FOOD Printing, use "Search the network" to find each printer, then Edit the printer here with that address.

27 print jobs are waiting and will print as soon as printing runs.

| DEVICE          | TYPE           | STATUS     | LAST SEEN  | DETAILS |
|-----------------|----------------|------------|------------|---------|
| Akosua device 1 | POS till       | ● Not sent | —          | paired  |
| Ama device 1    | POS till       | ● Not sent | —          | paired  |
| <b>POS-01</b>   | POS till       | ● Offline  | 9:16:36 PM | paired  |
| DRINK-01        | Kitchen screen | ● Offline  | 9:16:38 PM | paired  |
|                 |                | ● Offline  | 9:16:19 PM | paired  |
| KITCHEN-01      | Kitchen screen | ● Offline  | 9:16:17 PM | paired  |
| PASTRY-01       | Kitchen screen | ● Offline  | 9:16:21 PM | paired  |

**1 Find the till's name**

**2 Press on THAT row**

### 3 Type the code, press Pair device

Type the code exactly as the till shows it, then press **Pair device**.

The screenshot shows the 'Devices & printing' section of the MY FOOD Restaurant Management System. A modal dialog titled 'Pair POS-01' is open, displaying the code 'ENCZ-8YSM'. The dialog includes instructions: 'Type the code shown on the device's "Pair this device" screen (https://restaurant-management-staging.vercel.app/pair). The device then becomes POS-01 and continues by itself.' Below the code, a message states: 'POS-01 is already paired. Pairing it again gives it a new login: the screen that uses it now is signed out. Only continue for a new or reset screen.' At the bottom of the dialog are 'Cancel' and 'Pair device' buttons. Red arrows and numbered callouts indicate the steps: 1. Type the code from the till, and 2. Press Pair device.

**Pair POS-01**

Type the code shown on the device's "Pair this device" screen (https://restaurant-management-staging.vercel.app/pair). The device then becomes POS-01 and continues by itself.

POS-01 is already paired. Pairing it again gives it a new login: the screen that uses it now is signed out. Only continue for a new or reset screen.

A code you made with "Create code" is not entered here: it is typed on the device itself.

**ENCZ-8YSM**

Cancel Pair device


1 Type the code from the till

2 Press Pair device

| Device     | Status  | Last Seen  | Paired | Enter code from device | Create code | Edit | Revoke |
|------------|---------|------------|--------|------------------------|-------------|------|--------|
| AKOSUA-01  | Online  | 9:16:17 PM | paired | Enter code from device | Create code | Edit | Revoke |
| AMA-01     | Online  | 9:16:17 PM | paired | Enter code from device | Create code | Edit | Revoke |
| POS-01     | Online  | 9:16:17 PM | paired | Enter code from device | Create code | Edit | Revoke |
| DRINKS-01  | Online  | 9:16:17 PM | paired | Enter code from device | Create code | Edit | Revoke |
| GRILL-01   | Online  | 9:16:17 PM | paired | Enter code from device | Create code | Edit | Revoke |
| KITCHEN-01 | Offline | 9:16:21 PM | paired | Enter code from device | Create code | Edit | Revoke |
| PASTRY-01  | Offline | 9:16:21 PM | paired | Enter code from device | Create code | Edit | Revoke |

## 4 Done: the till shows the PIN pad

Within a few seconds the till continues by itself and shows **Enter your staff PIN**. Repeat steps 1–4 for every till, each on its own row.



Restarting the till is fine. It stays paired.

## 5 On the printing PC: download MY FOOD Printing

On the Windows PC at the counter, sign in to MY FOOD, open **Devices & printing** and click **MY FOOD Printing** to download it.


**Chefelisha Restaurant (test)**  
Main

**OPERATIONS**  
Dashboard  
POS  
Orders  
Cash register  
Customers  
Kitchen  
Supervisor  
Customer display  
**INVENTORY**  
Stock  
Stock taking  
**MENU & SETUP**  
Menu & recipes  
Stations & routing  
Floor & tables  
**Devices & printing**

### Devices & printing

Tills, kitchen screens, customer display and printers. Hardware can be connected at any time.

**Device status (from heartbeats and printer reports)** ● Live

**Printing is not running yet.** A browser cannot send to receipt printers by itself: one PC in the restaurant runs **MY FOOD Printing** and prints for everyone.

1. On a Windows PC at the counter that stays on during service, download and install [MY FOOD Printing](#)
2. It shows a code. Press **Enter code from device** on **PRINT-AGENT-01** and type it.
3. In MY FOOD Printing, use "Search the network" to find each printer, then Edit the printer with that address.


27 print jobs are waiting and will print as soon as printing runs.

| DEVICE          | TYPE           | STATUS     | LAST SEEN  | DETAILS |
|-----------------|----------------|------------|------------|---------|
| Akosua device 1 | POS till       | ● Not sent | —          | paired  |
| Ama device 1    | POS till       | ● Not sent | —          | paired  |
| POS-01          | POS till       | ● Offline  | 9:16:36 PM | paired  |
| DRINKS-01       | Kitchen screen | ● Offline  | 9:16:38 PM | paired  |
| GRILL-01        | Kitchen screen | ● Offline  | 9:16:19 PM | paired  |
| KITCHEN-01      | Kitchen screen | ● Offline  | 9:16:17 PM | paired  |
| PASTRY-01       | Kitchen screen | ● Offline  | 9:16:21 PM | paired  |

**1 Download MY FOOD Printing here (on the printing PC)**

## 6 Install it (Windows warning)

Open the downloaded file **MY-FOOD-Printing-Setup.exe**. Windows may show a blue warning. Click **More info**. A **Run anyway** button then appears: click it.



Drawing: the real window may look a little different.

This warning appears because the app is new, not because something is wrong. MY FOOD Printing then opens by itself and starts with Windows every day.

## 7 MY FOOD Printing shows a code

The window says **Connect this PC to MY FOOD** and shows a code.

**MY FOOD Printing**  
Chefelisha Restaurant

Not connected yet

**Connect this PC to MY FOOD**

1. On a phone or computer, open MY FOOD and go to **Devices & printing**.
2. On the print agent (for example **PRINT-AGENT-01**), press **Enter code from device**.
3. Type this code:

**H4TW-9KPD**

1 MY FOOD Printing shows a code

Waiting for the code to be entered... (the code works for about 9 more minutes; a new one then appears)

Enter it on the **print agent** row only, not on a till: this PC then prints for all tills.

Show a new code

**Find printers**

Find the address of a network printer, or the name of a USB printer plugged into this PC, then enter it in MY FOOD → Devices & printing → Edit printer.

Search the network

USB printers on this PC

Paper80 mm ▾

**Recent activity**

Nothing yet.

## 8

## Enter that code ONLY on PRINT-AGENT-01

On the manager's phone: **Devices & printing** → the **PRINT-AGENT-01** row → **Enter code from device** → type the code → **Pair device**.

**1** Only the PRINT-AGENT-01 row

**2** Press here, type the code, Pair device

| Name                | Type             | Status   | IP Address        | Waiting    | Actions                                             |
|---------------------|------------------|----------|-------------------|------------|-----------------------------------------------------|
| DRINKS-PRINTER-01   | Printer          | Not sent | 192.168.1.54:9100 | 14 waiting | Test print, Edit, Turn off                          |
| GRILL-PRINTER-01    | Printer          | Not sent | 192.168.1.52:9100 | 2 waiting  | Test print, Edit, Turn off                          |
| KITCHEN-PRINTER-01  | Printer          | Not sent | 192.168.1.51:9100 | 4 waiting  | Test print, Edit, Turn off                          |
| PASTRY-PRINTER-01   | Printer          | Not sent | 192.168.1.53:9100 | 3 waiting  | Test print, Edit, Turn off                          |
| PRINT-AGENT-01      | Print agent      | Not sent | not paired        |            | Enter code from device, Create code, Rename         |
| CUSTOMER-DISPLAY-01 | Customer display | Offline  | 9:16:39 PM        | paired     | Enter code from device, Create code, Rename, Revert |

**Add device**

Name (e.g. PASTRY-KDS-01) Type Station (KDS) Printer connected by

Printer IP address, or Windows printer name for USB Printer driven by agent Receipt printer (POS)

Add device

Print jobs not yet printed

Live

**Never** enter this code on a till's row. MY FOOD will refuse it, and nothing changes.

## 9 Printing is on. Find the printers.

The window says **Printing is on**. Press **Search the network** to see each printer's address. **Print test page** checks each printer.

**MY FOOD Printing**  
Chefelisha Restaurant

**Printing is on · PRINT-AGENT-01**  
Connected to MY FOOD · checked 09:20 PM. Keep this PC switched on during service.

| PRINTER            | CONNECTED BY | ADDRESS           | STATUS |
|--------------------|--------------|-------------------|--------|
| KITCHEN-PRINTER-01 | Network      |                   | Ready  |
| RECEIPT-PRINTER-01 | Network      | 192.168.1.51:9100 | Ready  |

**Find printers**  
Find the address of a network printer, or the name of a USB printer plugged into this PC, then enter it in MY FOOD → Devices & printing → Edit printer.


**Recent activity**  
Nothing yet.

Version 1.1.1 · <https://www.chefelisha.cc> [Disconnect this PC](#)

Printer address tip: hold the printer's FEED button while switching it on, and it prints its address.

# 10 Put each printer's address in MY FOOD

In **Devices & printing**, press **Edit** on each printer. Choose Network or USB, type the address, set **Printed by** to PRINT-AGENT-01, then **Save**.



An address ending in .1 (like 192.168.1.1) is usually the Wi-Fi router, not a printer.

# 11 Test print from MY FOOD

Press **Test print** on each printer's row. MY FOOD must say it **printed**.


**Chefellsha Restaurant (test)**  
Main

**OPERATIONS**  
 Dashboard  
 POS  
 Orders  
 Cash register  
 Customers  
 Kitchen  
 Supervisor  
 Customer display  
**INVENTORY**  
 Stock  
 Stock taking  
**MENU & SETUP**  
 Menu & recipes  
 Stations & routing  
 Floor & tables  
**Devices & printing**

|                            |                  |            |            |                   |                        |             |          |
|----------------------------|------------------|------------|------------|-------------------|------------------------|-------------|----------|
| <b>DRINKS-PRINTER-01</b>   | Printer          | ● Not sent | —          | 192.168.1.54:9100 | Test print             | Edit        | Turn off |
| <b>GRILL-PRINTER-01</b>    | Printer          | ● Not sent | —          | 192.168.1.52:9100 | Test print             | Edit        | Turn off |
| <b>KITCHEN-PRINTER-01</b>  | Printer          | ● Not sent | —          | 192.168.1.51:9100 | Test print             | Edit        | Turn off |
| <b>PASTRY-PRINTER-01</b>   | Printer          | ● Not sent | —          | 192.168.1.53:9100 | Test print             | Edit        | Turn off |
| <b>PASTRY-PRINTER-02</b>   | Printer          | ● Not sent | —          | 192.168.1.55:9100 | Test print             | Edit        | Turn off |
| <b>RECEIPT-PRINTER-01</b>  | Printer          | ● Not sent | —          | 192.168.1.60:9100 | Test print             | Edit        | Turn off |
| <b>PRINT-AGENT-01</b>      | Print agent      | ● Not sent | —          | not paired        | Enter code from device | Create code | Rename   |
| <b>CUSTOMER-DISPLAY-01</b> | Customer display | ● Offline  | 9:16:39 PM | paired            | Enter code from device | Create code | Rename   |

**Add device**  
 Name (e.g. PASTRY-KDS-01) Type Station (KDS) Printer connected by  
 — — —  
 Printer IP address, or Windows printer name for USB Printer driven by agent Receipt printer (POS)  
 — — **Add device**

**Print jobs not yet printed**
● Live

1 Test print: it must say "printed"

# 12 Kitchen printers: connect to their station

In **Stations & routing**, choose the **Station** (e.g. Main Kitchen), the **printer** and the role **Main**, then press **Connect screen or printer**.

**Chefellsha Restaurant (test)**  
Main

**OPERATIONS**

- Dashboard
- POS
- Orders
- Cash register
- Customers
- Kitchen
- Supervisor
- Customer display

**INVENTORY**

- Stock
- Stock taking

**MENU & SETUP**

- Menu & recipes
- Stations & routing**
- Floor & tables
- Devices & printing

| STATION      | CODE | SCREENS AND PRINTERS          |                      |
|--------------|------|-------------------------------|----------------------|
| Main Kitchen | KIT  | Printer: KITCHEN-PRINTER-01 ✗ | Screen: KITCHEN-01 ✗ |
| Grill        | GRL  | Printer: GRILL-PRINTER-01 ✗   | Screen: GRILL-01 ✗   |
| Pastry       | PAS  | Printer: PASTRY-PRINTER-01 ✗  | Screen: PASTRY-01 ✗  |
| Drinks       | DRK  | Printer: DRINKS-PRINTER-01 ✗  | Screen: DRINKS-01 ✗  |

Name  Code (e.g. GRL)  **Add station**

Station  Screen or printer  Role

**Connect screen or printer**

**Routing rules (product > category > default)**

|          |               | STATION      | PRIORITY |        |
|----------|---------------|--------------|----------|--------|
| product  | Birthday Cake | Pastry       | 0        | Delete |
| category | Drinks        | Drinks       | 0        | Delete |
| category | Pastries      | Pastry       | 0        | Delete |
| category | Food          | Main Kitchen | 0        | Delete |

**1 Connect the kitchen printer to its station**

# 13 Each till: choose its receipt printer

In **Devices & printing**, press **Edit** on each till, choose its **Receipt printer** and press **Save**.

**Chefellsha Restaurant (test)**  
Main

**OPERATIONS**

- Dashboard
- POS
- Orders
- Cash register
- Customers
- Kitchen
- Supervisor
- Customer display

**INVENTORY**

- Stock
- Stock taking

**MENU & SETUP**

- Menu & recipes
- Stations & routing
- Floor & tables
- Devices & printing**

**Devices & printing**

Tills, kitchen screens, customer display and printers. Hardware can be connected at any time.

**Device status (from heartbeats and printer reports)** ● Live

**Printing is not running yet.** A browser cannot send to receipt printers by itself: one PC in the restaurant runs **MY FOOD Printing** and prints for everyone.

- Open a Windows PC at the counter that stays on during service, download and install **MY FOOD Printing**.
- It will ask you for the IP address of the PC that runs MY FOOD Printing. Enter the IP address of the PC here with that address.
- In the MY FOOD Printing interface, click on the 'Printers' tab and add a new printer.

**Edit POS-01**

Name: POS-01

Receipt printer: RECEIPT-PRINTER-01

Receipts and bills from this till print here.

**1 Choose the till's receipt printer**

**2 Save**

| Device     | Type           | Status  | Time       | Action |
|------------|----------------|---------|------------|--------|
| AKOSUA-01  | Kitchen screen | Offline | 9:16:19 PM | paired |
| AMA-01     | Kitchen screen | Offline | 9:16:17 PM | paired |
| POS-01     | Kitchen screen | Offline | 9:16:21 PM | paired |
| DRINKS-01  | Kitchen screen | Offline | 9:16:19 PM | paired |
| GRILL-01   | Kitchen screen | Offline | 9:16:19 PM | paired |
| KITCHEN-01 | Kitchen screen | Offline | 9:16:17 PM | paired |
| PASTRY-01  | Kitchen screen | Offline | 9:16:21 PM | paired |

# 14 Same as the tills

On each kitchen screen and on the customer display, open **www.chefelisha.cc/pair**. Enter the code on **its own row** (KITCHEN-01, DRINKS-01, CUSTOMER-DISPLAY-01...). It opens its screen by itself.

**Chefelisha Restaurant (test) Main**

**OPERATIONS**

- Dashboard
- POS
- Orders
- Cash register
- Customers
- Kitchen
- Supervisor
- Customer display

**INVENTORY**

- Stock
- Stock taking

**MENU & SETUP**

- Menu & recipes
- Stations & routing
- Floor & tables
- Devices & printing

**Devices & printing**

Tills, kitchen screens, customer display and printers. Hardware can be connected at any time.

**Device status (from heartbeats and printer reports)** Live

**Printing is not running yet.** A browser cannot send to receipt printers by itself: one PC in the restaurant runs **MY FOOD Printing** and prints for everyone.

- On a Windows PC at the counter that stays on during service, download and install [MY FOOD Printing](#).
- It shows a code. Press **Enter code from device** on **PRINT-AGENT-01** and type it.
- In MY FOOD Printing, use "Search the network" to find each printer, then Edit the printer here with that address.

27 print jobs are waiting and will print as soon as printing runs.

| DEVICE              | TYPE             | STATUS   | LAST SEEN  | DETAILS |
|---------------------|------------------|----------|------------|---------|
| Akosua device 1     | POS till         | Not sent | —          | paired  |
| Ama device 1        | POS till         | Not sent | —          | paired  |
| POS-01              | POS till         | Offline  | 9:16:36 PM | paired  |
| DRINKS-01           | Kitchen screen   | Offline  | 9:16:38 PM | paired  |
| GRILL-01            | Kitchen screen   | Offline  | 9:16:19 PM | paired  |
| KITCHEN-01          | Kitchen screen   | Offline  | 9:16:17 PM | paired  |
| CUSTOMER-DISPLAY-01 | Customer display | Offline  | 9:16:21 PM | paired  |

**1 Kitchen screen: its own row**

**2 Same steps as the till**


# 15 Make a test order

On a till, sign in with a staff PIN → **Takeaway** → **+ New takeaway order** → tap a product → **Send to kitchen**. The kitchen screen shows it and the kitchen ticket prints.

The screenshot shows the 'New takeaway order' screen in the MY FOOD app. The top navigation bar includes 'Chefelisha Restaurant (test)', 'Hall', 'Takeaway', 'Bills', 'Completed', 'Customer screen', 'Open register', 'Orders', 'Kofi (Cashier) Browser till', 'PIN', and 'Sign out'. Below the navigation bar is a search bar and a grid of food items. The 'Jollof Rice' item is highlighted with a red box and a red arrow pointing to it from a red box labeled '1 Tap a product'. The 'Jollof Rice' item is priced at GHS 45.00. To the right of the grid is a 'New takeaway order' section with a 'Phone number' field, a 'Test' button, and a 'Jollof Rice' item with a quantity of 1 and a 'Note for the kitchen' field. At the bottom right, a red box labeled '2 Send to kitchen: the ticket must print' points to a red 'Send to kitchen' button. The bottom of the screen shows 'New Items (estimate)' for GHS 45.00.


# 16 Take payment

Press **Take payment** → **CASH** → type the money received → **Complete payment**.



# 17 Print the receipt

Press **Print receipt**. It prints on the till's receipt printer. Then restart every device once and check it still works.



## REMEMBER

# Pairing rules

### ✓ DO

- Enter a device's code on **that device's row**
- Use the code that is on the screen **now**
- Printing code → only **PRINT-AGENT-01**
- Wait up to 10 seconds after **Pair device**
- Read the message if a code is refused

### ✗ DON'T

- Don't keep pressing **Show a new code** or **Create code**
- Don't enter one device's code on another device's row
- Don't pair a device that already shows the PIN pad
- Don't send codes or PINs on WhatsApp

“**Create code**” is the other way round: that code is typed **on the device**, after pressing **I have a code from a manager**. You normally don't need it.

## Quick fixes

| You see                                               | Do this                                                                                                   |
|-------------------------------------------------------|-----------------------------------------------------------------------------------------------------------|
| "That pairing code has expired"                       | Use the new code the device shows now.                                                                    |
| "This code comes from MY FOOD Printing..."            | You used a till's row. Enter it on <b>PRINT-AGENT-01</b> .                                                |
| "That is a code created here in MY FOOD"              | Type it <b>on the device</b> ("I have a code from a manager").                                            |
| Red box on Devices & printing: "Printing has stopped" | Switch on the printing PC and check its internet. MY FOOD Printing must be running (icon near the clock). |
| Printer "Not reachable" / did not print               | Power, paper, cable. Search the network again and fix the address with <b>Edit</b> .                      |
| Ticket prints in the wrong place                      | <b>Stations &amp; routing</b> : check which printer is connected to that station.                         |
| Receipt shows on screen instead of printing           | Edit the till → choose its <b>Receipt printer</b> .                                                       |

**Still stuck?** Stop making new codes. Take a photo of the screen (no PINs) and call:

MY FOOD support: \_\_\_\_\_ Manager:  
\_\_\_\_\_