Monster Hunter Rise — Switch Axe (Slash Axe) Field Reference

Extracted via REFramework Object Explorer. Fields are read from the player object via snow.player.PlayerManager. Note: The Switch Axe is internally called 'Slash Axe' throughout the game files due to localisation differences between Japanese and Western releases. All timer values are in game ticks (not seconds). Static config fields are sourced from _PlayerUserDataSlashAxe.

Field Name	Sample Value	Category	Annotation
PHIAL / SWITCH GAUGE			
_BottleGauge	100	*Current phial/switch gauge value. This is the main resource consumed while in sword mode. Range: 0–100.*	Live — Phial Gauge
_BottleGaugeMax	100	*Maximum value of the phial gauge. Static config value, always 100 under normal conditions.*	Config — Phial Gauge
_BottelGaugeLow	37	*Threshold at which the gauge is considered 'low'. Note: typo in game files ('Bottel' not 'Bottle'). The gauge UI turns red below this value.*	Config — Phial Gauge
_BottleRecoverTime	300.0	*Total time (ticks) for the gauge to begin recovering after not being in sword mode.*	Config — Phial Gauge
_BottleRecoverValue	5	*Amount the gauge recovers per tick during recovery.*	Config — Phial Gauge
_BottleRecoverTimer	300.0	*Current countdown timer for gauge recovery. Counts down to 0 before recovery starts.*	Live — Phial Gauge
_BottleReduceTimer	300.0	*Timer tracking how long the gauge has been*	Live — Phial Gauge

		reducing while in sword mode.	
_NoUseSlashGaugeTime	0.0	*Time (ticks) required without using the slash gauge before recovery begins.*	Config — Phial Gauge
_NoUseSlashGaugeTimer	0.0	*Current timer tracking idle time since last gauge use. When this reaches _NoUseSlashGaugeTime, recovery starts.*	Live — Phial Gauge
<IsReduceBottheGauge>k__BackingField	false	*True when the phial gauge is actively being consumed (i.e. player is in sword mode and attacking). Note: typo in game files.*	Live — Phial Gauge
SWORD / AXE MODE			
GroupSlashAxe	true	*Master boolean for current weapon mode. true = Sword mode active, false = Axe mode. This is the primary mode indicator to use for UI.*	Live — Mode
ELEMENTAL BUILDUP — Two Arrows State			
_BottleAwakeAssistTimer	0.0 / 3600.0	*Tracks the elemental counter window (the two arrows in the vanilla UI). 0.0 = no arrows active. Jumps to 3600.0 when arrows appear and counts down. Use > 0 as boolean check for arrow state.*	Live — Elemental Buildup
_BottleElementValue	20.0	*Static config value related to elemental phial properties. Does NOT change with gameplay state — not useful as a live tracker.*	Config — Elemental Buildup

<IsHitElementStab>k__BackingField	false	*True when the player has successfully landed an elemental discharge (ZR+ZL finisher in sword mode).*	Live — Elemental Buildup
<IsEnableElementCounterEffect>k__BackingField	false	*Expected to track arrow state but observed to never flip during testing. May be unused or for a visual effect only.*	Live — Elemental Buildup
AMP STATE — Charged Sword (Blue Glow)			
_BottleAwakeGauge	0.0 / 70.0	*Core amp state indicator. 0.0 = not amped. Jumps to 70.0 when amp (blue glow) activates. Does NOT build up gradually — it is set directly on activation. Use > 0 as boolean check for amp state.*	Live — Amp State
_BottleAwakeDurationTimer	0.0 / 2700.0	*Countdown timer for amp duration. Starts at 2700.0 when amp activates and counts down to 0. Use this to draw a depletion bar for remaining amp time.*	Live — Amp State
_BottleAwakeDurationTime	2700.0	*Maximum duration of amp state in ticks. Static config value. Use as the max for the duration bar calculation: timer / 2700.0.*	Config — Amp State
_BottleAwakeReduceTimer	0.0	*Timer tracking amp gauge reduction rate. Likely internal pacing for how fast amp drains.*	Live — Amp State
_BottleAwakeGaugeReduceTime	300.0	*Time interval (ticks) between each amp gauge reduction tick.*	Config — Amp State

_BottleAwakeGaugeReduceValue	5.0	*Amount the amp gauge reduces per reduction tick.*	Config — Amp State
_BottleAwakeShellMaxCount	4	*Maximum number of amp shells (Amped Element Discharge charges). Corresponds to the shell count in the Wilds UI's Amped Charge display.*	Config — Amp State
SWING / STAMINA TRACKING			
<AxeSwingCount>k__BackingField	0 / 3	*Tracks axe swing count for stamina consumption purposes. Default resting value is 3. Increments by 2–3 per wild swing. Resets to 0 on sword mode entry. NOT related to elemental buildup or UI arrows.*	Live — Stamina
<IsSwingStaminaEmpty>k__BackingField	false	*True when the player has run out of stamina during axe swings.*	Live — Stamina
SILKBIND / WIRE ATTACKS			
<IsHitWireAttackSword>k__BackingField	false	*True when the player has landed a silkbind attack while in sword mode.*	Live — Silkbind
ELEMENT STAB (Internal Tracking)			
<ElementStabStickEmID>k__BackingField	-1	*Entity ID of the monster the element stab is stuck into. -1 = no active stab.*	Live — Element Stab
<ElementStabStickJointName>k__BackingField	nil	*Name of the monster joint the element stab is attached to.*	Live — Element Stab
<ElementStabStickConstAxist>k__BackingField	0	*Constraint axis for the element stab physics attachment.*	Live — Element Stab

<ElementStabStickConstState>k__BackingField	0	*State of the element stab constraint. 0 = inactive.*	Live — Element Stab
<IsElementStabStickFixPosture>k__BackingField	false	*Whether the element stab is currently fixing the player's posture during the stab animation.*	Live — Element Stab
MISC / MULTIPLAYER			
_SlaveBottleType	2	*Bottle type used in multiplayer slave/follower context. Likely determines phial type behaviour for AI partners.*	Config — Misc
_BottleAwakeAssistTimer	0.0	*See Elemental Buildup section. Listed again here as it also serves as an assist mechanic timer in multiplayer contexts.*	Live — Misc

UI Mapping Summary — Wilds-style HUD

Based on the Wilds UI reference image provided:

Wilds UI Element	Rise Field(s)	Implementation Notes
Switch Gauge	_BottleGauge	Draw as bar: _BottleGauge / 100. Turn red when value < _BottelGaugeLow (37).
Power Axe (mode indicator)	GroupSlashAxe	true = Sword mode active. false = Axe mode. Use to highlight the active mode in the UI.
Reload Limit (two arrows)	_BottleAwakeAssistTimer	Active when > 0. Max value is 3600.0. Draw as countdown bar: _BottleAwakeAssistTimer / 3600.0.
Amped Charge (blue glow)	_BottleAwakeGauge _BottleAwakeDurationTimer	Active when _BottleAwakeGauge > 0. Draw duration bar as _BottleAwakeDurationTimer / 2700.0. Max shells = _BottleAwakeShellMaxCount (4).

Generated during REFramework modding session. Fields extracted from snow.player.PlayerManager → PlayerList → PlayerQuestBase.