ATMAS-II

MANUAL

DRAFT, NOVEMBER 14, 2018.

ATMAS-II Manual

A Macro-assembler, editor and machine language monitor for the ATARI 400/600XL/800/800XL and ATARI 130XE with a diskdrive and at least 48kB RAM

The ATMAS-II program, disk and manual are copyright by

 $\operatorname{Ing.}$ W. Hofacker GmbH and Dipl.-Ing. Peter Finzel

All rights reserved, 1985

Scanned, OCR'd, typeset in LATEX $2\varepsilon {\rm and}$ translated from German to English by Ivo van Poorten, 2011

LOAD INSTRUCTIONS


- Remove any cartridge from the cartridge slot of your ATARI Computer.
- Turn on the diskdrive and monitor.
- Once the red LED of the disk drive is off, insert the disc with the inscription at the top; the oval cut enters the drive first. Close the door of the diskdrive.
- Then turn your ATARI computer. On XL models you have to hold the [OPTION] key while swithing on the computer.
- ATMAS-II is now loading. After a short time the opening credits appear and then the editor. The loading process is complete.

If the message 'ATMAS-II benötigt 48K-Speicher' (ATMAS-II needs 48K Memory) appears, there are several options:

- a There's still a cartridge in the cartridge slot.
- b The OPTION key is not pressed (XL models only).
- c Your computer does not have enough memory. ATMAS-II needs at least $48\mathrm{kByte}$.

DEMO PROGRAM HOWTO

If you want to view a short demo program of the ATMAS-II system before you read the manual, you can achieve this by following the instructions below:



Note: [ESC] means you have to press the ESC-key. [CTRL-Y] means you have to hold the CTRL-key while you press the Y-key.

Contents

Co	onten	ts		5
1	The	editor	c	9
	1.1	Using	the editor	9
		1.1.1	The status bar	9
		1.1.2	Text window	10
		1.1.3	Command line	10
	1.2	Text in	nput	10
	1.3		ommands in text mode	10
		1.3.1	Cursor movement	11
		1.3.2	Deleting characters	11
		1.3.3	Deleting lines	11
		1.3.4	Cursor jumps	11
		1.3.5	Tabulator	11
		1.3.6	Copy-Register (C-Register)	12
		1.3.7	Special commands for the editor	12
		1.3.8	Calling the assembler and the monitor	12
	1.4	Comm	ands on the command line	13
		1.4.1	Using the command line	13
		1.4.2	Edit functions on the command line	13
		1.4.3	More editing commands	13
		1.4.4	Special functions	14
		1.4.5	Commands for in-/output of text	14
		1.4.6	Listings	15
		1.4.7	Notes on advanced editor use	15
2	The	macro	o assembler	17
	2.1	Using	the macro assembler	17
	2.2	_	format of the assembler	17
		2.2.1	Addressing modes	18
		2.2.2	Labels	18
		2.2.3	Konstante	19
		2.2.4	Negative Konstante	19
		2.2.5	Interner Adresszähler	19
		2.2.6	Ausdruck	20
	2.3	Assem	bler-Direktiven	20
	-	2.3.1	ORG	20
		2.3.2	EQU. EPZ (Equates)	21

	2.4	2.3.3 DFB (Define Byte) 2.3.4 DFW (Define Word) 2.3.5 ASC (ASCII-String) 2.3.6 OUT (Output Listing) Mahrofähigkeit 2.4.1 Makro-Definition 2.4.2 Makroaufruf, Makroexpansion 2.4.3 Lokale Labels 2.4.4 Verschachtelte Makros 2.4.5 Makros contra Unterprogramme
3	Der	Maschinensprache-Monitor
•	3.1	Allgemeine Benutzungshinweise
	3.2	Befehlsvorat des Monitors
		3.2.1 M - Memory-Dump
		3.2.2 D - Disassemble
		3.2.3 C - Change Memory
		3.2.4 F - Fill Memory
		3.2.5 B - Blocktransfer
		3.2.6 G - Goto Address
		3.2.7 S - Binary Save
		3.2.8 L - Binary Load
		3.2.9 E - Editor
		3.2.10 I - Disketteninhaltsverzeichnis
4	Exa	mples
	4.1	Demo program, color scrolling
	4.2	Macro libraries
A	ATMA	S-II Memory Map
В	Erro	or codes
	B.1	Assembler errors
	B.2	Editor errors
	B.3	Monitor error codes
\mathbf{C}	ATMA	S-II REFERENCE CARD

Introduction

ATMAS-II is a powerful development system for assembly programs on your Atari computer. ATMAS-II consists of three integrated subsystems: an editor, a macro assembler and a machine language monitor. These components together provide a convenient and fast low level assembly program development.

All three parts of this programming environment are tightly integrated and only a keystroke away from each other. A user-friendly, screen-based editor with features such as a copy register, repeatable command sequences and space-saving real tabs, facilitate the entry of large programs. The macro assembler is able to achieve the shortest possible assembling time by using modern hashing algorithms such that longer programs are assembled in only a few seconds. Finally, there's a built-in monitor for testing programs.

Although someone who has never programmed in assembly will quickly feel familiar with ATMAS-II , it also offers many features for advanced users, such as the powerful editor functions and the macro programming commands.

It should be noted that this manual is not a textbook for learning 6502-machine language. I refer to other books on the subject, particularly to a book appearing in the fall of '85 by the author of this manual that is tailored specifically to the Atari computer. In addition, the examples in chapter 4 of this manual show a little insight into the assembly language programming of the Atari computer.

CHAPTER 1

The editor

The ATMAS-II editor is a screen oriented editor that works without any line numbers. It essentially behaves like a word processor. This eliminates the tedious entry of LIST commands such as is used by several other editors (e.g. in BASIC). You can easily move through the listing by using the cursor keys, which then scrolls from top to bottom or from bottom to top.

1.1 Using the editor

Once ATMAS-II has been loaded from the floppy disk, you go directly into the editor, which is also sort of the Control Center of the ATMAS-II system. From here you can call the macro assembler and the machine language monitor. The RESET key will always bring you back to the editor.

After booting, you will see the following screen:

	+		+		
	I P:000	000 T:17408 C:1	1024 OK I <-	Status 1	bar
	+		+		
Cursor -	>I C		I		
	I		I		
	I	Textwindow	I		
	I		I		
	I		I		
	+		+		
	I			Command	line
	+		+		

1.1.1 The status bar

The status bar will continuously inform you about the cursor position, free memory, the copy register and the state of the editor.

'P:nnnnn' tells you the distance (in characters) of the cursor from the beginning of the text to the current position, 'T:xxxxx' provide you with information

on free memory, (i.e. you can still enter 'xxxxx' characters). 'C:yyyy' offers information on the free space of the copy register (the so-called C-register) which consists of 1024 characters when it is empty. The last two characters in the status bar display a status message from the editor. If everything is fine, you'll find 'OK' displayed there. Any error or status messages (e.g. if the copy register is open) is shown here. A list of possible messages can be found in Appendix B.

1.1.2 Text window

The next 21 lines are the text window, where you always see the current text, which you can edit with the editing functions discussed in the following sections. In the truest sense of the word, this screen must be understood as a window into the text, which can be moved up and down over the text with e.g. the cursor keys. All editing is immediately visible in the text window.

1.1.3 Command line

The last line of the screen is reserved for entering commands. Besides a number of direct commands that are given directly in the text window, there is also another command mode of the editor, which is activated by pressing the key. Here you enter commands that require additional information, such as a word to look for. Commands for loading and saving of text can be entered here, too.

1.2 Text input

You can immediately start entering text, without any line numbers. Each character is stored at the current cursor position and the cursor moves right one position. You can always start a new line by pressing RETURN. If you enter more than 38 characters in a row, the cursor disappears from the right side of the screen similar to pressing the RETURN key and appears at the beginning of the next line again. This behavior seems unusual at first glance, but you will soon find that in assembly language programs this is quite an advantage. The essential part of an assembler program is always in the first 30 characters, because the assembler instruction is there. When you want to edit long lines (e.g. comments), there is a special function available (CTRL-V), see section XXXXXX on special features), giving you a maximum of 76 characters on two lines of the screen. You will notice, however, that the normal 38-character screen is much better for editing assembly programs, because all assembly instructions, contrary to the two-line mode, will not be interrupted by blank lines between them.

As usual, all the keys have the auto-repeat function. Lower case can be achieved with the **CAPS** key.

1.3 Edit commands in text mode

As mentioned above, the ATMAS-II editor offers two different levels of command input. The simpler of the two are the so-called direct commands, also

called commands in text mode. These commands are executed either by special keys, for example [BACKSPACE], or control functions. The latter simply means that the [CTRL] key (For 600/8OOXL: [CONTROL]) has to be hold down while you press another key, similar to how you move the cursor in ATARI BASIC. If you read the following: [CTRL-X], it means that you are holding down [CTRL] while pressing the X key.

1.3.1 Cursor movement

In text mode, you have the following cursor functions:

To move the cursor right, press $[CTRL-\rightarrow]$.

A cursor movement to the left is done with [CTRL--]. When you get to the right end of a line, the cursor is moved to the beginning of the next line. Go beyond the left end, and the cursor is moved to the end of the previous line.

To move the cursor up, press [CTRL-↑]. The cursor is, if it is not already there, moved to the left margin. If that is this case, it is the second key press that moves one line up.

The cursor can be moved to the line below to the beginning of the next line by pressing [CTRL-1]. With all cursor movements, you can not go beyond the beginning and end of the text. Unlike other editors, you will notice that the cursor is not on the text, but is inserted. This has the advantage that you always know exactly where the text will be inserted.

1.3.2 Deleting characters

To delete a character left of the cursor, press [BACKSPACE]. When the cursor is at the beginning of the line, the return character is deleted, i.e. the line where the cursor was is appended to the previous one. If this was a blank line and consisted solely of a return character, the blank line is deleted.

To delete a character right of the cursor, press [CTRL-BACKSPACE]. Just like the above case, the next line can be appended to the current line. If this is a blank line, it is deleted.

1.3.3 Deleting lines

If you want to delete a line, you can press [CTRL-X]. All characters from the current cursor position till the end of the line will be deleted. If the cursor is at the beginning of a line, the whole line will be deleted.

1.3.4 Cursor jumps

[CTRL-E] brings you to the beginning of the text. [CTRL-D] brings you to the end of the text.

1.3.5 Tabulator

The ATMAS-Editor has a real Tabulator that moves the cursor between 1 and 9 spaces, but internally only occupies 1 character. To reach the next tabulated point, simply press [TAB].

If you later move your cursor around a tab location, you will notice that the cursor jumps and inserts before a tab do not move the text after it. The tab is stored as a single character, hence you can use it to create readable listings without wasting memory space.

1.3.6 Copy-Register (C-Register)

The C-Register is a secondary text buffer which has a size of 1024 characters. You can use it to move or copy parts of your text. First, position the cursor at the end of the block you want to transfer and open the C-Register by pressing [CTRLR].

At the left of the status bar, this mode is denoted with 'CR'. If you move the cursor backwards, the text you walk-over will be copied to the C-Register buffer. You can follow its progress. The number of free characters in the C-Register ('C:1024')decreases with every cursor movement.

When you're finished, you can close the C-Register by pressing [CTRL-F].

Now you can paste the contents of the Copy-Register wherever you want by pressing [CTRL-J]. The contents of the Copy-Register are preserved, so you can make multiple copies of the same text. To clear the Copy-Register, press [CTRL-K]. The C-Register is also cleared if you run the assembler or any I/O takes place.

Moving, instead of copying, a block of text can be done by filling the C-Register buffer using [BACKSPACE] or [CTRL-X] instead of [CTRL-7] or [CTRL-4]. The deleted text now resides in the C-Register an can be inserted at another location.

You can also combine several pieces of text by reopening and closing the C-Register without clearing it in between with [CTRL-K].

When the C-Register is full ('C:0000'), the error message 'C?' will appear at the left side.

1.3.7 Special commands for the editor

You can switch to two-line mode by pressing [CTRL-V]. In this mode, lines that are longer than 38 characters are displayed on two lines. The maximum line length is increased to 76 character, but the number of lines displayed is decreased to 11. Pressing [CTRL-V] again brings you back to single-line mode.

Control characters, especially tabs and end-of-line characters, can be made visible by pressing [CTRL-T] . All control characters are shown in inverse video. Pressing [CTRL-T] again brings back the normal mode.

[CTRL-G] repeats the command present on the command line. See section 1.4 for more information.

1.3.8 Calling the assembler and the monitor

The ATMAS-II macro assembler is called by pressing [CTRL-Y]. Immediately, ATMAS-II begins assembling the source code that resides in the text buffer. When it is finished, you can return to the editor by pressing a key.

The machine code monitor can be called by pressing [CTRL-P]. 'MONITOR.' is shown and it awaits your input (see section 3). Returning to the editor can be accomplished by inputting 'E'.

1.4 Commands on the command line

In addition to the direct commands in text mode, the ATMAS-II editor has another powerful editing mode! The command line. You will find primarily commands here that need more information than the actual call of the command, such as a character string to be searched for. You will also find some commands that you know from the text mode here, but these can be provided with repetition factors and chained. A sort of 'command macros'.

1.4.1 Using the command line

You enter the command mode by pressing the sex, which is represented as a dollar sign. Now you can enter individual commands while using the sex as a delimiter. The command line is executed when you press twice. The execution is acknowledged with a double cross behind the chain of commands, you then move back to text mode. If the command line has proven to be faulty, you will be told so in the upper left corner by an error symbol.

All commands (except the I/O commands R and W) can be performed repeatedly by preceding it with a repetition factor between 2 and 255. In addition, a single repetition of a complete command line can be done by pressing [CTRL-G] from the text mode.

Errors in the command line itself can be corrected with [BACKSPACE]. [CTRL-X] will delete the command line and return to text mode.

1.4.2 Edit functions on the command line

- B Cursor one position backwards
- F Cursor one position forwards
- D delete one character left from the cursor
- T delete from cursor position until the end of the line

With these commands, for example, rapid cursor movement in the text is possible. Open the command line with <code>ESC</code> and type '200F' followed by pressing <code>ESC</code> twice. Each repetition of the command line with <code>CTRL-G</code> will bring you 200 characters further in the text buffer.

1.4.3 More editing commands

H<HexByte> Insert any ATASCII-code in the text, e.g. for printer control. EXAMPLE: \$H0F\$ switches an EPSON printer to condensed
 S<String> Search string from current position to the end of the text. If it's not found, 'S?' will appear in the status bar. EXAMPLE: \$SLABEL\$ searches for LABEL.
 !<String> Inserts string < String> at the current cursor position. Can be used as a search and replace function (see below) in conjunction with the S command.

1.4.4 Special functions

- J Repeat the complete command line. Can, for example, be used for global search and replace.
- K Clears the entire text buffer. CAUTION: All entered text will be deleted!
- U USER Command. Call a machine code program located at \$A800 with the JSR instruction. CAUTION: be sure there's an actual program at that location.
- @<n> Set the tab-width to <n> characters. If none is specified, it is set to 8. EXAMPLE: \$@6\$: set tab-width to 6 characters.
- M Return to DOS. You can return to ATMAS-II with 'B * ATMAS-II *' from the DOS menu.

Two more commands that affect the C register:

- E Clear the C-Register (like CTRL-K)
- G Insert C-Register contents in the text (like [CTRL-J])

1.4.5 Commands for in-/output of text

If you want to save a text present in the text buffer to disk, you can do this with the 'W'-command. You only need to specify the desired name of the file preceded by a device name.


EXAMPLE: If you want to safe the text as TEST. SRC on drive 1, you enter:

The extension .SRC is appended automatically. You can also specify a different extension manually, like WD1:TEST.ATM

CAUTION: The text will be saved starting at the *current cursor position*. Hence, if you want to save the full text, you need to press [CTRLE] first.

In a similar way, you can load a text file from disk to memory. For this, the command 'R' is used, which is used like 'W'.

EXAMPLE: To load the demo file DEMO.SRC of the ATMAS-II diskette (in drive 1):



The extension .SRC will again be appended automatically. The file is then loaded starting at the current cursor position. This gives two possibilities:

- 1. When a new file is to be loaded, then delete the previous text buffer in advance with $\lceil ESC \rceil$ $\lceil ESC \rceil$ $\lceil ESC \rceil$.
- 2. You can also insert individual files in the text buffer (similar to the copy register) by bringing the cursor to the desired position and then execute the load command.

If an error occurs during an I/O command, this is displayed in the status line with the text 'RW'.

1.4.6 Listings

Printouts of the source code can be made with the 'L' command. There are several options:

- L Listing scrolls across the screen
- L0 Output to RS232 Interface # 1 of the 850 interface modules (R1:)
- L1 Output is via the normal Printer-handler 'P:', that is usually on the Atari 850 interface module, too.
- L7 Listing is output via the Centronics interface on the joystick ports 3 and 4. This option is available only for the Atari 400/800 computer.

1.4.7 Notes on advanced editor use

The possibility of command chaining at the command line allows very convenient editing features:

\$SLDA\$3D\$ILDX\$J\$ ESC

This chain of commands will exchange all LDA commands from the cursor position to LDX commands. How does it work? First, an LDA instruction is sought (\$SLDA). After that, the cursor can then be thought to be positioned behind the string searched for. '\$3D' now deletes three characters to the left of the cursor (remember the repetition factor!), while '\$ILDX' inserts the string 'LDX'.

' texttt \$J' in turn causes the entire command line to be executed until the text is finished, or a 'S?' error (String not found) occurs.

The macro assembler

2.1 Using the macro assembler

From within the editor the ATMAS-II macro assembler is invoked with [CTRL-Y]. It then immediately begins assembling the source code, which must reside in the text buffer of the editor.

The assembly is divided into three passes. The second pass indicates its activity by a rapidly changing character in the upper left corner of the screen. The third pass is a listing of the assembled program on the printer or the screen output (see OUT-directive).

The process of assembling is continued until either the end of the source text has been reached, a Ctrl-Z character is detected (assembler stop character) or an error has been detected. In the last case, an error message (see Appendix B) is displayed on the screen. Any key will take you back to the editor, exactly at the place that caused the error. You can immediately improve the error and restart the assembler with CTRL-Y.

This comfortable 'hand-in-hand' work between editor and assembler is a key point that makes ATMAS-II so powerful as a development system for machine language programs, and yet it makes the operation easy.

2.2 Input format of the assembler

The ATMAS-II macro assembler knows all the opcodes of the 6502 CPU as far as they are described in the 'MOS Technology 6502 Programming Guide'. Similarly, the notation of the addressing modes follows what is proposed in that book (see below).

A line of code can have the following formats:

- a) Blank line: Consists only of a **RETURN** character.
- b) Comment line: Starts with a 'texttt *' in the first column. Example:
 - * Copyright (c) M. Huber

c) Command line with label: Starts with a label followed by a delimiter (space or tab), then a 6502 opcode or assembler directive, and finally, after a further delimiter, it can be followed by a comment.

Example:

```
LOOP LDA #$10
DOSVEC EQU $000C DOS-VECTOR
```

d) Command Line: Must always start with a delimiter. To get clean Listings it is recommended to have these begin with a tab. This is followed by a 6502 opcode or assembler directive. As in the previous case, a comment can be here after another delimiter.

Example:

```
STA COLORO CHANGE COLOR DFB 100,120,140
```

2.2.1 Addressing modes

Im folgenden eine kurze Zusammeniassung der Schreibweisen der einzelnen Adresslerungsarten, jeweils mit einem Beispiel versehen:

Implied Akku	$<\!\!Opcode\!\!>$	ASL
Immediate	$<\!\!Opcode\!\!>$ # $<\!\!Ausdruck\!\!>$	LDA #\$FF
Absolut, Zeropage	$<\!\!Opcode\!\!> <\!\!Ausdruck\!\!>$	STA \$600
Relativ	$<\!\!Opcode\!\!> <\!\!Ausdruck\!\!>$	BNE *+4
Absolut X-indiziert	$<\!\!Opcode\!\!><\!\!Ausdruck\!\!>$, X	CMP \$3000,X
Absolut Y-indiziert	$<\!\!Opcode\!\!><\!\!Ausdruck\!\!>$, Y	LDA TABLE,Y
Indirekt-indiziert	$<\!\!Opcode\!\!>$ ($<\!\!Ausdruck\!\!>$),Y	EOR (\$FO),Y
Indiziert-indirekt	$<\!\!Opcode\!\!> (<\!\!Ausdruck\!\!> , X)$	STA (\$FO,X)

Wie schon erwähnt, ist vor jedem $<\!Opcode\!>$ ein Label möglich, nach jedem Assemblerbefehl kann ein Kommentar stehen, der mit einem Trennzeichen abgesetzt ist.

AUSNAHME: Nach implied-Akku Befehlen muß das Kommentarfeld durch einen Strichpunkt abgetrennt sein.

2.2.2 Labels

Labels oestehen aus Buchstaben und Zahlen, wobei das erste Zeichen immer ein Buchstabe sein muß. Die maximale Länge beträgt 8 Zeichen, wobei alle Zeichen signifikant sind.

Gültige Labels	Ungültige Labels
SCHLEIF	1L00P
SCHLEIF1	SCHLEIFEN (9 Buchstaben!)
S12345	

2.2.3 Konstante

ATMAS-II kennt vier Arten von Konstanten: Dezimal-, Hexadezimal-, Binärund Zeichen-Konstante.

a) Dezimale Konstante

Bestehen einfach aus der Zahl selbst (im Bereich 0 bis 65535).

Beispiele: 10, 100, 3000, 65535

b) Hexadezimale Konstante

Bestehen aus einem Dollar-Zeichen (' * ') und gültigen Hexadezimalziffern (0-9,A-F).

Beispiele: \$10, \$FF, \$AB00, \$FFFF

c) Binare Konstante

Bestehen aus einem Prozent-Symbol mit nachfolgenden gültigen Binärziffern (0,1).

Beispiele: %1, %1001, %11110000

d) Zeichen-Konstante

Werden aus einem Apostroph mit nachfolgenden ASCII (bzw. ATASCII)-Zeichen gebildet. Die Zeichen werden in 7-Bit-Werte umgewandelt (Bit 7 immer Null).

Beispiele: 'X, '#, 'e, '"

2.2.4 Negative Konstante

Alle Vonstanten können durch ein vorangestelltes Minus-Zeichen als negative Zahlen interpretiert werden. Die Darstellung erfolgt im Zweierkomplement (-1=\$FFFF).

Beispiele: -1, -\$100, -%101101, -'B'

2.2.5 Interner Adresszähler

ATMAS-II führt während der Assemblierung einen internen Adresszähler mit, der jeweils auf den Upcode. der gerade übersetzten Anweisung zeigt (bzw. auf das nächste freie Byte nach dem zuletzt berechneten Ausdruck in DFB/DFW Direktiven). Dieser interne Adresszähler kann jederzeit durch das '*-Symbol abgerufen werden. Dies kann in vielfältigen Weisen benutzt werden:

- a Speicherplatz reservieren: ORG *+\$100 reserviert 256 Bytes
- b relative Sprünge ohne Label: BNE *+4 überspringt die nächsten 4 Bytes
- c Adressversetzte Labels für Software-Stackinq RETADR EQU *-1 momentane Adresse minus 1

2.2.6 Ausdruck

Ein Ausdruck kann eine Konstante, ein Label, ein Makroparameter (siehe 2.4), der momentane Adress-Zähler ('*') oder eine arithmetische Verknüpfung derselben sein. Zugelassene Verknüpfungen sind: +, -, *, /, der Rechenbereich beträgt O-65535. Einige Beispiele dazu:

LDA #\$FF Konstante
LDA #LABEL1 Label
STA LABEL+\$A0 Verknüpfung
LDA *+\$10 momentaner Adr.-Zähler+Offset

Zusätzlich sind auch Klammern zur Klärung der Priori- tät möglich:

```
LDA #($A0+5)/10
LDA #LAB1-(Lab1/256)*256
```

2.3 Assembler-Direktiven

2.3.1 ORG

Zweck: bestimmt den Inhalt des assemblerinternen Adress-

Zählers.

Syntax: $[\langle label \rangle]$ ORG $\langle AL \rangle[,\langle AP \rangle]$ $[\langle kom \rangle]$

Beispiel: ORG \$A800

ORG bestimmt die Anfangsadresse des Dbjektprogrammes, im obigen Beispiel ist der für diese Zwecke reser- vierte Speicherbereich ab \$ABOO gewählt. In manchen Fällen ist es aber nicht möglich, das Objekiprogramm direkt in den gewünschten Speicher- bereich zu legen, wenn dieser 2.8. von ATMAS-II belegt wird (s. Memory-Map im Anhang!). Hierzu können Sie den zweiten Parameter der ORG-Direktive verwenden, die sogenannte 'physikalische Adresse' $\langle AP \rangle$.

ORG \$3000,\$A800

Dieser ORG-Befehl würde ein Programm so assemblieren, daß es an der Adresse \$3000 (logische Adresse, $<\!AL>$) lauffähig ist, während der Assemblierung aber im freien Speicherbereich ab der Adresse \$4800 abgelegt wird. Damit das Programm ausgeführt werden kann, muß es an die richtige Stelle verschoben werden, das kann 2.8. mit dem SAVE-Befehl des Monitors geschehen, der ein Binärfile so abspeichern kann, daß es beim erneu- ten Einlesen an den richtigen Speicherplatz kommt. In einfacheren Fällen (2.8. wenn das Programm in dem Adressbereich abgelegt werden soll, in dem ATMAS-II seine Symboltabelle hat) hilft auch der Blocktransfer-Befehl des Monitors.

2.3.2 EQU, EPZ (Equates)

Zweck: Zuordnung eines Wertes zu einem Label.

Syntax: $\langle label \rangle$ EQU $\langle ausdruck \rangle$ [$\langle kom \rangle$]

< label> EPZ < ausdruck> [< kom>]

Beispiel: GRUEN EQU \$A0

CIOV EQU \$E456 SAVHSC EPZ \$58

PLAYER EQU PHBASE+1024

Die EQU-Direktive wird benutzt, um einen Label mit einem bestimmten Wert zu definieren, es kann sich dabei sowohl um ein Datum oder eine Adresse handeln. Der erste Label des Beispieles wird z.B. sicher als Datum für einen immediate-Befehl verwendet werden (LDA #GRUEN), während das zweite Beispiel eine ROM-Ein-sprungadresse bezeichent (JSR CIOV).

EPZ (Equate Page Zero) hat prinzipiell die gleiche Funktion, kann aber verwendet werden, wenn zum Ausdruck gebracht werden soll, daß der Label einen Zeropage-Speicherplatz darstellt. Es besteht aber kein Zwang zur Verwendung von EPZ, da ATMAS-II Zeropage-Adresslerungsarten selbsttätig erkennt. EPZ dient hierbei nur der Verdeutlichung, Sie können in allen Fällen auch EQU verwenden.

2.3.3 DFB (Define Byte)

Zweck: definiert den Inhalt einzelner Bytes im Objectcode

Syntax: $[\langle label \rangle]$ DFB]fooausdruck $[\langle ausdruck \rangle]$ $[\langle kom \rangle]$

Beispiel: TABELL DFB 1,2,4,8,16,32,64,128

DFB 'A, 'B, 'C DFB 'X+128

Die nach DFB folgenden Ausdrücke werden als 8-Bit werte in den Objektcode abgelegt. Die erste Zeile des Beispieles würde folgende Sequenz erzeugen:

01 02 04 08 10 20 40 80

ATASCII werte werden als 7-Bit Nerte abgelegt, das höchstwertige Bit ist immer Null.

2.3.4 DFW (Define Word)

Zweck: definiert den Inhalt eines 16-Bit Wortes im Objektcode.

 $Syntax: \quad [< label>] \ DFW \ < ausdruck>[, < ausdruck>...][\ < kom>]$

Beispiel: ADRTAB DFW \$A900,\$AA03,\$AB06

DFW ADRTAB-1, ADRTAB+2

Die nach DFW foldenden Ausdrücke werden als 16-Bit Werte im Objektcode abgelegt. Dabei wird die Reihen- folge der 6502-Adressen benutzt, d.h. zuerst das niederwertige (LSB), dann das höherwertige Byte (MSB). Die erste Zeile des Beispiels würde demnach folgendes erzeugen:

00 A9 03 AA 06 AB

2.3.5 ASC (ASCII-String)

Zweck: fügt einen String in ATASCII- oder Bildschirmcodierung

in den Objektcode ein.

Syntax: $[\langle label \rangle]$ ASC $\langle STZ \rangle \langle string \rangle \langle STZ \rangle [, \langle STZ \rangle \langle$

string><STZ>][<kom>]

Beispiel: TEXT ASC "HALLO"

MELD ASC /DISK-FEHLER/ ASC /MAKRO/,\ASSEMBLER\

ASC Z Normaler Bildschirmcode Z ASC S Inverser Bildschirmcode S

Strings nach einer ASC-Direktive werden Byte für Byte in den Objektcode übertragen. Abhängig vom Trennzeichen ($\langle STZ \rangle$) können verschiedene Funktionen angewählt werden:

- " Text im ATASCII-Code eintragen
- / ATASCII-Code, aber Bit 7=1 (Invers)
- \ ATASCII-Code, beim letzten Zeichen wird Bit 7 gesetzt (Ende-Kennung)
- % interner Bildschirmcode wird generiert
- \$ Bildschirmcode mit Bit 7=1 (Invers)

Jeder String muß von zwei gültigen String-Trennzeichen umschlossen werden. Anfangs- und Endtrennzeichen müssen gleich sein.

Statt dem Anführungszeichen " (SHIFT-2) können Sie auch ein beliebiges anderes nicht alphanumerisches Zeichen benutzen, die oben genannten natürlich ausgeschlossen. Denkbar wären hier z. B. !, #, oder &, Bedingung ist lediglich, daß der String mit dem gleichen Trennzeichen abgeschlossen wird. Mit diesem Trick ist es möglich, daß Sie ein Anführungszeichen in den Text bekommen.

In Verbindung mit dem Displaylistkonzept der Atari- Computer gestattet Ihnen der ASC-Befehl die komfortable Programmierung von Titeln und Uberschriften, da direkter Bildschirmcode erzeugt werden kann. Das Beispielprogramm ASCDEMO.SRC auf der ATMAS-II Diskette zeigt Ihnen, wie's gemacht wird.

2.3.6 OUT (Output Listing)

Zweck: Ausgabe eines Assembler-Listings

Syntax: $[\langle label \rangle]$ OUT $[L][N][M][P0][P1][P2][\langle kom \rangle]$

Beispiel: OUT L

OUT LP1
OUT LNMP1

Mit OUT können Sie bestimmen, ob Sie ein Protokoll des Assembliervorganges haben möchten und das zugehörige Ausgabegerät festlegen. Folgende Parameter werden erkannt:

- L Listing wird erzeugt
- N Symboltabelle wird ausgegeben
- M Makros werden NICHT expandiert (ausgedruckt!)
- PO RS232 Schnittstelle
- P1 Atari-Drucker, Centonics-Schnittstelle (850)
- P2 Joystick-Interface Port 3 und 4 (nur 400/800)

Nach jeweils 66 Zeilen wird ein Seitenvorschub generiert.

2.4 Mahrofähigkeit

ATMAS-II gestattet Ihnen die Verwendung von Makrobefehlen. Darunter versteht man eine Folge von Assemblerbefehlen, denen im Rahmen einer Makrodefinition ein Name zugeordnet wurde. Bei der Verwendung dieses Makro-Namens im Quelltext werden die gesamten, ihm zugeordneten Assemblerbefehle erzeugt, man sagt, der Makro-Befehl wird expandiert. Mit Hilfe von Makros können Sie sich eine Art von zusätzlichen Assemblerbe- fehlen schaffen, die in Wirklichkeit aus einer Sequenz von einzelnen Maschinenbefehlen bestehen.

2.4.1 Makro-Definition

Bevor Sie ein Makro verwenden können, müssen Sie es zuerst definieren. Zu diesem Zweck dienen die zwei Assembler-Direktiven MACRO und MEND.

Zum besseren Verständnis zuerst ein Beispiel, das den Basic-Befehl POKE imitiert:

POKE MACRO ADRESS, DATA

LDA #DATA STA ADRESS MEND

Die Definition wird von der MACRO-Direktive mit voranstehendem Namen des Makros (hier: POKE) eingeleitet. Dieser Name wird später zum Aufruf

verwendet. Nach der MACRO-Direktive folgen die sogenannten formalen Parameter, das sind keine Labels im eigentlichen Sinn, sondern nur Platzhalter für die beim Aufruf angegebenen tatsächlich einzusetzenden Parameter. Dieser Vorgang der Parametersubstitution wird bei der Besprechung des Makro-Aufrufes noch genauer erläutert.

Jetzt folgen die Assemblerbefehle, die als Operanten sowohl gewöhnliche Labels als auch die in der MACRO-Direktive angegebenen formalen Parameter benutzen können. Abgeschlossen wird die Makro-Definition durch die MEND (Makro-Ende)-Direktive

```
 \begin{array}{lll} \text{Syntax:} & <\!\!Makroname\!\!> \texttt{MACRO}\;[<\!\!param\!\!>][,<\!\!param\!\!>\dots] \\ & \dots \\ & & \texttt{MEND} \\ \end{array}
```

2.4.2 Makroaufruf, Makroexpansion

Das in 2.4.1 definierte Makro kann im Quelltext mit

```
POKE 752,1
```

aufgerufen werden. Bei der Assemblierung findet dann folgendes statt: AT-MAS-II erkennt, daß es sich bei POKE um ein bereits definiertes Makro handelt und fügt die Maschinenbefehle der Definition in den Objektcode ein. Dabei werden die formalen Parameter der Definition mit den tatsächlichen Werten des Aufrufes ersetzt. Im Beispiel wird folglich ADRESS durch 752, und DATA durch 1 ersetzt. Nach der Makroexpansion ergibt sich folgendes Maschinenprogramm:

```
LDA #1
STA 752
```

Die allgemeine Syntax für den Makroaufruf lautet:

```
[\langle label \rangle] \langle Makroname \rangle [\langle param \rangle][,\langle PAR \rangle...]
```

Es müssen ebensoviele Parameter (<param>) übergeben werden, wie formale Parameter in der Definition angegeben wurden. Als Parameter können Konstante, Ausdrücke und auch Strings verwendet werden. Ein Beispiel zur Verwendung von Strings als Parameter finden Sie im Teil 4.2 (Makro-Bibliotheken).

2.4.3 Lokale Labels

Als nächstes Beispiel betrachten Sie bitte das Listing des unten angegebenen Makros. Es handelt sich dabei um ein Programm zum Löschen eines Speicherbereiches von max. 256 Bytes (einer Page). Da das Programm mit einer Schleife arbeitet, enthält es folgerichtig auch einen Label. Hürden Sie dieses Makro zweimal innerhalb eines Programmes aufrufen, so wäre das Label LOOP doppelt verwendet, wodurch der Assembler den Fehler 'SAME LABEL TWICE' meldet.

```
LOESCH MACRO ADRESS, LAENGE
LDY #LANGE
LDX #0
LDA #0
LOOP STA ADRESS, X
INX
DEY
BNE LOOP
MEND
```

Auch hier bietet Ihnen ATMAS-II Unterstützung an: Ein Label, das mit dem '@' Symbol ([SHIFT-8]) endet, wird als lokales Label des Makros angesehen. Im Beispiel: statt LOOP muß der Label LOOP@ verwendet werden (auch im BNE-Befehl!). Intern ersetzt ATMAS-II das '@' Symbol durch eine vierstellige Zahl, die bei jedem Makroaufruf um eins erhöht wird. Dadurch erzeugt auch zweimalige Aufruf von LOESCH verschiedene Labels (nämlich LOOPOOO1 und LOOPOOO2).

2.4.4 Verschachtelte Makros

Eine Makrodefinition selbst kann wiederum einen Makro- aufruf einschließlich der Übergabe von Parametern enthalten. Als Beispiel kann ein Double-Poke Befehl dienen, der das bereits besprochene POKE-Makro benutzt:

```
DPOKE MACRO ADRESS, WORT
POKE ADRESS, WORT
POKE ADRESS+1, WORT/256
MEND
```

Diese Verschachtelungstechnik ist nur durch den Hardwarestack begrenzt.

2.4.5 Makros contra Unterprogramme

Sicherlich ist Ihnen bei der Beschreibung der Makros die nahe Verwandtschaft zu Unterprogrammen aufgefallen. Es gibt jedoch eine Reihe von wichtigen Unterschieden, die Sie sich verdeutlichen sollten:

Makros sind universeller in der Benutzung, da Sie über den Mechanismus der Parameterübergabe verfügen. Sie eignen sich daher gut zum Aufbau von Makro- (Programm) Bibliotheken. Solche Makrosammlungen lassen sich leicht mit dem flexiblen ATMAS-II Editor in den Quelltext einbinden. Makros gestatten wesentlich übersichtlichere Assemblerprogramme, man darf allerdings nicht übersehen, daß alle in der Definition des Makros angegebenen Maschinenbefehle bei jedem Aufruf des Makros in das Programm eingesetzt werden. Das · bedeutet, wenn Sie das LOESCH-Makro fünfmal im Programm verwenden, daß es ebenso oft in Ihr Programm eingesetzt wird, und natürlich auch dementsprechend Speicherplatz verbraucht.

Die Verwendung von Unterprogrammen ist wesentlich optimaler in Bezug auf Speicherplatz, wobei es allerdings schwieriger ist, die übergabe der Parameter so elegant wie im Makro zu gestalten. Ein weiterer, in manchen Fällen entscheidender Gesichtspunkt ist die Geschwindigkeit: Während Makros hier

die bessere Lösung darstellen, dauert es bei Unterprogrammen etwas länger, da ${\tt JSR}$ und ${\tt RTS}\text{-}{\tt Befehle}$ auch Zeit benötigen.

CHAPTER 3

Der Maschinensprache-Monitor

Vom Editor gelangen Sie durch die Eingabe von [CTRLP] in den Maschinensprache-Monitor. Der Bildschirm wird gelöscht und das "MONITOR."-Prompt erscheint in der linkem oberen Bildschirmecke. Mit dem ATMAS-II Monitor können Sie Maschinenprogramme starten, auf Diskette ablegen, den Speicherinhalt prüfen, verändern und disassemblieren und dabei ein Protokoll am Drucker mitführen. Da der Monitor über eine dialogorientierte Eingabe verfügt, brauchen Sie sich keinerlei komplizierte Befehlssyntax merken.

3.1 Allgemeine Benutzungshinweise

Alle Eingaben innerhalb des Monitors erfolgen in hexadezimaler Schreibweise (ohne vorangestelltes Dollar-zeichen!). Sollten Sie sich bei der Eingabe vertippen, so kann diese jederzeit mit 'X' abgebroched werden. Wenn Fragen im Dialog auftreten, werden diese mit 'Y' (Yes) positiv beantwortet, jeder andere Tastendruck (auch RETURN) beantwortet die Frage verneinend. Auch hier ist ein Abbruch mit 'X' möglich. Filenamen müssen immer im Standard-Atari Format einge- geben werden, d.h. zuerst einen Gerätenamen (D:, D1:, D2:...) dann der Filename mit max. 8 Zeichen, der nach einem Dezimalpunkt noch eine max. 3 Zeichen lange Erweiterung haben darf.

Beispiele: D:TEST.OBJ, D2:CODE.COM, D1:FILE

3.2 Befehlsvorat des Monitors

Die Befehle des Maschinensprache-Monitors bestehen aus einfachen Buchstaben, die Parameter, soweit nötig, werden im Dialog abgefragt.

3.2.1 M - Memory-Dump

Hit dem M-Befehl können Sie einen Speicherbereich in hexaderimaler Schreibweise auf Bildschirm oder Drucker ausgehen, weiterhin können Sie eine zusätzliche Darstellung den Speicherinhaltes in ASCII-Zeichen erhalten.

Beispiel:

Ihre Eingabe	Bildschirm
M	DUMP
D000	FROM:D000
D080	TO:D080
Y	ASCII?Y
RETURN	PRINT?

Nun wird der Speicherbereich von \$D000-\$D080 sowohl in hexadezimaler Schreibeweise als auch in ASCII ausgegeben. Hätten Sie bei der Frage ASCII? einfach [RETURN] gedrückt, so würde nur die hexadezimale Schreibweise ausgegeben. Antworten Sie auf die Frage PRINT? mit 'Y', dann müssen Sie sich für einen Ausgabekanal entscheiden:

- (1) wählt die serielle Schnittstelle R1: des ATARI-Interfaces als Ausgabekanal
- (2) Ausgabekanal ist die Centronics-Schnittstelle des ATARI-Interfaces (normaler 'P:'-Printer-Handler).
- (3) Ausgabe über Joystickinterface Port 3 & 4 (400/800)

3.2.2 D - Disassemble

Mit dem D-Befehl können Sie den Inhalt eines Speicherbereiches als 6502-Befehle rückübersetzen (disassemblieren) lassen. Wie bei M können Sie die Ausgabe auf den Drucker umlenken.

Beispiel:

Ihre Eingabe	Bildschirm
D	DISASSEMBLER
D000	START?D000
RETURN	PRINT?

Jetzt wird der Speicherinhalt ab der Adresse \$D000 in disassemblierter Form ausgegeben, wobei immer nach einer Füllung des Bildschirmes unterbrochen wird. Durch Drücken einer beliebigen Taste (außer 'X') wird der nächste Bildschirm ausgegeben. 'X' beendet die Disassemblierung. Bei Ausgabe auf Drucker findet keine Unterbrechung des Listings statt, der Ausdruck kann mit RESET abgebrochen werden.

3.2.3 C - Change Memory

Das C-Kommando erlaubt Ihnen die Veränderung von Speicherinhalten. Die Eingabe erfolgt in hexadezimaler Schreibweise.

Beispiel:

Ihr	e Eingabe	Bildschirm
C		CHANGE
A90	00	ADDRESS?A900
FF		A900 => FF
00		A901 => 00
Х		A902 =>
		MONITOR.

Sie können gezielt einzelne Bytes oder auch zusammenhängende Speicherblöcke in hexadezimaler Form eingeben. Durch die Eingabe von 'X' kommen Sie wieder in den Befehls-Eingabemodus des Monitors zurück.

3.2.4 F - Fill Memory

Mit dem F-Befehl können Sie einen Speicherbereich mit einem gewünschten Wert vorbesetzen.

Beispiel:

Ihre Eingabe	Bildschirm
F	FILL
A900	FROM: A900
AFFF	TO:AFFF
FF	WITH:FF

Wirkung: Der Speicherbereich \$ A900 bis \$ AFFF wird mit dem Wert \$ FF gefüllt.

3.2.5 B - Blocktransfer

Das B-Kommando erlaubt die Verschiebung ganzer Speicherblöcke. Dies kann nützlich sein, wenn Sie bei der Assemblierung mit ATMAS-II eine unterschiedliche logische und physikalische Adresse gewählt haben. Der B-Befehl benötigt Anfangsund Endadresse des zu verschiebenden Bereiches, sowie die Anfangsadresse des Zielbereiches.

Beispiel:

Ihre Eingabe	Bildschirm
В	BLOCKTRANSFER
A800	FROM: A800
A900	TO:A900
ACOO	INTO: ACOO

Wirkung: Der Speicherblock von \$A800 bis \$A900 wird in den Speicherbereich von \$AC00 bis \$AD00 kopiert.

3.2.6 G - Goto Address

Mit dem G-Befehl können Sie ein Maschinenprogramm starten, dessen Einsprungadresse Sie eingeben müssen.

Beispiel:

Ihre Eingabe	Bildschirm
G	GOTO
A800	GOTO A800

ACHTUNG: Sie müssen selbst dafür Sorge tragen, daß ein ausführbares Maschinenprogramm an der angegebenen Stelle steht!

Die Kontrolle wird an den Monitor zurückgegeben, wenn das Maschinenprogramm entweder mit einem RTS (Return from Subroutine) oder BRK (Break-Befehl, Hex-Byte \$00) endet. Im letzteren Fall bekommen Sie die Registerinhalte und die Prozessor-Flags angezeigt, eine hervorragende Möglichkeit, um ein Programm nach Fehlern zu durchsuchen.

3.2.7 S - Binary Save

Um ein vom Assembler erzeugtes Maschinenprogramm auf Diskette abzuspeichern, können Sie entweder ins DOS gehen (über Editor, ESC M ESC) oder den Monitor-Belehl S benutzen. Der Monitor speichert Maschinenprogramme so ab, daß Sie vom DOS-II (oder dazu kompatiblen DOS-Versionen) wieder geladen werden können.

Beispiel:

Ihre Eingabe	Bildschirm
S	SAVE
A800	FROM: A800
AFOO	TO:AF00
RETURN	INTO:
D:TEST.OBJ	FILENAME(D:FN.EXT)? D:TEST.OBJ

Dieses Beispiel bewirkt, daß der Speicherbereich von \$A800 bis \$AF00 als File TEST.OBJ im Laufwerk 1 abge- speichert wird. Der Filename muß immer im Standard- Atari Format eingeben werden.

Der SAVE-Befehl des ATMAS-II Monitors hat noch einige Zusätze aufzuweisen, die über den Standard hinaus- gehen:

a) Adressversetztes Abspeichern: Sie können ein Programm so abspeichern, daß es beim erneuten Einlesen in einen anderen Speicherbereich geladen wird. Das ist sehr nützlich, wenn Sie Programme mit getrennter logischer und physikalischer Adresse (s. ORG-Direktive) assembliert haben.

Sie müssen dazu bei den Fragen FROM bzw. TO den physikalen Adressbereich angeben (wo das Programm momentan abgelegt wurde) und bei der Frage INTO die logische Adresse (an die das Programm geladen werden soll) angeben.

Beispiel:

Ihre Eingabe	Bildschirm
S	SAVE
A800	FROM: A800
A780	TO:A980
4000	INTO:4000
D:TEST.OBJ	FILENAME(D:FN.EXT)?D:TEST.OBJ

Dieses Beispiel würde ein Programm, das von \$A800 bis \$A980 im Speicher steht, so auf die Diskette schreiben, daß es beim erneuten Einlesen im Bereich von \$4000 bis \$4180 liegt. Hatten Sie das Programm mit ORG \$4000,\$A800 assembliert, so ist es jetzt ein lauffähiges Maschinenprogramm. ACHTUNG: Sie sollten dieses File nicht mehr im Monitor einlesen, da sonst ATMAS-II überschrieben würde!

b) Append-Option: Wenn Sie als letztes Zeichen des Filesnames ein Größer-Zeichen ('>') eingeben, so wird das File an ein eventuell bereits bestehendes mit gleichem Filenamen angehängt. Sie können damit Com- pound-Files (aus mehreren Blöcken zusammengesetzte Files) oder Files mit INIT und RUN-Adresse erzeugen.

Beispiel:

Ihre Eingabe	Bidschirm
S	SAVE
AAOO	FROM: AAOO
ABOO	TO:AB00
RETURN	INTO:
D:TEST-OBJ>	FILENAME (D:FN.EXT)?D:TEST.OBJ>

Das File TEST.OBJ (von vorhin) wird in diesem Beispiel um den Speicherblock von \$AAOO bis \$ABOO verlängert. Mit derselben Methode können Sie auch RUN und INIT-Adressen an ein File anfügen: Sie tragen die RUN-Adresse

(LSB, MSB) in die Adressen \$02E0, \$02E1 (INIT: \$02E2, \$02E3) ein und hängen den jeweiligen 'Speicher-block' (der nur aus zwei Bytes besteht FROM: 02E0 TO: 02E1) an das File an.

3.2.8 L - Binary Load

Analog zum Save-Befehl kann hier ein Binär-File von der Diskette geladen werden. Es kann sich dabei um ein vom Save-Befehl erzeugtes oder um ein DOS erzeugtes Binär-File handeln, auch zusammengesetzte Compound-Files werden geladen. RUN und INIT Sprünge werden nicht ausgeführt.

Beispiel:

Ihre Eingabe	Bildschirm
L	LOAD
D:TEST.OBJ	FILENAME(D:FN.EXT)? D:TEST.OBJ
	FROM: 5000 TO: 5190
	FROM: AAOO TO: ABOO

Der Load-Befehl gibt Ihnen gleich an, in welchen Speicherbereich das Binär-File geladen wurde. Im Beispiel wurde ein File geladen, welches ähnlich zu dem im Save-Beispiel erzeugten ist.

3.2.9 E - Editor

Mit dem E-Kommando gelangen Sie zurück in den Editor, der Cursor befindet sich noch an der Stelle, wo Sie den Editor Verlassen haben.

3.2.10 I - Disketteninhaltsverzeichnis

Der I-Befehl zeigt Ihnen alle Filenamen des Laufwerks 1 auf dem Bildschirm an.

CHAPTER 4

Examples

4.1 Demo program, color scrolling

The following example should clarify the interaction of the individual components of ATMAS-II . It would be advantageous if chapter 1 (The editor) of this manual has been read and you are slightly familiar with the editor. Chapter 2 and 3 would not necessarily be required, but they will certainly contribute to better understanding.

Although the following demo program is included on the ATMAS-II disk (DEMO.SRC) you should still type it in manually in order to better familiarize yourself with the editor. When problems occur, you can use the included file as a fallback.

```
***********
* ATMAS-II Demo: Color Scrolling PF85
* Stop by pressing START
***********
COLPF2 EQU $D018
                   Color register
HSYNC
      EQU $D40A
                   Horizontal sync
VCOUNI EQU $D40B
                   Rasterline
                   VBI Clock
RTCLK
      EQU $14
CUNSDL EQU $D01F
                   function keys
* Program in USER-space
 (at $A800)
      ORG $A800
      LDA #8
                   Prepare polling the
```

	STA CONSOLD	START-key
SCRCOL	CLC	
	LDA VCOUNT	Screen counter
	ADC RTCLK	plus raster line
	STA HSYNC	synchronise
	STA COLPF2	to color register
	LDA CONSOL	function keys
	AND #1	START-key?
	BNE SCRCOL	no, continue>
	RTS	

As a reminder, here are some tips on typing in the program: comment lines start with a star in the first column. Also have lines that are provided with a label starting at the first column. For all other lines, it is advantageous to use a tab at the beginning of the line.

Example:

The first 'EQU' line should be typed like this:

```
COLPF2 TAB EQU $D01B RETURN
```

After you have typed-in the whole program, you can begin assembling by pressing [CTRL-Y]. You see the copyright of the assembler and if the assembler has detected no error, it will display the end address of the generated object code.

If errors occurred, these are presented to you in plain text on the screen. You can change them using the error table in Appendix B to track the down. We only discuss typo's here.

First, you press any key to return to the editor. The cursor is now at the offending line. A small tip: Sometimes it helps by pressing [CTRL-T] to see if perhaps a tab sits at the wrong location (i.e. a line that has only one tab or has only spaces will be reported as a SYNTAX ERROR).

If the assembler does not report an error, you can go out to start the program you just assembled. To do this, you press any key to get back to the editor and then type [CTRL-P] to call to the monitor.

In the monitor you can view the program generated by the assembler. To do this, type 'D' (Disassemble) followed by 'texttt A800' and RETURN . You should now see a disassembled listing of the program on the screen. Now press 'X' to cancel the disassembler's listing.

To start the program type 'G' (GOTO) and the start address of the program, in our case 'A800'. If you did everything correctly, you should now see 128 colors running on the screen. The color spectacle can be terminated by pressing <code>[START]</code> or <code>[RESET]</code>. When you press <code>[RESET]</code>, you will automatically return to the editor. By pressing <code>[START]</code>, the program is properly terminated and control goes back to the monitor. 'E' finally reactivates the editor.

4.2 Macro libraries

On the ATMAS-II disk, you can find two files - IOLIB.SRC and GRAFLIB.SRC whose source code is included on the following pages. Both are so-called macro libraries, which means that, except for a small demo program, they only include macro definitions. Both contain inline comments, so an in-depth description is not necessary.

GRAFLIB. SRC contains macros that behave similarly to their BASIC counterparts (GRAPHICS, COLOR, PLOT and DRAWTO). You can view the demo by loading and assembling GRAFLIB. SRC and by using the monitor to 'G' o to address \$A800.

IOLIB. SRC contains macros similar to the OPEN, CLOSE, PRINT and INPUT BASIC commands and two additional macros (BGET and BPUT) for loading and saving binary data. This library also contains an interesting demo, which can be run similarly as that of GRAFLIB.

The macro libraries contain examples of nesting macros and passing string parameters. Both files can be seen as examples of what can be done with ATMAS-II .

Obviously, it is allowed to extend and improve both libraries as you wish.

```
***********
         GRAFLIB.SRC
         Macro Library
         GRAPHICS
        For ATMAS-II
                      PETER FINZEL
***********
* IOCB Structure
ICCOM
           EQU $342
           EQU $343
ICSTA
ICBAL
           EQU $344
ICBAH
           EQU $345
ICBLL
           EQU $348
ICBLH
           EQU $349
ICAX1
           EQU $34A
ICAX2
           EQU $34B
CIOV
          EQU $E456
* CIO Commands
COPEN
           EQU 3
CCLSE
           EQU 12
CGTXT
           EQU 5
           EQU 9
CPTXT
           EQU 7
```

CGBIN

```
CPBIN
             EQU 11
CDRAW
             EQU $11
* ATARI Graphics Variables
ATACHR
              EBU $2FB
ROWCRS
              EBU $54
                                     CURSOR-
              EBU $55
COLCRS
                                     POSITION
* GRAPHICS-Command
* Call: GRAPHICS <mode>
* <mode> 0 bis 15 (XLs)
          0 bis 11 (400/800)
GRAPHICS MACRO MODE
        JMP GR10
DEV@
       ASC 'S:'
GR1@
       LDX #$60
        LDA #CCLSE
                          FIRST CLOSE CHANNEL 6
        STA ICCOM, X
        JSR CIOV
        LDA #MODE
                          SET NEW MODE
        STA ICAX2,X
        AND #$FO
        EOR #$10
        ORA #$OC
        STA ICAX1,X
        LDA #COPEN
        STA ICCOM, X
        LDA #DEV@
        STA ICBAL, X
        LDA #DEV@/256
        STA ICBAH, X
        JSR CIOV
        MEND
* Select drawing color
* Call: COLOR <color>
* <color> ranges from 0-255,
            depending on graphics mode.
            Must be constant
```

```
COLOR
       MACRO COL
        LDA #COL
        STA ATACHR
        MEND
* Move cursor to position
* Call: POSITION <x>,<y>
* <x>,<y> depends on graphics mode
           both must be constant
POSITION MACRO X,Y
       LDA #X
        STA COLCRS
        LDA #X/256
        STA COLCRS+1
        LDA #Y
        STA ROWCRS
        MEND
* Draw point
* Call: PLOT <x>,<y>
* <x>,<y> depends on graphics mode
          must be constant
*
PLOT
       MACRO X,Y
       POSITION X,Y
        LDX #$60
                        CHANNEL 6
        LDA #CPBIN
        STA ICCOH, X
        LDA #0
        STA ICBLL,X
        STA ICBLH, X
        LDA ATACHR
        JSR CIOV
        MEND
* Draw line
* Call: DRAWTO <x>,<y>
* <x>,<y> depends on graphics mode
                        must be constant
DRAWTO MACRO X,Y
        POSTTION X,Y
```

```
LDA #CDRAH
      STA ICCOM, X
      LDA #CCLSE
      STA ICAX1,X
      LDA #O
      STA ICAX2,I
      JSR CIOV
      MEND
**********
* Demo-Program for Graphics Library
* draw diamond shape in GRAPHICS 7
**********
* assemble to memory reserved
* for object-code
      ORG $A800
      GRAPHICS 7+16
      COLOR 1
      PLOT 79,0
      DRAWTO 159,47
      DRAWTO 79,95
      DRAWTO 0,47
      DRAWTO 79,0
ENDLESS JMP ENDLESS
* Stop by pressing <RESET>
**********
       IOLIB.SRC
       MACRO LIBRARY
        Input/Output
        for ATMAS-II
             by PETER FINZEL
**********
* IOCB Constants
CIOV EQU $E456
```

LDX #\$60

CHANNEL 6

```
ICCOM EQU $342
ICSTA EQU $343
ICBAL
      EQU $344
ICBAH EQU $345
ICBLL EQU $348
ICBLH EQU $349
ICAX1
       EQU $34A
1CAX2
       EQU $34B
* CIO Commands
       EQU 3
COPEN
CCLSE
      EQU 12
CGTXT EQU 5
CPTXT EQU 9
CBBIN EQU 7
CPBIN EQU 11
EOL
       EQU $9B
* MACRO FOR CALCULATING THE CHANNEL NUMBER
* (only for internal use, is
* an example of nested
* macro calls)
CHANNUM MACRO CHANNEL
        LDA #CHANNEL
                           IOCB-Offset
        ASL
                           *output channel number
        ASL
                           *(times 16)
        ASL
        ASL
        TAX
                           * Result in X-Register
        MEND
* Name
       : OPEN
* Goal : Open file
* Call : OPEN <Num>,<Aux1>,<Aux2>,<Filename>
* Example : OPEN 1,4,0,"D:TEST.DBJ"
OPEN
        MACRO CHANNEL, AUX1, AUX2, FILENAME
        JMP OP1@
FNAME
        ASC FILENAME
        DFB EOL
0P1@
        CHANNUM CHANNEL
        LDA #AUXI
        STA ICAX1,X
        LDA #AUX2
```

```
STA ICAX2,X
        LOA #COPEN
        STA ICCOM, X
        LDA #FNAME
        STA ICBAL, X
        LDA #FNAME/256
        STA ICBAH, X
        JSR CIOV
        MEND
         : CLOSE
* Name
          : Close file
* Goal
        : CLOSE <Num>
* Call
* Example : CLOSE 1
CLOSE
      MACRO CHANNEL
        CHANNUM CHANNEL
        LDA #CCLSE
        STA ICCOM, X
        JSR CIOV
        MEND
* Name
         : PRINT
         : Print a string defined with 'ASC',
* Goal
           must end with EOL
* Call
         : PRINT <Channel>,<Label>
* Example : PRINT 0, TEXT1
PRINT
       MACRO CHANNEL, LABEL
        CHANNUM CHANNEL
        LDA #CPTXT
        SIA ICCOM, X
        LDA #LABEL
        STA ICBAL, X
        LDA #LABEL/256
        STA ICBAH,X
       LDA #127
                        maximum length
        STA ICBLL, X
        LDA #0
        STA ICBLH, X
        JSR CIOV
        MEND
         : PRINTS
* Name
* Goal
          : print string directly
            to screen
         : PRINT <String>
* Call
* Example : PRINTS "HALLO"
```

```
PRINTS MACRO STRING
        JMP PR2@
PRI10
        ASC STRING
        DFB EOL
PR2@
       PRINT O, PRI1 macro above!
        MEND
       : INPUT
* Name
* Goal
         : Read string
       : INPUT <Channel>,<Label>
* Call
* Example : INPUT 0,TEXT1
INPUT
       MACRO CHANNEL, LABEL
        CHANNUM CHANNEL
        LDA #CGTXT
        STA ICCOM, X
        LDA #LABEL
        STA ICBAL, X
        LDA #LABEL/256
        STA ICBAN, X
        LDA #127
                       maximum length
        STA ICBLL,X
        LDA #0
        STA ICBLH,X
        JSR CIOV
        MEND
        : BGET
* Name
* Goal
         : Read data block
           of length L at address A
* Call : BGET <Num>,<L>,<A>
* Example : BGET 1,$B000,$100
BGET
        MACRO CHANNEL, LENGTH, BUFFER
        CHANNUM CHANNEL
        LDA #CGBIN
        STA ICCOM, X
        LDA #LENGTH
        STA ICBLL, X
        LDA #LENGTH/256
        STA ICBLN, X
        LDA #BUFFER
        STA ICBAL, X
        LDA #BUFFER/256
        STA ICBAN, X
        JSR CIOV
        MEND
```

* Name : BPUT

* Goal : Save data block

of length L at address A

* Call : BPUT <Num>, <L>, <A> * Example : BPUT 1,\$B000,\$100

BPUT MACRO CHANNEL, LENGTH, BUFFER

CHANNUM CHANNEL

LDA #CPBIN STA ICCOM, X LDA #LENGTH STA ICBLL,X

LDA #LENGTH/256 STA ICBLH, X

LDA #BUFFER

STA ICBAL, X LDA #BUFFER/255

STA ICBAH, X

JSR CIOV MEND

* Demo Program I/O-Library

* display directory of drive 1.

ORB \$A800

PRINTS "Directory Drive 1:" OPEN 1,6,0,"D1:*.*"

INPUT 1,BUFFER NEXT

Read directory line BMI END End of File? PRINT O, BUFFER and print JMP NEXT next line

END CLOSE 1 Done!

RTS

BUFFER ORG *+20 Reserve space

- * START THE DEMO:
- * Assemble with <CTRL>-Y,
- * activate the monitor with <CTRL>-P
- * and start with 'G'oto A800.

APPENDIX A

ATMAS-II Memory Map

```
0000 - 007F:
                    Used by Operating System
                    *** free for personal use ***
0080 - 0085:
0086 - 00DF:
                    Used by ATMAS-II Editor and Monitor
00E0 - 00FD:
                    Used by ATMAS-II Assembler, but is free
                    to use after the assembler has finished
                    Hardware stack, O.S. Vectors, IOCB's etc...
OOFE - 047F:
0480 - 05FF:
                    *** free for personal use ***
0600 - 06FF:
                    *** free for personal use (Page 6) ***
0700 - <LOMEM>:
                    DOS, <LOMEM> DOSII:=$1F00
                    DOSXL:=$2700
                    *** free for personal use ***
<LO> - 27FF:
2800 - 4AFF:
                    ATMAS-II
4800 - 4BFF:
                    Line buffer
4C00 - 5FFF:
                    Symbol table
6000 - 63FF:
                    Copy-register
6400 - A7FF:
                    Text buffer (source code)
A800 - <MEMTOP>:
                    *** free for personal use ***
<ME> - BFFF:
                    Display list and screen memory
```

There are several ranges of free memory you can use for your object code:

- A) \$600-\$6FF: the infamous Page 6, especially used for writing small routines to be called by USR() from BASIC.
- B) \$1F00-\$27FF: this range starts at the end of DOS, which can be determined by reading \$2E7-\$2E8, up to the start address of ATMAS-II itself. The end of DOS can vary for different DOS versions, so you have to be careful here. For standard DOS-II, this range starts at \$1F00.
- C) \$A800-\$BC3F: The standard range for object code, reaches up to the display list and screen memory.

The memory used by the symbol table (\$4C00-\$5FFF) can be used for variables, font definitions or Player-Missile Graphics, as the symbol table will not

be used after the assembler has run and will be rebuilt the next time the assembler is run.

 $_{\scriptscriptstyle{ ext{APPENDIX}}}$ B

Error codes

B.1 Assembler errors

SYNTAX ERROR e.g. a line-number is specified or a line consists

only of whitespace (tabs and spaces)

NAME UNKNOWN Invalid opcode, e.g. SRA instead of STA

UNDEFINED EXPRESSION Invalid operand, e.g. invalid expression or un-

defined label.

ADDRESSING ERROR Addressing mode mismatch, i.e. STA #\$6FF

IMPOSSIBLE BRANCH Branches (BNE, BCS...) can only reach ad-

dressess between $*{\text -}128$ and $*{\text +}127.$ Use ${\tt JMP}$

instead.

DIVISION BY ZERO e.g. LDA #100/0

NUMBER-ERROR Invalid number, e.g. LDA #%30 or LDA #A0

WRONG DELIMITER Invalid delimiter used for ASC command.

NO ASCII Invalid ASCII character constant, e.g. LDA #'

RETURN

LINE TO LONG Maximum line length is 127 characters

MACRO ERROR Invalid macro definition or macro call (invalid

parameters)

ORG ERROR Invalid ORG-directive

TOO MANY LABELS Symbol table is full

OPCODE DIFFERENT

Pass 3 does not match pass 2. This can happen if pass 2 overwrites the text buffer because of an invalid ORG.

B.2 Editor errors

- RW Error during disk I/O
- CO Command line too long
- E? Error, invalid command line
- H? Invalid hexadecimal value
- I? Textbuffer is full (T:00000)
- L? Device error during output of listing
- S? String not found (search-function)
- T? Invalid tab-width (must be 1-9)
- C? Copy-register is full (C:0000)
- #? Invalid repeat-factor (must be 2-255),
- OK Situation Normal, All...is well. Copy-register is closed
- CR Copy-register is open

B.3 Monitor error codes

ADR ERROR Wrong address during loading or saving of a program. If

this occurs during a LOAD-command, it's probably not a

binary file, but, for example, a text file.

ERRORCODE 80-FF: Operating System Error, see the DOS-Manual. Er-

ror codes are hexadecimal.



ATMAS-II REFERENCE CARD