







[SOLVED] Remove node from cluster

≗ alterman1994 · ③ Oct 28, 2021

命 > Forums > Proxmox Virtual Environment > **Proxmox VE: Installation and configuration**



alterman1994

New Member



~


Oct 28, 2021 < #1
Hello Guys,

I mistakenly added new node to cluster using public network (instead of storage one). I'm checking https://pve.proxmox.com/wiki/Cluster_Manager#_remove_a_cluster_node

to remove the node. I powered off the machine (pve7) to make sure it will never power on again (going to reconfigure it from scratch)



However, when I execute pvecm nodes, I don't see this node listed



How can I properly remove it? Could someone please assist? The cluster is in production, don't want to screw it up.

Proxmox version: 6.4-13

Thanks.



Oct 28, 2021 #2

Yes, pvecm nodes only lists the active ones.

In the GUI you see the name of the node you want to delete. Use that for the command pvecm delnode as described in the docs/wiki.

Best regards,

Mira

Do you already have a Commercial Support Subscription? - If not, Buy now and read the documentation



Oct 28, 2021

#3

@mira Hello, thank you for your feedback.

I run it and that's what I got:

alterman1994

New Member

Code:

root@pve1:~# pvecm delnode pve7 Could not kill node (error = CS_ERR_NOT_EXIST)

Killing node 7

command 'corosync-cfgtool -k 7' failed: exit code 1

Seems like it did the trick, I don't see pve7 anymore in gui, /etc/corosync /corosync.conf and /etc/pve/corosync.conf

However, do I need to worry about the output? Anything I need to reload after this operation? Sorry if questions look stupid to you.

Thanks in advance.



alterman1994

New Member

2

Oct 28, 2021

#4

Nevermind, I've reinstalled it from scratch, cleaned old known_hosts and added new node properly.

Thanks for your great support!

mira



Active Member

Nov 24, 2022

#5

I, too, am trying to remove a node from my cluster (to set it up anew and rejoin it).

~

I managed to delete it using pvecm but it still showed up in the GUI.

So I removed the respective folder under /etc/pve/nodes and now it is gone.

But doing this, I discovered that I have another folder /etc/pve/nodes/pve which does not correspond to a node shown in the GUI or still in existence. My cluster has evolved over time and I removed all original nodes and replaced them with newer ones. It *may* be that one of the originals nodes was named "pve". Can I simply remove also this folder or might I kill my cluster?

Thanks

Jannoke

Last edited: Nov 24, 2022

#6

ぺ #7

\$ #8



Jannoke

Well-Known Member

~

Dec 15, 2022

You probably won't kill the clustet, but you can backup it and remove it and test if something goes wrong. You can always put it back. Just don't do it on working hours. Anyways thanks for the tip on removing the /etc/pve/nodes /<node> folder. I got to same point where it deleted the node but did not remove it from GUI.

chrzimm

Jan 22, 2023



cryptocurt

New Member

~

proxwolfe said: 5

I, too, am trying to remove a node from my cluster (to set it up anew and rejoin it).

I managed to delete it using pvecm but it still showed up in the GUI.

Click to expand...

How did you remove the folder, I get an error; **rm: cannot remove 'local': Is a directory** I tried the -f flag but that's not working



kajizta

New Member

~

Jan 26, 2023

cryptocurt said: 5

How did you remove the folder, I get an error; rm: cannot remove 'local': Is a directory I tried the -f flag but that's not working

use rm -rf /path/to/foo to delete folder

\$ #9

#10



hrz

New Member

Feb 19, 2023

Jannoke said: 5

You probably won't kill the clustet, but you can backup it and remove it and test if something goes wrong. You can always put it back. Just don't do it on working hours. Anyways thanks for the tip on removing the /etc/pve/nodes /<node> folder. I got to same point where it deleted the node but did not remove it from GUI.

THANK YOU, this worked, you can use the command "rm -rf /etc/pve/nodes /NAME" reboot and the pesky node is finally gone from the dashboard...



ihr

New Member

Feb 21, 2023

On Proxmox 7.3 after running


Code:

pvecm delnode <cabecicubo>

The node got deleted, and pvecm nodes no longer shows cabecicubo on the list; but, in the UI, the node is still visible, without the green check, but visible.

How can I remove it from the UI?

Attachments



Window-3.png

Last edited: Feb 21, 2023



Feb 21, 2023

\$ #11

Have you tried removing the folder corresponding to the node under /etc/pve

proxwolfeActive Member

/nodes?

Feb 21, 2023

#12

ihr

New Member

proxwolfe said: 5

Have you tried removing the folder corresponding to the node under /etc/pve /nodes?

No, That directory exist. In that folder there is "old" information about that node but the interesting thing is that in the sub-folder called <code>qemu-server</code> there is still one file <code>lss.conf</code> that contains the configuration of one VM that I no longer use.

The cleanest think to do is to remove all resources that corresponds with that VM and then, remove the node info for that folder.



Feb 21, 2023

\$ #13

Jannoke Well-Known Member

~

I just found that there was still my old node data available on the /etc/pve /nodes path. So just to test it out I just created dummy 1.conf file in the qemuserver subfolder and it immidiately added this node to he list of nodes in web ui. Of course it's with quiestion mark. After removing the 1.conf file, the node will not have any virtual machines, but wil not dissapear from the list until i refresh browser. So yes - qemu-server folder needs to be empty for it to dissapear from nodes tree.



<mark>fpdragon</mark> New Member Hi there,

Sep 17, 2023

c #14

I think I am currently in a similar problem. The whole mess kind of started when I tried to create a cluster between two different versions of pve nodes. I have learned now and tried to cleanup everything and apgrade both nodes. now they are on same version 7.4-16.

However I still see the old node after I create a NEW cluster with a new name. Since a manually removed several configuration files related to cluster and corosync modules before, I guess the problem relies in the /etc/pve/nodes/* directories.

However, maybe I am dumb but I was not able to remove them. I also tried with rm -rf /etc/pve/nodes/nodename but I always get a "Permission denied". There are several subdirs (lxc, openvz priv qemu-server) that I also can't remove the subdirs.

Another problem is, when I execute systematl stop pve-cluster my remote

. .

console connection drops and I am not able remove the directories afterwards. Currently I dont have a physical direct console available so I do have to use the web interface or SSH shell.

Any idea how to get rid of the directories? Thanks.



fpdragon **New Member**

Sep 17, 2023



Ok, I figured out how to remove the directories. The trick was once again, to remove the whole cluster with

Code:

rm -f /etc/pve/cluster.conf /etc/pve/corosync.conf

rm -f /etc/cluster/cluster.conf /etc/corosync/corosync.conf

rm /var/lib/pve-cluster/.pmxcfs.lockfile

After reboot the cluster disappeard and I also was able to remove the node directories.

So it seems that everything was clean now and when creating a new cluster no old node shows up any more.

However that has not solved my main problem that I can't add my second node to the cluster. I guess I will create a new post for that.



Jannoke

Well-Known Member

Sep 17, 2023



I believe permission denied error came from you not having chorus - You should have at least 3 nodes so that chorus would work. If you have two - as soon as one breaks, the whole cluster will go read-only, because remaining node does not have confirmation if he's "in" or "out". Third node can be some simple NUC or rasperry pi. Does not have to be fullblown machine bearing load.



fpdragon

New Member

\$ #17

Jannoke said: 5

Sep 17, 2023

I believe permission denied error came from you not having chorus - You should have at least 3 nodes so that chorus would work. If you have two - as soon as one breaks, the whole cluster will go read-only, because remaining node does not have confirmation if he's "in" or "out". Third node can be some simple NUC or rasperry pi. Does not have to be fullblown machine bearing load.

yeah, I do know that nomally 3 nodes are required. I was using 2 nodes before since is still quite handy to migrate vms between the two nodes.



Dec 19, 2023 < #18

hello im having a isue with my node not booding after a cup failuer i can no longer boot up this node how to i remove the nde from my cluster so i can use my vms after when i get to the gui all i see is this (image 1) i can not boot any vm i get the err code 500 sombody help me

Attachments



You must log in or register to reply here.

Share: 🗹 👄

♠ > Forums > Proxmox Virtual Environment > Proxmox VE: Installation and configuration

About

The Proxmox community has been around for many years and offers help and support for Proxmox VE, Proxmox Backup Server, and Proxmox Mail Gateway.

We think our community is one of the best

We think our community is one of the best thanks to people like you!

Quick Navigation

Home

Get Subscription

Wiki

Downloads

Proxmox Customer Portal

About

Get your subscription!

The Proxmox team works very hard to make sure you are running the best software and getting stable updates and security enhancements, as well as quick enterprise support. Tens of thousands of happy customers have a Proxmox subscription. Get your own in 60 seconds.

Ħ Buy now!

Proxmox Support Forum - Light Mode Contact us Terms and rules Privacy policy Help Home

A

Community platform by XenForo®© 2010-2023 XenForo Ltd.

This site uses cookies to help personalise content, tailor your experience and to keep you logged in if you register.

By continuing to use this site, you are consenting to our use of cookies.

Learn more...