



- Jaxer Guide
- Introduction
 - Setup
 - Develop
 - Debug

JaxerManager Command Line Interface (CLI)

The Jaxer process itself is effectively single-threaded, so a pool of Jaxer processes is used to handle multiple simultaneous requests. JaxerManager is the application that manages the lifecycle of these Jaxer processes, starting them up when it starts and spinning up new ones as the load increases, tearing them down when the load decreases or JaxerManager exits (or when a Jaxer is "misbehaving"), connecting them to the web server to handle requests, and configuring them. When you start up Jaxer, you're really starting up JaxerManager: check your list of processes for a single JaxerManager.exe (or jaxermanager on Mac OS X and Linux) and multiple Jaxer.exe (or jaxer) processes. JaxerManager listens on one port, its "web port", for requests from the web server, and routes them to Jaxers in its pool. It also listens on a different port, its "command port", for commands. These commands can also usually be specified on the command line when JaxerManager is started, or in a config file loaded when JaxerManager starts (or restarts/reloads).

Contents

- Precedence
- Jaxer Commands and Settings
 - Commands that can only be issued after JaxerManager has started
 - Example: Actions against JaxerManager in a command shell

Precedence

When JaxerManager starts, it processes the commands/settings in the following order (last setting wins):

- Defaults hardcoded in the binary
- Default config file
- Config file specified on the command line
- Command line arguments

Jaxer Commands and Settings

Commands and settings can be communicated to JaxerManager in three ways, each with its own format:

- arguments on the command line, as --<command>=<value>
- configuration file, one command per line as <command> <value>
- command port, only after the manager is running using the tellJaxerManager utility as tellJaxerManager -p <port_num> set <command> <value>

The following table lists all the commands, settings and parameters that JaxerManager understands, and if it can be specified in each of three manners.

To see the settings your manager supports, except for those only applicable to the CLI, execute JaxerManager --help at an OS command prompt.

On Windows, JaxerManager can also be run as a service (see details with JaxerManager --help)

Note: The default value is the hardcoded in the manager binary.

Command/Setting	Value	Default	Arguments	Config File
configfile	file_path	None	yes	no
Specify a config file on the cmdline that will be loaded during startup.				
webport	port	4327	yes	yes
commandport	port	4328	yes	yes
minprocesses	integer	1	yes	yes
Minimum number of Jaxer processes. If set to higher than maxprocesses, then maxprocesses set to the same value.				
maxprocesses	integer	10	yes	yes
JaxerManager will not start more Jaxer processes if there are already <number> or more running; if lower than the value of minprocesses, then minprocesses is set to the same value				
roundrobinjaxers	on off	on	yes	yes
Determines if requests will be roundrobined to all idle Jaxers.				
startjaxertimeout	integer	>=30	yes	yes
JaxerManager will exit if it fails to maintain the minprocesses Jaxers for a consecutive of <number> seconds. This is mainly to prevent JaxerManager on trying to start Jaxers on a platform it repeatedly fails. A zero value turns this off.				
jaxeridletimeout	integer	>=10	yes	yes
Determines when an idle Jaxer process will be killed.				

pingtimeout	integer	0	yes	yes
Set the timeout of Jaxer Manager that will die if a ping is not received within <number> seconds.				
maxmemory	integer	150	yes	yes
A hard limit of <number> megabytes of aggregate RAM used is imposed on all Jaxer processes; zero means no limit. The setting affects only newly created Jaxer processes, except on Mac where it affects all processes.				
maxrequests	integer	0	yes	yes
A Jaxer is terminated after it performs <number> requests. A value of zero is equivalent to infinity.				
requesttimeout	integer	20	yes	yes
A Jaxer that takes more than <number> seconds to process a request is terminated. A value zero is equivalent to infinity.				
loglevel	FATAL ERROR WARN INFO DEBUG TRACE	INFO	yes	yes
Specifies the log level for jaxerManager (not Jaxer).				
log:output	absolute_path	framework/ JaxerCoreJSConsole.log	yes	yes
Specifies the logfile or a pipe to a process. To specify a process, the first character must be ' ' and you are responsible for starting that process.				
log:filesize	integer	512000	yes	yes
Logfile size in bytes				
log:numbackups	integer	10	yes	yes
Number of logfile backups to keep.				
pref: <pref_name>	pref_value	none	yes	yes
Preference setting that will be passed to Jaxer.				
cfg:<name>	cfg_value	none	yes	yes
config settings that will be passed to Jaxer when it starts up.				

Commands that can only be issued after JaxerManager has started

Sent in the form of tellJaxerManager -p portNumber <cmd> or tellJaxerManager -p portNumber <cmd> <val>.

- **exit:** Immediate, non-graceful termination of all Jaxers and then of JaxerManager.
- **stop:** Graceful termination of all Jaxers once they've finished processing, then when they're all dead stop JaxerManager.
- **pause:** Suspend processing of requests
- **resume:** Resume processing of requests
- **ping:** Test for JaxerManager responsiveness, returns "pong" followed by one of: paused|running|stopping|reloading
- **reload:** Graceful termination of all Jaxers, followed by loading a named config file (optional, otherwise configuration is unchanged) and restarting of all Jaxer processes.
- **restart:** Immediate, non-graceful termination of all Jaxers, followed by loading a named config file (optional, otherwise configuration is unchanged) and restarting of all Jaxer processes
- **get version:** Returns the version string
- **get [param]:** Returns the value for the specified parameter. If [param] is not a recognized parameter, then "*** bad" is returned, followed by "\r\n".
- **get all:** Returns all parameters and their values in the form of param=value separated by a comma and followed at the end by "\r\n".
- **setconfig [property] [value]:** Sets the specified property on Jaxer.Config to the passed value. Note that [property] is of the form prop1.subprop1.subsubprop1, example: setconfig DB_CONNECTION_PARAMS.PATH "resource:///../data/appdata.sqlite"

Actions against JaxerManager in a command shell

You can tell apart the input lines from the output lines because the former always start with tellJaxerManager.

```
01. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager -p 4328 get version
02. *** 1.0.0.3989_RC_C
03.
```

```
04. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager get all
05. version=1.0.0.3989_RC_C
06. commandport=4328
07. jaxeridletimeout=10
08. loglevel=INFO
09. maxmemory=150
10. maxprocesses=10
11. maxrequests=1000
12. minprocesses=1
13. pingtimeout=0
14. requesttimeout=0
15. roundrobinjaxers=on
16. startjaxertimeout=30
17. timeout=0
18. webport=4327
19. log:filesize=500000
20. log:numbackups=10
21. log:output=D:\ajam\Aptana Jaxer\\logs\jaxer.log
22.
23. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager set maxprocesses 5
24. *** ok
25.
26. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager ping
27. *** pong running
28.
29. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager maxprocesses
30. *** Unknown command
31.
32. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager get maxprocesses
33. 5
34.
35. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager get foobar
36. *** bad option
37.
38. D:\ajam\Aptana Jaxer\jaxer>tellJaxerManager stop
39. *** ok
```