

HUBBLE FIELDS

工地考勤系统功能介绍与使用指南

Feature Overview & User Guide

中英双语 · Bilingual (中文 / English)

Version 0.1 · Field Attendance App

目录 / Contents

1. 产品简介 Product Overview
2. 角色与权限 Roles & Permissions
3. 快速开始 Getting Started
4. 日常考勤操作 Daily Attendance
5. 现场人员与历史 Onsite & History
6. 人力名册 Manpower
7. 管理功能 Administration
8. 设置 Settings
9. 平台控制台 Platform Console
10. 常见问题 Troubleshooting

说明：每一节同时提供中文与英文，便于现场中外团队共用同一份文档。

Note: Each section includes Chinese and English so mixed teams can share one document.

1. 产品简介 / 1. Product Overview

Hubble Fields 是面向建筑工地的移动端/桌面端网页考勤系统。现场主管可为工人办理签到与签退，系统记录 GPS 地理围栏状态与现场照片，并支持弱网离线排队同步。

Hubble Fields is a mobile/desktop web attendance app for construction sites. Supervisors check workers in and out with GPS geofence validation and a required site photo, with offline queuing when the network is weak.

平台运营侧可使用 Hubble Fields Platform Console 管理客户公司、项目与项目管理员账号。

Platform operators can use the Hubble Fields Platform Console to manage customer companies, projects, and Project Admin accounts.

核心能力 · Key capabilities

- 工人签到 / 签退 — Worker check-in / check-out with GPS + photo
- 在场名单与考勤历史 — Live onsite roster and attendance history
- 人力名册管理 — Manpower directory (ID, company, trade, status)
- 报表与 CSV 导出 — Shift-hour reports and CSV export (admin)
- 用户邀请与密码重置 — Invite users and reset temporary passwords
- 离线同步 — Offline punch queue with automatic sync
- 中英双语界面 — English + Simplified Chinese UI

2. 角色与权限 / 2. Roles & Permissions

不同角色看到的菜单与可执行操作不同。请按岗位分配账号。

Menus and actions differ by role. Assign accounts according to job responsibility.

角色 Role	签到 Check-in	历史 History	人力 Manpower	报表 Reports	用户 Users
Project Admin 项目管理员	✓	✓ (92天)	读写 Manage	✓ CSV	邀请/重置
Supervisor 主管	✓	✓ (14天)	只读 Read	—	—

角色 Role	签到 Check-in	历史 History	人力 Manpower	报表 Reports	用户 Users
Safety Officer 安全员	√	√ (14天)	只读 Read	—	—
Attendance Admin 考勤管理员	√	√ (14天)	只读 Read	—	—
Project Manager 项目经理	√	√ (14天)	只读 Read	—	—
Viewer 只读访客	—	√ (14天)	只读 Read	—	—
Platform Admin 平台管理员	同项目角色	—	—	—	控制台 Console

- 项目管理员可邀请：Supervisor / Safety Officer / Attendance Admin / Project Manager / Viewer。
- Project Admins can invite the roles above (not another Project Admin from the project app).
- 平台管理员可进入 Platform Console (/platform 或 /console) 创建客户公司与项目管理员。

3. 快速开始 / 3. Getting Started

3.1 打开登录页 · 3.1 Open the sign-in page

在手机或电脑浏览器打开登录地址，例如生产环境：https://hubblefields.com/signin
；本地开发：http://localhost:3000/signin。同一 Wi-Fi 下也可用局域网 IP 访问。

Open the sign-in URL in a phone or desktop browser, e.g. production https://hubblefields.com/signin or local http://localhost:3000/signin. On the same Wi-Fi you can also use the LAN IP.

3.2 登录 · 3.2 Sign in

1. 输入公司邮箱与密码，点击「Sign in →」。

Enter company email and password, then tap Sign in →.

2. 若为首次登录或临时密码，系统会要求设置新密码（至少 10 位，含大写字母与数字）。

On first login or temporary password, create a new password (10+ characters, including an uppercase letter and a number).

3. 临时密码如未更换，将在 7 天后失效。

Temporary passwords expire in 7 days if not changed.

3.3 忘记密码 · 3.3 Forgot password

应用内无自助找回。请联系项目管理员在「User access」中重置临时密码。种子管理员可由运维执行 `npm run db:reset-admin`。

There is no self-service reset. Ask a Project Admin to Reset a temporary password under User access. For the seed admin, ops may run `npm run db:reset-admin`.

4. 日常考勤操作 / 4. Daily Attendance

主管及具备签到权限的角色在「Overview / 首页」办理签到与签退。每次打卡必须开启定位并拍摄现场照片。

Supervisors and other check-in roles use Overview to check workers in or out. Every punch requires GPS location and a site photo.

4.1 签到 Check In · 4.1 Check In

1. 点击「Check In」。

Tap Check In.

2. 在「WORKER ARRIVAL」中搜索并选择工人（姓名 / 工号后四位 / 工种）。

In WORKER ARRIVAL, search and select a worker (name / last four of ID / trade).

3. 确认 Location：显示 Location verified · on site；若 Outside site，请移动至工地范围内（严格模式下离场将被拒绝）。

Confirm Location shows Location verified · on site. If Outside site, move into the geofence (strict mode blocks off-site punches).

4. 可选填写 Remarks（最多 300 字）。

Optionally enter Remarks (max 300 characters).

5. 拍摄 Site photo：Capture / Album，确认后 Submit check in。

Capture a Site photo (Capture / Album), then Submit check in.

4.2 签退 Check Out · 4.2 Check Out

流程与签到相同，入口为「Check

Out」或在场名单中的「Out」。工人须当日已在场才能签退；已签到者不可重复签到。

Same flow as check-in via Check Out or Out on the onsite list. A worker must already be onsite to check out; a worker already checked in today cannot check in again.

4.3 地理围栏与照片 · 4.3 Geofence & photo

- GPS 始终需要；请在系统设置与浏览器中允许定位，并在应用 Settings → GPS Location 保持开启。
- GPS is always required; allow location in the OS/browser and keep Settings → GPS Location on.
- 照片为必填，客户端压缩至 ≤ 2MB JPEG。
- A photo is required; the client compresses images to ≤ 2MB JPEG.
- 仅 Active 状态工人可被打卡；Inactive 不可选。
- Only Active workers can be punched; Inactive workers cannot.

5. 现场人员与历史 / 5. Onsite & History

5.1 在场名单 Onsite · 5.1 Onsite list

Overview 显示 ONSITE 人数与在场工人列表。可从列表快速签退（Out）。桌面端可查看 Latest activity。

Overview shows the ONSITE count and current workers. Use Out for a quick check-out. Desktop also shows Latest activity.

5.2 考勤历史 · 5.2 Attendance History

导航「Attendance History / 历史」查看近期进出记录。非管理员默认最多约 14 天；管理员报表可查至约 92 天。

Open Attendance History for recent in/out records. Non-admins typically see up to ~14 days; admin reports can cover up to ~92 days.

6. 人力名册 / 6. Manpower

「Manpower / 人力」列出工人、公司、工种与状态（Active / Inactive）。所有角色可搜索查看；仅项目管理员可新增与启停。

Manpower lists workers, company, trade, and status (Active / Inactive). All roles can search; only Project Admins can add or activate/deactivate.

项目管理员：新增工人 · Project Admin: add a worker

1. 点击「+ Add」。

Tap + Add.

2. 填写 Worker ID (后四位)、Full name、Company、Trade。
Enter Worker ID (last four digits), Full name, Company, Trade.
3. 保存后工人状态为 Active，即可被签到。
After save the worker is Active and can be checked in.
4. 不再雇佣时使用 Deactivate；需要时可再 Activate。
Use Deactivate when no longer employed; Activate again if needed.

7. 管理功能 / 7. Administration

以下功能仅 Project Admin 可见：User access (用户权限) 与 Reports (报表)。
The following are visible only to Project Admins: User access and Reports.

7.1 用户权限 User access · 7.1 User access

1. 打开 ADMINISTRATION → User access。
Open ADMINISTRATION → User access.
2. 点击「+ Invite」，创建管理账号并选择角色，私下告知临时密码。
Tap + Invite, create the account, choose a role, and share the temporary password privately.
3. 账号状态可能为 Active / Temporary password / First login required。
Status may show Active / Temporary password / First login required.
4. 用户忘记密码时，对其点击 Reset 生成新的临时密码 (不可重置其他 Project Admin)。
If a user forgets the password, tap Reset for a new temporary password (not for other Project Admin rows).

7.2 报表与 CSV · 7.2 Reports & CSV

1. 打开 Reports，选择 From / To 日期，点击 Run report。
Open Reports, set From / To dates, then Run report.
2. 查看 TOTAL MOVEMENTS、CHECK INS、TOTAL HOURS，以及按工种、班次与进出明细。
Review TOTAL MOVEMENTS, CHECK INS, TOTAL HOURS, plus by-trade, shifts/hours, and movements.
3. 点击 CSV
导出：含日期时间、工人、工号后四位、公司、工种、事件、备注、记录人、GPS、围栏结果、照片与工时等。
Tap CSV to export date/time, worker, ID last 4, company, trade, event, remarks, recorder, GPS, geofence, photo, and shift hours.

8. 设置 / 8. Settings

「Settings / 设置」提供工作区入口与系统偏好。
Settings provides workspace links and preferences.

项目 Item	说明 Description
History / Manpower / All Projects	工作区快捷入口 Workspace shortcuts
Reports / User access	管理员功能 (按角色显示) Admin-only when permitted
Platform Console	仅平台管理员 Platform admin only
Languages	English / 简体中文
GPS Location	必须开启以完成打卡 Required for punches
Offline Mode	默认开启；弱网时排队同步 On by default; queues punches
Sign Out	退出登录 End the 12-hour session

离线说明：打卡会写入本地队列（pending → uploading → synced / failed），应用启动、恢复联网及每 60 秒自动同步。界面可能显示「Syncing N offline punch(es)…」。

Offline note: punches are queued locally (pending → uploading → synced / failed) and sync on app start, when online, and every 60 seconds. A banner may show Syncing N offline punch(es)...

9. 平台控制台 / 9. Platform Console

平台管理员在 Settings → Platform Console，或直接访问 /platform、/console。

Platform admins open Settings → Platform Console, or go to /platform or /console.

1. Choose company: 选择或 + Add company 新建客户公司。

Choose company: select or + Add company.

2. 维护该公司下的 Projects（项目）。

Maintain Projects under that company.

3. Customer Admins: Create admin account，为客户创建 Project Admin。

Customer Admins: Create admin account for a customer Project Admin.

4. 将登录地址与临时密码交给客户管理员；其登录后邀请现场主管并录入人力。

Share the sign-in URL and temporary password with the customer admin; they then invite supervisors and add manpower.

10. 常见问题 / 10. Troubleshooting

问题 Issue	处理 Resolution
无法定位 / No GPS	开启手机定位与浏览器权限；Settings → GPS Location 打开。Enable OS/browser location; turn on GPS Location in Settings.
Outside site 无法提交	移动至工地围栏内；若非严格模式仍可记录 Off site。Move inside the geofence; non-strict mode may still record Off site.
无法拍照	允许相机/相册权限；照片为必填。Allow camera/photos; a site photo is required.
离线未上传	保持 Offline Mode；联网后等待自动同步横幅消失。Keep Offline Mode on; wait for auto-sync when online.
临时密码失效	联系项目管理员 Reset；须在 7 天内首次改密。Ask Project Admin to Reset; change password within 7 days.
会话过期 Signed out	会话约 12 小时，请重新登录。Sessions last about 12 hours; sign in again.
工人搜不到	确认 Manpower 中为 Active，且工号/姓名正确。Ensure the worker is Active and the ID/name is correct.

如需技术支持，请联系项目管理人员或平台运营方。本文档对应 Hubble Fields 考勤应用 v0.1。

For support, contact your project administrator or platform operator. This guide matches Hubble Fields attendance app v0.1.