



# OM Plus Delivery Manager (DM)

User Guide and Technical Reference

*Enterprise Output Management Software*

*Streamline Print Operations and Enhance Document Delivery*

## NOTICES

### COPYRIGHT NOTICE

Copyright © 2003-2024 by Plus Technologies All rights reserved. Any other use is prohibited. No part of this book may be reproduced or transmitted in any form or by any means, electronic or mechanical, without the written permission of Plus Technologies This includes photocopying, recording, or an information storage and retrieval method, including posting to the Internet.

OM Plus™ is undergoing continual revision, refinement, and expansion in order to include additional features. This documentation is believed to be accurate and reflects the product at the time of publication.

However, Plus Technologies assumes no responsibility for its use or for any infringements of patents or other rights of third parties that may result from its use. Plus Technologies reserves the right to change this product at any time without notice.

### TRADEMARKS

OM Plus, Context Delivery, Report Bundler, Report Distributor, PD Plus, Fleet Manager and LP Plus are trademarks of Plus Technologies. All other products and company names are trademarks of their respective companies.

SAP is a registered trademark of SAP AG.

All other company and product names may be trademarks of their respective owners. The information contained herein is subject to change without notice.

### PUBLISHED BY

Plus Technologies

1860 Lyons Road Dayton, OH 45458 USA

Web: [www.plustechnologies.com](http://www.plustechnologies.com) Telephone: +1. 877.899.7587

## USING THIS GUIDE

Plus Technologies is always interested in improving the quality of the software documentation. If any errors or omissions are discovered in this guide, or if you have any improvements suggestions, e-mail specifics comments to Plus Technologies at [support@plustechnologies.com](mailto:support@plustechnologies.com). It is possible to send comments anonymously, or to provide complete contact information so we may contact you. Your input is solicited and welcome.

## USING THE PDF VERSION OF THIS GUIDE

A portable document format (PDF) version of this guide is located in the Help folder in the OM Plus installation directory. To open the PDF guide, Adobe Acrobat Reader version 4.0 or higher must be installed on the computer. The latest version of Acrobat Reader can be downloaded from [www.adobe.com](http://www.adobe.com) at no charge.

With Adobe Acrobat Reader it is possible to display, search, copy, print pages, and click hyperlinks. It is also possible to click headings or page numbers in the table of contents or references in the text to display those headings or pages.

For help using PDF files, from the Adobe Acrobat Reader **Help** menu, click **Reader Help** or **Reader Guide**, depending on which version of Reader is installed.

## CONTACTING PLUS TECHNOLOGIES CUSTOMER SUPPORT

If you have questions about OM Plus and are unable to find answers in this guide, contact Plus Technologies in one of the following ways:

- Web: [www.plustechnologies.com](http://www.plustechnologies.com)
- Telephone: +1.937.847.0614
- US Toll Free: +1.877.899.7587
- Fax: +1.937.384.0842

Plus Technologies Support is available Monday through Friday from 8:00 A.M. to 8:00 P.M., Eastern Time (GMT -5 hours), except on certain U.S. holidays. They are Memorial Day, July 4<sup>th</sup>, Labor Day, Thanksgiving Day, Christmas Eve and Day and New Year's Day.

Additional 24x7 support packages are available.

## TABLE OF CONTENTS

|                                                     |    |
|-----------------------------------------------------|----|
| Notices.....                                        | 2  |
| Trademarks.....                                     | 2  |
| Copyright Notice.....                               | 2  |
| Published By .....                                  | 2  |
| Using this guide .....                              | 3  |
| Using the PDF Version of This Guide.....            | 3  |
| Contacting Plus Technologies Customer Support.....  | 3  |
| Introducing OM Plus Delivery Manager .....          | 14 |
| Overcoming Existing System Limitations .....        | 14 |
| Managing the Delivery of Enterprise Documents ..... | 14 |
| Using Advanced Document Delivery.....               | 15 |
| Ease of use.....                                    | 16 |
| Server Requirements .....                           | 16 |
| Client Requirements .....                           | 16 |
| Getting Started With OM Plus .....                  | 16 |
| OMHOME and LPHOME Environment Variables.....        | 17 |
| Installing OM Plus.....                             | 17 |
| Installing on Windows .....                         | 17 |
| Installing on UNIX/Linux .....                      | 20 |
| Installing the OM Plus client .....                 | 23 |
| Installing on Windows .....                         | 23 |
| Configuring the First OM Plus Destination .....     | 23 |
| Configuring on Windows .....                        | 23 |
| Configuring on UNIX/Linux.....                      | 24 |
| Sending Requests to OM Plus .....                   | 25 |
| Sending Requests from Windows.....                  | 25 |
| Sending Requests from UNIX.....                     | 25 |
| Sending Requests Using LPD on Windows and UNIX..... | 25 |

|                                                 |    |
|-------------------------------------------------|----|
| Linking OM Plus to UNIX LP (or LPR).....        | 26 |
| Working with the OM Plus Client Interface ..... | 26 |
| Installation .....                              | 26 |
| Destinations .....                              | 26 |
| Classes .....                                   | 26 |
| Using Define Destination .....                  | 29 |
| Dynamic Class Maintenance .....                 | 40 |
| Group Maintenance .....                         | 40 |
| Types .....                                     | 43 |
| i-Sat .....                                     | 43 |
| Notification Addresses .....                    | 45 |
| Epic Print Records .....                        | 45 |
| System .....                                    | 47 |
| Advanced Forms .....                            | 47 |
| Forms Maintenance .....                         | 49 |
| Health Check (UNIX only) .....                  | 52 |
| Working With Remote Host Setup .....            | 52 |
| Registration Status .....                       | 53 |
| RID Spans Setup .....                           | 54 |
| System Settings .....                           | 55 |
| System Status .....                             | 59 |
| Client .....                                    | 60 |
| Client Settings .....                           | 60 |
| Security .....                                  | 63 |
| Using Security Groups .....                     | 63 |
| Setting up Permission Models .....              | 64 |
| Creating Security Groups .....                  | 65 |
| Adding Users to Groups .....                    | 68 |
| Adding Remote Users (Host/Domain) .....         | 69 |

|                                                      |    |
|------------------------------------------------------|----|
| User List .....                                      | 70 |
| Adding Login Users .....                             | 71 |
| Security in Distributed Environments .....           | 71 |
| OM Plus Status screen.....                           | 72 |
| Understanding Client Specific Information .....      | 72 |
| Using the Hosts Menu .....                           | 73 |
| Sorting Requests .....                               | 73 |
| Viewing Requests .....                               | 74 |
| Using DccView (File View) .....                      | 74 |
| Viewing Request Status and Destination Details ..... | 75 |
| Understanding Request Statuses .....                 | 76 |
| Accessing Command Selections .....                   | 77 |
| Using Request Commands .....                         | 77 |
| Canceling Requests .....                             | 77 |
| Changing Print Control Files .....                   | 77 |
| Copying Requests .....                               | 78 |
| Changing Destinations .....                          | 78 |
| Changing Email Addresses .....                       | 78 |
| Changing Fax Numbers .....                           | 78 |
| Changing Form Files .....                            | 79 |
| Display Parent/Child Information .....               | 79 |
| Holding Requests .....                               | 80 |
| Keeping Requests .....                               | 80 |
| Logfile Display .....                                | 80 |
| Mounting Forms .....                                 | 80 |
| Changing Copy Counts .....                           | 81 |
| Changing Priorities .....                            | 81 |
| Purging Requests .....                               | 81 |
| Releasing Requests .....                             | 81 |
| Restarting Requests .....                            | 82 |

|                                           |    |
|-------------------------------------------|----|
| Printer Status .....                      | 82 |
| Suspending Requests .....                 | 82 |
| Tracing Status Requests .....             | 82 |
| Viewing Requests .....                    | 83 |
| Changing the Banner Status.....           | 83 |
| Changing Advanced Form Files .....        | 83 |
| Setting Scheduled Printing .....          | 83 |
| Changing Titles .....                     | 84 |
| Updating Options .....                    | 84 |
| Using Destination Commands .....          | 84 |
| Accepting Requests .....                  | 84 |
| Attaching Terminals (UNIX Only) .....     | 84 |
| Disabling Destinations .....              | 85 |
| Dynamic Class Maintenance .....           | 85 |
| Enabling Destinations .....               | 85 |
| Getting Daemon/Service Information .....  | 85 |
| Mounting Forms .....                      | 86 |
| Logfile Display .....                     | 86 |
| Print Test Page .....                     | 86 |
| Printer Status .....                      | 86 |
| Printer Properties .....                  | 87 |
| Rejecting Requests .....                  | 87 |
| Selecting Translation Tables .....        | 87 |
| Launching Destinations URLs .....         | 87 |
| Using Lookup Commands .....               | 88 |
| All Requests for all Destinations .....   | 88 |
| Disabled Destinations (Client only) ..... | 88 |
| Form .....                                | 88 |
| Groups (Client only) .....                | 88 |
| Requests for Selected Destinations .....  | 88 |

|                                                              |     |
|--------------------------------------------------------------|-----|
| Status .....                                                 | 88  |
| Title .....                                                  | 88  |
| User .....                                                   | 88  |
| Goto Page (Character-based only) .....                       | 88  |
| Remote Hosts .....                                           | 89  |
| OM Plus Archive System.....                                  | 89  |
| Activating and Configuring OM Plus Archive .....             | 89  |
| Days remaining in the trial period .....                     | 89  |
| Archive Directory .....                                      | 89  |
| Temporary Directory .....                                    | 90  |
| How long should archive files be kept .....                  | 90  |
| How often should a new archive subdirectory be created ..... | 90  |
| How long should files be kept in the temp directory .....    | 90  |
| Archiving Reports .....                                      | 91  |
| From the Command Line .....                                  | 91  |
| The LPPARCHIVE Environment Variable .....                    | 91  |
| From the Request Status Screen .....                         | 91  |
| Querying Archived Reports .....                              | 92  |
| Cleaning up the Archive and Temporary Directories .....      | 92  |
| Document Conditioning Components .....                       | 93  |
| Context Delivery .....                                       | 93  |
| Defining Search Criteria in Context Delivery .....           | 93  |
| Spooling with Context Delivery Plus.....                     | 93  |
| Decreasing Spooling Time .....                               | 96  |
| Report Bundler .....                                         | 97  |
| Configuring Report Bundler .....                             | 97  |
| Spooling with Report Bundler Plus .....                      | 99  |
| Report Distributor .....                                     | 100 |
| Understanding Report Distributor .....                       | 100 |
| Defining Search Criteria in Report Distributor .....         | 100 |



|                                                                               |     |
|-------------------------------------------------------------------------------|-----|
| Nomatch or Lastmatch .....                                                    | 102 |
| Logical Operators .....                                                       | 102 |
| Configuring Multiple OM Plus Installations in a Distributed Environment ..... | 104 |
| Starting Remote Services .....                                                | 104 |
| Starting on Windows .....                                                     | 104 |
| Starting on UNIX.....                                                         | 104 |
| Broadcasting Defined Destinations .....                                       | 104 |
| Receiving Broadcasted Destinations .....                                      | 105 |
| Advanced settings .....                                                       | 105 |
| Spooling to Remote Destinations .....                                         | 105 |
| Editing the receiveHosts and sendHosts Files .....                            | 106 |
| Alias .....                                                                   | 106 |
| Send to any/Receive from any .....                                            | 106 |
| Proxy .....                                                                   | 106 |
| Adding/Removing Servers .....                                                 | 107 |
| Save .....                                                                    | 107 |
| OM Scan Service .....                                                         | 108 |
| Starting OM Scan Service .....                                                | 108 |
| Configuring OM Scan Service .....                                             | 109 |
| Initial settings .....                                                        | 109 |
| Folder Scans .....                                                            | 110 |
| Email Scans .....                                                             | 111 |
| Database .....                                                                | 112 |
| R-3/SAP BCXOM Interface .....                                                 | 113 |
| Configuring SAP .....                                                         | 113 |
| Importing SAP Configuration .....                                             | 113 |
| SAP Real OMS Configuration .....                                              | 114 |
| SAP Logical OMS & Commands Configuration .....                                | 115 |
| SAP Device Configuration for OM Plus .....                                    | 122 |
| Setting up the OM Plus RID Span .....                                         | 123 |

|                                             |     |
|---------------------------------------------|-----|
| Configuring OM Plus for SAP Callbacks ..... | 125 |
| Sample .....                                | 126 |
| Command Reference .....                     | 128 |
| DCCSAPSUB .....                             | 128 |
| DCCSAPSTAT .....                            | 129 |
| Command Reference .....                     | 130 |
| arcadmin .....                              | 130 |
| buildhtml .....                             | 131 |
| dccaccept .....                             | 132 |
| dccadmin .....                              | 133 |
| dccasweep .....                             | 134 |
| dccbkadmin .....                            | 135 |
| dccbkst .....                               | 136 |
| dccbkstshut .....                           | 137 |
| dcccancel .....                             | 138 |
| dccdestchg .....                            | 139 |
| dccdisable .....                            | 140 |
| dcce2enot .....                             | 141 |
| dcce2eser .....                             | 142 |
| dccenable .....                             | 143 |
| dccfree .....                               | 144 |
| dccgdisable .....                           | 145 |
| dccgenable .....                            | 146 |
| dccgrp .....                                | 147 |
| dccgsuspend .....                           | 149 |
| dcchealth .....                             | 150 |
| dccinfo .....                               | 151 |
| dcclogmsg .....                             | 153 |
| dcclogrep .....                             | 154 |
| dcclp .....                                 | 156 |

|                        |     |
|------------------------|-----|
| dcclpdser .....        | 159 |
| dcclpdshut .....       | 160 |
| dcclplink .....        | 161 |
| dcclpr .....           | 162 |
| dcclpunlink .....      | 163 |
| dccmount.....          | 164 |
| dccmsghelp.....        | 165 |
| dccnetstat.....        | 166 |
| dccprtval.....         | 167 |
| dccqval.....           | 168 |
| dccrange.....          | 169 |
| dccredit.....          | 170 |
| dccreject.....         | 171 |
| dccreset.....          | 172 |
| dccsapstat.....        | 173 |
| dccsapsub.....         | 174 |
| dccscan (UNIX).....    | 175 |
| dccscan (Windows)..... | 176 |
| dccsched.....          | 177 |
| dccshut.....           | 178 |
| dccstat.....           | 179 |
| dccstatdef.....        | 180 |
| dccsuspall.....        | 181 |
| dccsuspend.....        | 182 |
| dccswitch.....         | 183 |
| dccview.....           | 184 |
| disable.....           | 185 |
| enable.....            | 186 |
| hexdump.....           | 187 |
| installcdplus.....     | 188 |

|                                   |     |
|-----------------------------------|-----|
| lpadmin.....                      | 189 |
| lplinkonly.....                   | 192 |
| lppusers.....                     | 193 |
| lpstat.....                       | 194 |
| omlogusers.....                   | 195 |
| ompremove.....                    | 196 |
| omqdepth.....                     | 197 |
| omremsetup.....                   | 198 |
| omresolve.....                    | 200 |
| OM Plus Event Processing .....    | 201 |
| Using Windows Event Scripts ..... | 201 |
| Using UNIX Event Scripts .....    | 203 |
| Environment Variables .....       | 204 |
| ACCEPTUNKNOWN .....               | 204 |
| COPYBREAK .....                   | 204 |
| DATATYPE .....                    | 204 |
| FILEBREAK .....                   | 204 |
| HOLDPRINTED .....                 | 205 |
| LPDEST .....                      | 205 |
| LPDGRAPHICS .....                 | 205 |
| LPPATTR .....                     | 205 |
| LPPAUTO .....                     | 206 |
| LPPAUTOMODE .....                 | 206 |
| LPPCONFIRM .....                  | 206 |
| OMPLUSACK .....                   | 206 |
| PRTCNTL .....                     | 207 |
| PTPARENT .....                    | 207 |
| SILENT.....                       | 207 |
| VIEW80 .....                      | 207 |

---

|                                         |     |
|-----------------------------------------|-----|
| VIEW132 .....                           | 208 |
| VIEWCOL .....                           | 208 |
| WHEN .....                              | 208 |
| Working with the Logfile .....          | 209 |
| Viewing the Logfile Display .....       | 209 |
| Viewing Windows Logfiles .....          | 210 |
| System Log .....                        | 210 |
| Understanding the log details .....     | 210 |
| Setting Logfile Limits.....             | 212 |
| Viewing Port Monitor Logfiles .....     | 212 |
| Viewing UNIX or Linux Logfiles .....    | 212 |
| System Logs .....                       | 212 |
| Customizing the Logs .....              | 213 |
| Understanding UNIX Logfile Limits ..... | 213 |
| Viewing System Messages .....           | 213 |
| Viewing Accounting Logfiles .....       | 213 |
| Setting Email Notification .....        | 216 |
| Data Types .....                        | 218 |
| Destination Details Screen .....        | 219 |
| Request Details screen .....            | 221 |

## INTRODUCING OM PLUS DELIVERY MANAGER

OM Plus Delivery Manager, the document output management software solution from Plus Technologies, provides advanced delivery and control of documents across complex network environments to multiple destination types. These destination types include printers, fax systems, email systems, web sites and intranet sites. Additionally, OM Plus Delivery Manager provides robust, streamlined destination management.

Companies depend on the creation and delivery of documents such as reports, checks, bills of lading, invoices and pick tickets. Typically, these documents are then handed off by the business application to the operating system for delivery (traditionally, to a printer). Unfortunately, operating systems, such as Windows, UNIX or Linux have not been designed to handle the production delivery of documents across an enterprise. These operating system limitations may impact company business and add unnecessary support costs.

## OVERCOMING EXISTING SYSTEM LIMITATIONS

Due to the limitations of existing operating systems, problems arise with reliable and confirmed document delivery, centralized management and control, document integration with electronic forms, and the supportability of the entire enterprise's document-delivery systems. Documents are lost, not delivered correctly or in a timely manner, and customer satisfaction or business processes suffer.

## MANAGING THE DELIVERY OF ENTERPRISE DOCUMENTS

OM Plus receives documents from a variety of systems in a variety of formats. It manages the reliable delivery of the documents to multiple destination types including , printers, fax servers, email servers, Web sites, and Intranet sites without any changes to the enterprise application. The application prints and OM Plus completes the rest.

Companies with large enterprise application implementations will create large volumes of documents. OM Plus is designed to manage all aspects of the document delivery process within the enterprise and solve document delivery problems.

OM Plus runs on all popular server operating systems including, commercial Microsoft, UNIX, and Linux/open-source servers. OM Plus is designed to be robust, efficient, as well as simple to install and run. Installations take less time than similar solutions because many of the functions are automated. This ease of installation and use is a major difference from other enterprise management products. In most cases OM Plus does not require changes to the host applications because it replaces or co-exists with the print subsystem of the operating system. When the application calls the native spooling system it is really calling OM Plus. OM Plus is compliant with most ERP applications, including SAP, PeopleSoft, Oracle, QAD and more. OM Plus is fully SAP<sup>TM</sup> R/3 certified.

### USING ADVANCED DOCUMENT DELIVERY

OM Plus provides advanced document delivery of enterprise documents. The wide-ranging document delivery feature set includes:

- Integrated delivery to printers, fax servers, email servers, web sites and Intranet sites based document data or other spool file information.
- Automatic routing of jobs to the backup server, if the primary server becomes unavailable.
- Confirmation of job delivery.
- Automatic notification (email or pager notification or job re-routing) if destinations become disabled or if job delivery fails (or other customer identified events).
- With many devices, OM Plus can provide advanced delivery confirmation, not just printer buffer acceptance of data, but print function completion status.
- Scalable upward and downward (for example > 4000 destinations and hundreds of thousands of daily print jobs on a single system).
- Comprehensive audit logs of every function and process involved in the print process involved in the print process (logs also include information regarding destination use, individual and group accounting and more).
- An open, easy-to-use client interface that reflects job and destination status on a single screen and provides control with a rich tool set for administration.
- SNMP capability to query destination status.
- Printer web server access from within OM Plus.
- Security features to control end user access to functions, documents and devices (security can be set at individual or group levels).
- Encryption capabilities between OM Plus servers.
- Job scheduling and load balancing.
- Delayed print purging to enable re-printing of documents without having to re-create them from within the application.
- Re-start, re-direct and re-print capabilities.
- Support for rich content documents including page range and next page capabilities.
- Automatic delivery of multiple copies or portions of documents.

## EASE OF USE

OM Plus has multiple end user interfaces including a Client interface, Browser interface and terminal interface for UNIX users.

The Client interface runs on any Java Runtime Environment (JRE)-capable computer and supports JRE 1.5 or higher.

The Browser interface allows access to the application from any browser.

There is a character-based (“green screen”) interface with list menus for UNIX terminals.

*The Browser interface is available as an add-on application to OM Plus. For information, contact your Plus Technologies Account Manager.*

## SERVER REQUIREMENTS

OM Plus Server supports Windows Server 2012 – 2022, as well as most commercial UNIX operating systems including, Sun Solaris 8, 9, 10 and 11, HP-UX 11.x and greater, IBM AIX 5.1 and greater, Red Hat Enterprise Linux version 7 and greater, Red Hat AS/ES 3.0 and greater open source operating systems and other comparable Linux operating systems.

On Windows, the minimum system requirements are a 2+ GHz processor, with 4+ GB of RAM and 80+ GB of disk space. Disk space requirements vary based on document volume and length of time before purging documents.

For UNIX, the minimum system requirements include 128MB of memory, a 500 MHz processor and 500 MB of disk space, plus space for spool files. Disk space requirements vary based on document volume and length of time before purging documents.

## CLIENT REQUIREMENTS

The OM Plus Client supports any Windows operating System that is 64bit and supported by Microsoft. To ensure proper performance, install the OM Plus Client on a computer/OS minimum requirements.

The OM Plus Client can also be installed on many Unix and Linux distributions with a graphical desktop.

## GETTING STARTED WITH OM PLUS

OM Plus is a powerful yet user friendly output management software platform that system administrators can use to manage printing, resolve problems and provide additional functionality to the output process. Users can also use the system to manage their own output environment. OM Plus has complete security and is easy to integrate into most systems to provide quick access and control of the output. OM Plus can also allow for the viewing of requests, allow for rules or administrator to decide whether or not to print, to print select pages, cancel requests, move requests to other destinations and more. In each case OM Plus can provide the power and ease of use needed to manage any output environment.



With any new software product there is a learning curve to overcome before effectively using it. OM Plus was made to be as easy-to-use and comprehensive as possible.

Before beginning, review the following information:

**Server:** Manages the output

**Client:** Allows for user interface with the OM Plus Server

Installing OM Plus does not disturb current printing jobs. OM Plus is a separate delivery system that can be configured to work entirely independently of the native spooling system. In many cases, OM Plus is configured to work in conjunction to the native system.

## OMHOME AND LPHOME ENVIRONMENT VARIABLES

The OMHOME and LPHOME environment variables, set by OM Plus, are very important to system operation. OMHOME is used on Windows operating systems. LPHOME is used on UNIX and Linux operating systems. These variables are set to the fully qualified path name of the folder or directory where OM Plus is installed.

If OM Plus is installed in the default location, the values include:

| Operating System | Variable Name | Default Value             |
|------------------|---------------|---------------------------|
| Windows          | OMHOME        | C:\Plustech\omplus\server |
| UNIX             | LPHOME        | /usr/lppplus              |

If OM Plus is not installed in the default folder or directory, it can be located from the command line by issuing the following:

| Operating System | Command       |
|------------------|---------------|
| Windows          | echo %OMHOME% |
| UNIX             | echo \$LPHOME |

*Throughout this guide will be references to these variables. These variables are interchangeable and represent the default values listed for each operating system unless otherwise indicated. For example, if %OMHOME% is printed for Windows, it is possible to replace it with \$LPHOME for UNIX.*

## INSTALLING OM PLUS

### INSTALLING ON WINDOWS

OM Plus can be installed on Windows Server 2012- latest, Windows 10 and Windows 11.

To install OM Plus Server on Windows, complete these steps:

1. Navigate to the directory containing the OM Plus install file and execute it.
2. When prompted, select the folder to select the installation directory.
3. The installation will complete.

*If the installation directory is changed, make sure there are no spaces in the path. For example, changing the folder name to C:\Progam Files (with a space) would cause a problem.*

## STARTING THE OM PLUS WINDOWS SERVICES


OM Plus adds the following services to Windows:

- omAdminServ
- omDir2Email
- omLPDServ
- iSat
- iSATServ
- ome2eServ
- ompLogServ
- omspoolServ
- ompServ
- omRemoteServ
- omScanServ
- omschedServ
- omstatusServ
- ommsemailclient

Once installation is complete OM Plus can be accessed and utilized.

To access OM Plus, complete these steps:

1. From the Windows **Start** menu, **Plus Technologies OM Plus DM** and then **OM Plus DM Server**.




The OM Plus for Windows screen appears.

2. Click **Install All**

Green boxes with check marks appear in the Installed column.

### 3. Click **Start All**

The screen now appears similar to the following.



*The lpdServ is the OM Plus LPD listener. If it is not expected that this system will receive print jobs using this port, it is not necessary to have this service running. Also, it is common to find the default LPD port (515) blocked by a firewall or anti-virus or being used by the native Windows LPD Listener.*

*The iSat Client, Server and Scan Service will not start as part of the “Start All” function as typically, it is not needed.*

## CHANGING THE WINDOWS ENVIRONMENT

OM Plus also makes changes to the Windows environment. For example, it adds the system environment variable, OMHOME, which is the location of the OM Plus installation (the default is C:\plustech\omplus\server)

## INSTALLING OVER AN EXISTING VERSION

If an existing version of OM Plus is already installed on Windows and it is time to upgrade or install a new version, the new version can be installed while retaining all the user definitions set in the existing version. To do this, the services must first be stopped, and the existing version must be uninstalled using the following settings.

To install over an existing version, complete these steps:

1. From the Windows **Start** menu, select **Plus Technologies OM Plus DM** and then **OM Plus DM Server**.

The OM Plus for Windows screen appears.

2. Click **Remove All** to stop and remove all services.

Empty red boxes appear in the columns.

3. From the Windows Start menu, select **Plus Technologies OM Plus DM** and then uninstall **OMPlus DM Windows Server**. The Uninstall screen appears.
4. Select Keep all user definitions (destinations, etc.), and then click Uninstall.

The OM Plus Server is no longer installed, but all user definitions remain intact.

5. Install the new version of OM Plus, and then restart all services. For installation information, refer to installing on Windows.

## INSTALLING ON UNIX/LINUX

OM Plus Delivery Manager can be installed on most commercial UNIX and Linux operating systems including, Sun Solaris 8, 9 and 10, HP-UX 11.x and greater, IBM AIX 5.1, 5.2 and greater, Red Hat Enterprise Linux Version 7 and greater, Red Hat AS/ES 3.0 and greater open source operating systems and other comparable Linux operating systems.

The OM Plus Delivery Manager installation process uses the `uncompress` command. Please ensure that the system is able to use this utility is installed or that a compatible utility has been linked in its place. To install properly, you must be logged in as root.

1. Download the appropriate install package for the system.
2. Unpack the package into an empty directory.
3. Run the following command:

```
./ominstall
```

```
(./OMINSTALL\;1 for HP systems)
```

And follow the install prompts

4. To start services, type **dccadmin > Services > Click Enter** on the services to start

*To ensure that the LPHOME environment variable is properly set you must log out and in again.*

## STARTING THE DAEMONS

For information on the daemons associated with OM Plus, refer to the following table.

| Daemons      | Description                                                                                                                   |
|--------------|-------------------------------------------------------------------------------------------------------------------------------|
| Admin Server | Performs administrative system functions. The client requires this to function correctly. To run, issue the dccbkadm command. |
| LPD Server   | Receives requests from other hosts using the LPD/LPR Protocol. To run, issue the dcclpdser command.                           |

|                |                                                                                                                                                                                     |
|----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Network Status | Used for remote communication. The client requires this to function correctly. To run, issue the dccbkst command.                                                                   |
| OM Plus Server | Receives requests from other OM Plus application. To run, issue the dcompser command.                                                                                               |
| Scheduler      | Dispatches requests. OM Plus requires this to function correctly. To run, issue the dccshed command.                                                                                |
| Remote Service | Transfer printer definitions between OM Plus Servers. This service must be started from the command line by issuing the dccpingrem command. To stop it, the process must be killed. |
| iSat Service   | Receives requests via the OMGateway for remote iSats (internet print client).                                                                                                       |
| IPP Service    | Receives inbound IPP Protocol print jobs.                                                                                                                                           |

*The OM Plus Interface and System-to-System communication relies on IP listeners. There must be clear network communication for that functionality. In the event of an error please check firewall setting and make sure those ports are not blocked.*

## STARTING THE DAEMONS AT BOOT TIME

The daemons can be set to execute automatically at boot time so the spooling services are automatically available. To do this make symlinks in the rc startup and the init d directory.

To set the daemons to start at boot time, run the following command:

```
# dcclplink
```

## SETTING THE UNIX ENVIRONMENT

For OM Plus to function properly, the environment variable LPHOME must be set to the base OM Plus directory (for example, /usr/lppplus) and the path must contain an entry for the OM Plus applications (for example, /usr/lppplus/bin). During the OM Plus installation, an entry is placed in the /etc/profile. To determine if the environment is set to use OM Plus, from the command line, enter #env.

The following example appears displaying the **env** command output with the OM Plus variables indicated in bold.

```
HOME=/
```

```
HZ=100
```

```
LOGNAME=root
```

```
LPHOME=/usr/lppplus
```

```
LPPCONFIRM=
```

```
MAIL=/var/mail/root
```

```
NONAMESERVER=1
```

```
PATH=/sbin:/usr/sbin:/usr/bin:/etc:/usr/lppplus/bin
```

```
TERM=vt100
```

TERMCAP=/etc/termcap

TZ=EST5EDT

---

## STARTING THE OM PLUS UNIX SERVICES

In addition to the environment variables, OM Plus adds the following lines to the services file.

|           |           |
|-----------|-----------|
| dccbkst   | 53971/tcp |
| OM Plus   | 53972/tcp |
| dcce2eser | 53973/tcp |
| dccbkadm  | 53974/tcp |
| dccpingr  | 53975/tcp |

---

## INSTALLING OVER AN EXISTING VERSION ON UNIX

If OM Plus is already installed on UNIX the new version can be installed while retaining all the user definitions set in the existing version. To install over an existing version, first stop all services (daemons) and then install the new version. To stop the daemons, run `dccadmin` and then from the services menu select the services to stop. For information, refer to `dccadmin`. Once all daemons are stopped, proceed to installing to UNIX.

*Before performing an update or in place re-install, be sure to back up the `$LPHOME` directory in order to be able to restore the original installation in case of any unforeseen events.*

## INSTALLING THE OM PLUS CLIENT

### INSTALLING ON WINDOWS

Execute the provided OM Plus DM Client installation file. The installation process will prompt for the location to install to, default is C:\PlusTech\OMPlus\Client3\. After the files have been put in place, the installer will open a configuration window to the “Hosts” tab. Enter the name of the OMPlus server or servers to connect to using the “Add” button in the lower right, click “Save” in the lower left and then exit. The OM Plus Client installation is now complete.

## CONFIGURING THE FIRST OM PLUS DESTINATION

### CONFIGURING ON WINDOWS

Configuring a destination in Windows consists of two parts, the second of which is optional. First, a destination must be created and then, if desired, it may be linked to a Windows print queue.

The main advantage of “linking” to a Windows printer is that it allows native Windows applications to use Windows default spooler to enter jobs into OM Plus. Also, it allows for easier printer sharing in a Windows environment.

Even if a destination is linked to a Windows printer, jobs can be spooled directly to that destination using the command line. Also, a destination may be linked to more than one Windows printer.

### CREATING A DESTINATION

To configure the first OM Plus destination on Windows, Click on Windows Start Menu > Plus Technologies OM Plus > OM Plus Administration > Destinations > Destination. The OM Plus Destination screen will be displayed.


To create a new destination, select “Destinations” under the host name you wish to create the destinations on and then click “New” in the bottom left corner. A window will appear asking for a name and the type of destination to be configured. Select a type and then input the required information.

For a first destination, Plus Technologies recommends using a Network Printer running in Raw TCP mode. The address in this case can be the IP address or resolvable host name for printer and the port should be 9100. Once this has been configured, select “Finish” to create the destination.

### LINKING A WINDOWS PRINTER

To Link a Windows Printer Definition to an OM Plus Destination, complete these steps:

From the Windows Start Menu > Plus Technologies OM Plus DM > OM Plus DM Queue Linker



On the left side are the Windows printers and the right the OM Plus destinations. Click on the Windows printer and the corresponding printer from the OM Plus side, then click the button create link. The port name will change from the IP address to a Plustech port.

## CONFIGURING ON UNIX/LINUX

1. From the command line, enter **dccadmin** to define an OM Plus destination.

```

OM Plus Destination Configuration Menu

Destination Name      [ ]

Destination Mode      [ ]

UNIX Device          [ ]

Pull Mode Printer ?  [n]

Comments             [ ]

Enter the name you wish to use for this destination.

F1=Adv F2=Classes F3=Save F4=Choices F5=Del F6=net F7=Groups ESC=Exit ?=Help
    
```



2. Using the **Enter** key, from the **Setup** menu select **Destination Configuration**.
3. In the following fields, provide the appropriate information.
  - **Destination Name:** Enter a name between 1 and 50 characters, without spaces, to be assigned to this destination.
  - **Destination Mode:** Enter `termserv`
  - **UNIX Device:** Enter the hostname or IP address of the network printer followed by an exclamation point (!), and then the number 9100 (for example, `printer!9100`). This combination of mode and device will work for typical network printers.
4. Press **F3** to save the destination, and then **Esc** to exit.

*OM Plus Delivery Manager also uses the `ncurses-libs.i686` library. This is not always included in 64 bit operating systems. If you see a warning to this effect at this point, please install the library before continuing.*

**UNIX/LINUX Keyboard Tip:** If you are connecting to a UNIX/LINUX system via a Terminal Emulator program (like Putty or PowerTerm) then you may not have the correct key mapping. If that is true then you will not be able to use the keyboard function keys. OM Plus will accept a combination of the control key and “f” followed by the function number. (ex. hold down `ctrl` and tap the “f” key like you’re doing a find command, then release and tap 3 to create an F3 command.)

## SENDING REQUESTS TO OM PLUS

---

### SENDING REQUESTS FROM WINDOWS

The most common way to spool a request is to print to a Windows-defined printer. This is the printer linked to the OM Plus destination that corresponds with where the requests is to be sent. This option is also available if the Windows destination is a shared printer on another computer running OM Plus . For additional parameters, refer to the `dcclp` command in Using the Command Reference.

---

### SENDING REQUESTS FROM UNIX

Requests can be spooled to OM Plus from the command line by issuing the `dcclp` command with a `-d [destination]` parameter. For example:

```
dcclp -d firstprinter /etc/profile
```

This causes the `/etc/profile` file to print to the destination defined for OM Plus, as `firstprinter`. For additional parameters, refer to the `dcclp` command in Using the Command Reference.

---

### SENDING REQUESTS USING LPD ON WINDOWS AND UNIX

If the LPD Server service is running, requests can be spooled to OM Plus by using the LPD/LPR Protocol. The target is `hostname:queueName`, where *hostname* is the name of the computer running OM Plus, and *queueName* is the OM Plus defined destination where the request should be delivered. For information, refer to the operating system documentation.

## LINKING OM PLUS TO UNIX LP (OR LPR)

OM Plus has a feature that can be used to link OM Plus to the native UNIX system. It is useful for legacy software that uses UNIX spooling commands.

To do so use the **dcclplink script**: to complete the following tasks:

- Disable the native lp startup and shutdown scripts.
- Copy the native lp program and then link lp to dcclp.
- Replace the native lpstat with OM Plus's lpstat command
- Replace the native enable and disable programs with OM Plus's enable and disable scripts.

In order to just replace the native lp with OM Plus, run the `lplinkonly` command to copy the native lp program and then link it to dcclp.

To unlink lp from OM Plus, run the `dcclpunlink` command.

OM Plus also comes with a program that has the ability to link to the native LPR command. To do so, link from the native LPR to `$LPHOME/bin/dcclpr`, and then use LPR.

*It is imperative that you run **dcclpunlink** before performing and operating system upgrade. Failure to do so may overwrite required OM Plus components. After the upgrade you may run **dcclplink**.*

## WORKING WITH THE OM PLUS CLIENT INTERFACE

### INSTALLATION

In Windows, execute the `OMPlusDMClientInstall_x.x.x.xxxx.exe` file. The installation process will prompt for the location to install to, default is `C:\PlusTech\OMPlus\Client3\`. After the files have been put in place the installer opens a configuration window to the "Hosts" tab. Enter the name of the OM Plus server or servers to connect to using the "Add" button in the lower right, click "Save" in the lower left and then exit. The OM Plus DM Client installation is now complete.

### DESTINATIONS


#### CLASSES

Destination classes are groups of printers to which it is possible to spool collectively. In traditional load balancing schemes, the printers receive jobs in a round robin fashion (Job 1 to printer 1, job 2 to printer 2, 3 to 3, 4 back to 1,

5 to 2, etc). While OM Plus typically follows this pattern, it will not send a job to a printer it knows to be currently active, therefore accelerating printing by more evenly distributing the print jobs.

OM Plus also has the ability to determine which printers in a class have the correct forms mounted to them. This would allow a user or program to send multiple types of jobs to the same class but have OM Plus intelligently distribute those jobs to the correct printers based on the forms mounts required by the documents.

Standard classes and members can be added and deleted. To access this component, from the OM Plus Control Panel, click Classes. The following Class Maintenance screen appears.



## ADDING A CLASS

A new standard class, which is a group of printers to which jobs can be collectively spooled, can be added. Requests will be printed to the first available printer in this working group in a round robin fashion. A class cannot be given the same name as a destination.

To add a class, complete these steps:

1. Click Add Class.
2. In the Enter New Class Name field, enter a new class name, and then click OK.

The class appears in the list.

## DELETING A CLASS

An existing standard class can be deleted when it is no longer desired to collectively spool to a group of printers.

To delete a class, complete these steps:

1. Select a class, and then click Delete Class.

A message appears asking for confirmation to delete the class and its contents.

2. Click Yes.

The class no longer appears in the list.


## ADDING DESTINATIONS TO CLASSES

New destinations can be added to an existing standard class to enlarge the group of printers to which jobs can be collectively spooled. The destination to add to a class must already be defined as a destination in OM Plus.

To add a destination to a class, complete these steps:

1. Select a class, and then click Add Member.

The Select Destination screen appears.



2. Select the destination to add, and then click OK.

The destination appears in the list under the class.

## DELETING DESTINATIONS FROM CLASSES

A destination can be deleted from an existing standard class in order to remove it from the group of printers to which jobs are collectively spooled.


To delete a destination from a class, complete these steps:

1. Select the class destination to be deleted.
2. Click Delete Member.

The destination no longer appears in the list.

## USING DEFINE DESTINATION

Destination management is one the most used functions of OM Plus. New destinations can be added and existing destinations can be modified or deleted. To access this component, from the OM Plus Control Panel, click Destination, and then the following OM Plus Destination Configuration screen appears.




The Destination Manager interface screen was created to allow quick and easy edition of OM Plus Destinations, even in large numbers.

## ADDING, DELETING, AND UPDATING DESTINATIONS

### ADD


Click the “New” button in the lower left corner of the screen. The Add New Destination screen will appear. Alternately, right click on “Destinations” beneath the host name and select “New” from the popup menu.



The 'Add New Destination' dialog box is shown. It has a title bar with a close button (X). The main area contains a 'Destination Name' text field. Below it is a 'Category' section with four radio button options: 'Network Printer' (selected), 'Local Printer', 'Server to Server', and 'Electronic Delivery'. Each option has an example text below it: 'Example: parallel/serial printer, native spooler' for Local Printer, 'Example: OM Plus Server, Other Print Server' for Server to Server, and 'Example: E-mail or fax' for Electronic Delivery. At the bottom of the category section is a 'Destination Type' dropdown menu. At the very bottom are three buttons: '< Back', 'Next >', and 'Cancel'.

Input a name for this destination, then select the type for this destination. After clicking “Next” the window will change to ask for more specific information depending on the category.

**Note:** Due to the ‘Destination Name’ being the key to the record, it is not possible to rename the destination. If you change the name and save you will create a new destination. You will have to create the new destination and save it, then delete the old destination. For this reason, OM Plus will not permit classes or destinations to have the same name.



The 'Add New Destination' dialog box is shown in its second state. The 'Destination Name' field now contains 'NewDestination'. The 'Protocol' dropdown menu is set to 'Raw TCP'. Below it are three text fields: 'Address' with '123.456.789.101', 'Port' with '9100', and 'Comment' which is empty. There are four checked checkboxes: 'Confirm Delivery', 'Use SNMP', 'Has Internal Web Server', and 'Poll Mode'. At the bottom are three buttons: '< Back', 'Finish', and 'Cancel'.

The destinations name from the previous will be brought over. The drop down menu for “Protocol” will display for network printers, but will display “Type” for other groups. Similarly, the device configuration fields will change depending on what is selected from the drop down. See “Device” below for more details on the options presented in each case.

Of note, though, is the “Poll Mode” option. This option, when configured, allows the printer to be configured to send jobs to a remote i-Sat print server. For more information on i-Sat and i-Sat Plus servers and devices, refer to the i-Sat documentation.

**Quick Product Reference:** *i-Sat is a solution for delivering print jobs to remote sites where reliable connections to the printers cannot be guaranteed. When Poll Mode is enabled, a properly configured i-Sat server will connect to the OM Plus DM server to retrieve the printer configuration and any jobs to be delivered to that printer. Since the remote server is initiating the connection, this often is a more reliable solution for remote sites.*

---

## DELETE

Right click on the name of the destination to be deleted, then select “Delete”. A window will appear to confirm the deletion.

---

## CLONE

A destination can be copied or cloned. To do so, right click on the name of the destination, then select “Clone”. A window will appear asking for the name of the new destination.

---

## EDIT

Select the destination from the left hand side. The settings from that destination will load in the main panel.

---

## SAVE HOST

To aid in defining destinations quickly and accurately in a distributed environment, OM Plus can save destinations to multiple OM Plus servers at the same time. To do so, select multiple hosts from the “Hosts” drop down menu in the upper left corner. Right click on each host name in the destination selection list and make sure “Save Host” is checked. The hostname will turn green. Now, any, destinations created or edited here will be saved to all Save Hosts.

---

## DEVICE

---

### NETWORK DESTINATION MODES

These destinations require access to a network in order to function.

---

#### RAW TCP

The destination takes data over a raw TCP connection. This can be used to communicate with terminal/printer servers or laser printers with network interface. This is the preferred mode for printing to a remote network device because of its simplicity and low overhead.

The address here should be the host name or IP address of the device. “Port” is the port number on which to communicate with the device . Most devices will use port number 9100.

This is also the Mode used for the Print Confirmation. Please see PJI/MPCL Job Confirmation Types.

---

## LPD/LPR

---

The network destination uses the LPD/LPR Transfer Protocol. Most network print devices support the LPD/LPR Protocol. The device for this destination type can be the host name, for example, hpjet18. Some destinations also require a queue name. For the proper queue name, refer to the manufacturer's documentation.

## IPP (OUTBOUND)

---

The network destination uses the Internet Printing Protocol (IPP). Most network print devices support IPP. The destination requires a URL.

---

## LOCAL DESTINATION MODES

---

Local modes are used for destination that do not require a transfer to another system. These include locally attached printers, as well as processes.

## DIRECTORY

---

The Destination Device field displays an existing directory for output. For example, a directory called /reports/save for saving output requests with OM Plus. A tilde ("~") character in the directory path expands to the user ID of the submitting user, therefore, if the directory path is specified as /reports/~, requests that user Bob submits would be written to /reports/Bob and reports that user Tom submits would be sent to /reports/Tom. By default, the file name is the request name, RIDXXXXX. This may be overwritten by the -o file=filename request parameter. Permissions on the destination directories should be set to prevent unauthorized user access to the contents. The target directory must already exist; OM Plus will not create it.

## BTPM QUEUE

---

This destination type is specifically designed to work with Bottomline's eComIntergrate products. For more information on configuring this device, please contact Bottomline.

## PIPE EVENT (WINDOWS ONLY)

---

This mode can be used for vendor-supplied software to route output requests. Some network terminal/print server vendors supply software filters for the delivery system to use. There is usually a better OM Plus mode to use instead of these filters. See Event Processing: Windows Events, pipe.bat.

## REPORT BUNDLER

---

A queue designed to hold bundled requests until they are to be released to another destination. Reports submitted to this type of destination will be saved and held until an acceptable trigger event causes them to be released.

## REPORT DISTRIBUTION

---

The destination connects to the Report Distributor pseudo-printer. Reports submitted to this type of destination will be broken into sub-reports based on content. The sub-reports then spool as new OM Plus requests. The



Destination Device field is the path to a working directory for temporary files (for example, /tmp). See the section on Report Distributor for more details.

## VIRTUAL

---

The destination is generic process destination, used to provide an environment to a specific process. When a job is sent to this Destination Type, it is de-spoiled into a 'User Filter' process that provides the data to a process (script / program / utility) and returns that process exit code back to the OM Plus system.

## WINDOWS PRINT QUEUE (WINDOWS ONLY)

---

The Destination Device field should contain the name of the Windows-defined printer to where the request should be sent. For example, an HP LaserJet 4 printer connected to the parallel port of the Windows print server and defined to Windows as HPLJ4 would be configured in OM Plus using a windows mode and a device of "HPLJ4".

## PARALLEL (UNIX)

---

Used to connect to a destination attached to the local server through a parallel port.

## SERIAL (UNIX ONLY)

---

A printer connected to server by a serial line. The device field should be the location of the serial port (eg, /dev/term/tty006).

***Note:** Serial mode destinations assume a standard set of settings: 9600 baud, 7 data bits, 1 stop bit, even parity and software flow control. In order to modify these settings, you must use the test based interface in the server.*

## STD OUT

---

OM Plus will output the result of the print stream to standard out which can then be routed to an executable process for additional processing.

## SERVER TO SERVER

---

These modes are used for connecting to remote systems, but not typically to print devices directly.

***Note:** Destinations using system-to-system modes do not honor the command parameters on the spooling system. With the exception of the -h, which places a job on hold, all parameters pass to the remote system for handling. Destinations using these modes do not determine the mounted form before transferring to the remote system. The form will be handled there.*

## OM PLUS LPD

---

Mode used to connect with a LPD Server. The server address and queue name must be given. "ex, legacy LP Plus, Linux, and UNIX"

---

## OM PLUS SERVER

---

Windows and UNIX. The destination is on a remote host system running OM Plus. This mode is used for passing requests between OM Plus systems, features encrypted transport, End-To-End status, and status tracing. An address and queue name must be specified.

## FTP

---

The destination is a directory on a remote system. FTP Protocol can be used for the transfer. By default, the file name for the transfer is the request name RIDxxxxx. This may be overwritten by the -o file=filename request parameter. Enter the address, the target directory and the user name to use when connecting to this server. A "~" character in remotedir expands to the user ID of the submitting user. If remotedir begins with a "/" it is treated as an absolute path on the remote computer. If it does not, it is treated as a path relative to the home directory for the login ID used for the transfer. If the user is not specified, it defaults to the ID used when submitting to OM Plus. The \$LPHOME/security/remotelogs file contains a table of host, user, and passwords for the FTP mode transfer. On Unix, make sure this file has permissions set to 600 to avoid compromising the remote user IDs. For example, <ftp.somplace.com>, someuser will transfer to the home directory of someuser.

## OTHER PRINT SERVER

---

The destination print queue on another host computer supports the LPD/LPR Protocol. The host can be a Windows computer, UNIX system, Novell server, mainframe, or any other system that supports LPD/LPR printing. This mode may also be appropriate for a network printer that spools to disk before printing. The server address must be given along with a viable queue name on that device.

---

## ELECTRONIC DELIVERY

---

This set of modes is used to send documents and notifications through other electronic means.

## EMAIL

---

The print requests are routed to an email server using Blat (Windows) or Sendmail (Unix).

## FAX

---

The print requests are routed to a fax server such as RightFax or VisiFax.

## PAGER

---

The print requests are routed to a pager service.


## TYPE

---

Type is used to link a Windows Print driver with a OM Plus Destination. In a properly configured system, OM Plus will automatically create shared Windows print queues for devices defined with a type. For setting up types, see Types configuration screen.

## TIMERS

This is a collection of time out and maximums for the destination. In all cases but purge delay a value of “0” means unlimited.



## PURGE DELAY

Amount of time, in seconds, for a job to remain in the queue after cancellation or completion

## WRITE TIMER

Time, in seconds, OM Plus will wait on a write to the destination device.

## OPEN TIMER

The amount of time, in seconds, for OM Plus to open a connection to the destination.

## CLOSE DELAY

The amount of time a connection is allowed to remain open after the close command has been sent.

\*\* In streaming mode, this is the maximum amount of time allowed between jobs before the connection to the destination is closed.

## RETRY TIMER

The amount of time, in seconds we will suspend waiting on a write.

## TRANSMIT RATE

The speed at which jobs will be transferred to a destination. Mostly useful for legacy dot matrix type devices or printers at remote sites with limited bandwidth.


## MAXIMUM REQUEST SIZE IN PAGES

The maximum number of pages a document can have and still printed on this device.

## FAILOVER

This allows for a failover destination to be designated for this device. To set a device to use the included failover logic, check the “Failover Error” box. If desired, select an alternate failover destination from the drop down menu or select the original destination to retry jobs on this printer until successful.

## MISCELLANEOUS



## PRINT BANNER

Should the banner page be printed for request spooled to this device?

## ADD CARRIAGE RETURN TO LINE FEEDS

On some printers and for some print jobs a line feed will be indicated but not a carriage return, causing the job to appear to have a “stair step” line of text off the right side of the page. This setting, when enabled, changes plain line feeds into carriage return line feeds that will reset the text line to the left edge after each line.

## FORM FEED AFTER EACH JOB

---

Inserts a form feed at the end of each job if one is not already present.

## FORM FEED AFTER EACH COPY

---

Inserts a form feed at the end of each copy of a job if one is not already present.

## HOLD DEFAULT

---

Holds (does not print) all jobs sent to this destination.

## PURGE DEFAULT

---

Allows jobs printed on this destination to be purged.

## DEFAULT FORM

---

The name of the form that, by default, is defined to this destination. For more information on forms, see Form Maintenance.

## CONTROL FILE

---

Default Print Control file for this destination.

## CUSTOM DATA FILTER

---

The full path name to a custom script to be used by this destination. The print job is delivered to the filter on standard in and the job is returned using standard out. If the filter does not return anything on standard out, this is a valid condition and OM Plus will accept that there is nothing further to process.

## FILTER CONTROL FILE

---

Determines whether the control file will be processed as part of the print job when the custom data filter is executed.

## NOTIFICATIONS

---


What user or group should be notified in case of an error with this device.

## PRINT STREAMS ALLOWED

---

Useful for legacy devices that may not support all print stream, or for destinations that use scripting for processing only certain types of data.

## TAMPER RESISTANCE



**Note:** This field is interpreted by the model, make sure to use the latest model included with our software.

## FREQUENCY

How often OM Plus should apply the Tamper Resistant Printing to jobs for a printer.

- Always – Apply regardless of the settings of the job
- Never -- Don't apply regardless of the settings of the job.
- Job Specific – If the job has a RX option, then apply, otherwise do not


## VERSION

The version of the pantograph being used.

## MACRO

The calibration setting saved on the printer.

## MY PRINT DELIVERY



## TYPE

The type of My Print Delivery being used.

- Queue – Jobs are released by any authenticated user for a defined queue.
- User –Jobs are released by the authenticated user who created the job.

## IP ADDRESS

The actual IP address that the requests will come from. For external card readers this is the card reader address. For “embedded” solutions this should be the address of the printer.

## HOLD QUEUE

Is the print queue that contains the jobs that can be released to this printer.

## QUEUE LABEL

Is the text to show on the Secure Queue Release screen.

---

## EXTENSIONS

Extensions can be used to configure custom parameters for a printer. These are used exclusively in custom implementations and should not be used without direction from Plus Technologies.

---

## ADVANCED

The advanced tab provides a centralized list of some advanced features. Most of these settings are intended for use by legacy or power users. In several places the functionality is duplicated in other screens (Mode, Device, PJJ, SNMP, etc) but some are unique to this screen.

---

## MODEL

Models can be defined to provide additional functionality to the destination. This must be the name of an executable script located in the models directory.

---

## SUPPORT

A comment field that can be used to give the name or contact information for a support technician.

---

## TRANSLATE TABLE

Translation tables are used to substitute characters in the print stream. The translation table must be a specially formatted file located in the “trans” folder.

---

## PCAP

This is a print control file that will be inserted at the beginning of a print job. While some users still use these, in most cases it is better and more efficient to use a different method.

---

## DYNAMIC CLASS MAINTENANCE

Dynamic destination classes function the same as standard classes, with the major exception being that users in the security group assigned to the dynamic class can change destinations in the class. In addition, unlike a standard class a dynamic class can belong to only one security group. To access this component, from the OM Plus Control Panel, double-click Dynamic Class Maintenance, and then the Dynamic Class Maintenance screen appears.


---

## GROUP MAINTENANCE

The Request Status screen may use destination groups to refine its data. For example, with anything more than thirty destinations defined, it can be difficult to find a particular printer in the list. Printers can be grouped by type of printer (color, directory, or laser), location (southeast or northwest), or floor and a printer can be assigned to more than one group. To access this component, from the OM Plus Administration, double-click Group Maintenance, and then the following Group Maintenance screen appears.

***Note:** Destinations must be added to the group before using them in the status menus. When using the **Lookup** menu on the Request Status screen, select **Groups** to view the defined groups.*





## ADDING A GROUP

Add a group to narrow the search for a printer in the Request Status screen. A group can be defined based on type of printer, location, or floor and it is possible to assign a printer to more than one group.

To add a group, complete these steps:

1. Select a host, and then click Add Group.
2. In the Enter New Group Name field, enter a new group name, and then click OK.

The group appears in the list.

## DELETING A GROUP

A group can be deleted when it is no longer needed. For example, if groups were defined by floor, and there were no longer printers on a particular floor, the group for that floor could be deleted.

To delete a group, complete steps:

1. Select a group, and then click Delete Group.

A message appears to confirm the deletion of the group and its contents.

2. Click Yes.

The group no longer appears in the list.

## ADDING DESTINATIONS TO GROUPS


Destinations are added to an existing group to narrow the search for a particular printer. For example, new color printers could be added to the Group "Color". A printer can be assigned to more than one group.

**Note:** The destination to add to a group must already be a defined destination in OM Plus.

To add a destination to a group, complete these steps:

1. Select a group, and then click Add Member.

The Select Additional Group Members screen appears.




2. Select the destination to add, and then click OK.

The destination appears in the list under the group.

## DELETING DESTINATIONS FROM GROUPS

Destinations can be deleted from a group when the printer is retired, or when it is longer needed to appear on the Request Status screen in a particular group. To do this, select the group destination to delete, and then click Delete Member. The destination no longer appears in the list.


## TYPES



This screen is used to define the drivers to be used with different types of printers. For setting a printer type, see Types in the destination configuration screen.

The first field should be a one word description of the device type. The second field should be the exact name precisely as it appears in the driver list on the target Windows server.

## i-SAT



The i-Sat interface provides an additional means of managing printers defined to different remote i-Sat units. This can also be done on an individual destination basis through the “poll mode” field on the destination configuration screen.

---

## CREATING A NEW i-SAT

To create a new i-Sat, Select File > Add i-Sat. A dialog box will appear asking for the name of the new i-Sat.

---

## REMOVING AN i-SAT

To remove an i-Sat, select the i-Sat in the tree and select File > Remove i-Sat. Click “yes” to remove.

---

## ADDING A DEVICE TO AN i-SAT

To add a device to i-Sat, open the OMPlus Control Panel and create a new destination. Enter a Destination name and select Network Printer then click Next. Enter the IP address and check the checkbox next to Poll Mode.

---

## REMOVING A DEVICE FROM i-SAT

To remove a device in i-Sat, Open the OM Plus Administration and select a destination that was added to i-Sat. Enter uncheck the checkbox next to Poll Mode.

---

## PUSH UPDATE

Select the  button, this will force the OM Plus server to update the remote i-Sat with a list of destinations that should be defined on that system.


---

## REQUEST LOG

Select the  button, this will display a copy of the log for the selected i-Sat on the local machine. This process can be very useful for remote troubleshooting.

## NOTIFICATION ADDRESS


This tool allows notification addresses to be entered. This is used to mask the true email addresses for users or distribution groups that will be receiving emails from the OM Plus system.



| Name | Address           |
|------|-------------------|
| tom  | tom@somewhere.com |

To add a new address, select “Add Address” from the command menu. To remove an address, select the address then select “Delete Address” from the command menu.

## EPIC PRINT RECORDS



| EPR Queue       | OM Plus Q...   | Printer Type | Tray   | Simplex/D... | Paper Size | Media Type   | RX                                  |
|-----------------|----------------|--------------|--------|--------------|------------|--------------|-------------------------------------|
| DEFAULT         | test           | lexmark      | Tray 1 | Simplex      | Letter     |              | <input type="checkbox"/>            |
| pharmacy_RXS... | emergency      | lexmark      | Tray 1 | Simplex      | Letter     | Plain        | <input type="checkbox"/>            |
| emergency       | emergency      | lexmark      | Tray 2 | Simplex      | Letter     | Vinyl Labels | <input type="checkbox"/>            |
| emergency_t2    | emergency      | hp           | Tray 2 | Simplex      | letter     |              | <input checked="" type="checkbox"/> |
| fl3_ns2_p001    | fl3_ns2_p001   | xerox        | Tray 1 | Long Edge    | letter     |              | <input type="checkbox"/>            |
| pharmacy_label  | pharmacy_label | zebra        |        |              |            |              | <input type="checkbox"/>            |

This tool is designed to be used with EPIC EMR systems. It is meant to configure a list of options for Epic Print Records that can be passed to an EPIC Transform Server. Unless the client is configured to allow it, this screen will not appear on most OM Plus installations.

## HOST

The host name where the OM Plus print queue will be defined. These are typically the same as the host name where this configuration file is created, but special cases can arise where a different server should be used to deliver jobs to a specific printer. This field can be used to direct traffic in that way.

## FILTER

A text based filter for quickly finding EPR or OM Plus queues in the table.

## EPR QUEUE

The name of the EPR as it appears on the Transform server.

## OM PLUS QUEUE

The name of the OM Plus queue that will handle delivery of the print job.

## PRINTER TYPE

With the Types screen, this will define that print driver that should be used to render the job on the transformer Server. This field will be passed to the Transform Server and a Windows queue for that driver will be created to render the job ready for print on the Transform Server before transferring it to the host specified in the first field.

## TRAY

Which tray number should be associated with the EPR.

## SIMPLE / DUPLEX

Turns on or off duplexing for the device.

## PAPER SIZE

The size of the sheet that should be used for this EPR.

## MEDIA TYPE

The paper type that should be associated with the EPR.

---

## FILE COMMANDS

---

### ADD NEW RECORD

---

Adds a new EPR to the list.

---

### REMOVE RECORD

---

Removes the selected EPR from the list.

---

### IMPORT RECORDS

---

Allows a .csvs of EPR records to be imported into the system. For proper formatting, please contact OM Plus support.

## SYSTEM

---

### ADVANCED FORMS

An Advanced Form in OM Plus has a specific and useful utility. With an Advanced Form attached to an OM Plus data stream, that data stream can be split and redirected to any number of other OM Plus Destinations. The split can be equal or in blocks of hundreds, or the data stream can be kept whole.

Advanced forms can be added, modified, or deleted in the Client Interface. To access this component, from the OM Plus Control Panel, double-click Advanced Forms, and then the following Advanced Forms screen appears.

The Advanced Form can have a number of uses. Its given use is to split a data stream to a number of destinations, but by setting the 'Type' to 'all' it is possible to send entire copies of the data stream to a number of different Destinations. This is often used as a distribution list.

Only the OM Plus Data streams noted as simple, PCL-1 or Post-DSC can be split using an Advanced Form. For more information, see Data Types.

To add an advanced form, complete these steps:

1. In the Advanced Form field, enter a new form name.
2. In the remaining fields, enter the appropriate information, and then click Save Advanced Form File.

An existing form can be updated and saved with another name by selecting the form, and then from the File menu, selecting Save As.

An existing form can be deleted by selecting the form, and then from the File menu, selecting Delete.

Fields used in this control include:

## LINES

Enter the lines per page, which is used for page counting purposes only. OM Plus counts pages by counting form feeds, if present in the output job, or by counting the number of lines until it reaches the lines per page value. OM Plus will NOT insert form feed characters into the data after the line per page value.

## PURGE

Select whether or not to spool the original output job and separate the segments. When an advanced form is used, the output job that initially spools can be optionally printed along with any segments, or removed after all segments of the advanced form spool. Setting the Purge column to Y deletes the initially spooled report without printing. This option would be used so that a complete copy of the initial report is not printed in addition to its separate components as defined by the form.

## DESTINATION

Which OM Plus print destination. This is specified for each segment.



---

## ADVANCED FORM (OPTIONAL)

Apply this electronic form to this segment. The default is none.

---

## ADVANCED FORM OPTIONS (OPTIONAL)

The fprint program options that may appear if an electronic form file is selected.

---

## FORMS

Which standard form to use with a segment. The default is the form for the segments print destination.

---

## TYPE

View the section of the original spooled output job to send to this segment.

---

### ALL

Delivers the document to multiple destinations, and each destination receives a complete copy of the report.

---

### SPLIT

Sends an equal amount of the original output job to this segment. For example, if there are three segments, the original output job is split into thirds.

---

## NUMBER OF PAGES

Specifies the number of pages this destination should accept for each segment. For example, if the goal is to send 100 pages to segment one, 50 pages to segment two, and 150 pages to segment three, the parameters would be 100, 50, and 150 respectively. If the spool file contains more pages than specified for the total number of segments, the last segment receives all the additional pages.

---

## FORMS MAINTENANCE

OM Plus uses the form name associated with an output job to ensure the correct paper is loaded in the destination before printing. The form name for the output job must match the form mounted on the destination, which is usually set when the job spools by using the -f form\_name command option of dcclp.


For example, when accounts payable wants to print checks and use special check paper or special micro toner cartridges, the check output job would spool using the form name "checks" and when the checks out job is submitted it will not print until the correct paper or toner is loaded in the printer. By mounting the form checks on the destination through OM Plus before loading the new paper in the destination, all other output jobs in the destinations queue not needing the form checks are held while the check job prints. When the check job completes, stock (default paper) can be returned to the destination and the form that was on the destination before the check job can be mounted.

**Note:** If either **LPPlus** or **OM Plus** is the destination mode indicating a transfer to a remote system, the form ID passes to the remote system. Transfers take effect immediately, therefore ignoring the currently mounted form. System mode will also transfer the request immediately, but the form ID is not passed.

OM Plus uses two types of forms, standard and advanced.

- **Standard Forms:** Ensures that the correct paper is loaded in the destination and sends a download file to the destination before the output job.
- **Advanced Forms:** De-spools to multiple locations, divides a report equally over multiple destinations, or divides a report based on a preset number of pages per section.

To access this component, from the OM Plus Administration, System double-click Forms, and then the following Form Definition screen appears.



## USING STANDARD FORMS

Standard forms can be added, modified or deleted to ensure the correct form is loaded for the output job.

## CREATING FORMS

1. In the Form Name field, enter a new form name.
2. In the remaining fields, enter the appropriate information, and then click Save.
3. When a message appears indicating the new form is updated, click OK.

## MODIFYING FORMS

To modify existing forms, select the form from the Form Name field, make changes, and then click Save. When a message appears indicating the form is updated, click OK.

---

## DELETING FORMS

---

Select the form from the Form Name field, and then from the File menu, select Delete. When a message appears to confirm the deletion of the form, click Yes.

---

## FIELDS

---

### FORM NAME

---

Select an existing name, or enter a name for a new form. Assign the form a functional name (for example, checks or PO). The form will be referenced by this name on the spooling command line or from the request status screen.

---

### MOUNT REQUIRED

---

Does this form need mounted to the printer before a request can print. Operator intervention may or may not be required for mounting forms. If “N” is selected, any spooled file requesting this form will automatically de-spool regardless of the form mounted on the destination. If “Y” is selected then a request will only de-spool if the form mounted in the selected destination matches this form. Otherwise the request is marked with a status of “fpend”. See the ‘fpend’ event script, under the ‘Using Event Processing’ section of this manual.

---

### LINES PER PAGE

---

Enter the value to use for page counting purposes. On some data types, OM Plus counts pages by counting form feeds, if present in the output job, or by counting the number of lines until it reaches the lines per page value. In the example, the check contains 22 lines per page. If this is not set correctly, the number of pages OM Plus counts will differ from the number of pages that print.

---

### ENABLE FORM DOWNLOAD FILE

---

If set to ‘Y’, a copy of the file name in the Copy Download File From Host File field is sent to the destination before the output job. If set to ‘N’, the download file is not sent.

---

### COPY DOWNLOAD FILE FROM HOST FILE

---

Indicate to allow the form file (if a true electronic form) to exist for Windows in the %OMHOME%\form\<FORMNAME> folder and for UNIX in the \$LPHOME/form/<FORMNAME> directory with the required filename downloaded. This file was created the first time the form was defined from this screen. The Client allows the downloaded file to be updated from a more recent or another file on the computer by selecting this option. The Character-based interface requires the form to be deleted and re-added to update the downloaded file.

---

### ENABLE POSTLOAD FILE

---

If set to ‘Y’, a copy of the file name in the Copy Download File From Host File field is sent to the destination after the output job. If set to ‘N’, the download file is not sent.

## COPY POSTLOAD FILE FROM HOST FILE


Indicate if this file, if similar to the downloaded file, should allow for resetting of the destination after de-spooling with this form. Selecting this option allows for Windows %OMHOME%\form\<FORMNAME>\ postload and UNIX \$LPHOME/forms/<FORMNAME>/postload file to be updated without deleting and re-adding the form.

## HEALTH CHECK (UNIX ONLY)

For OM Plus on UNIX, there is a built in health check to determine the status of the installation and confirm that it is operating properly. To access this component, from the OM Plus Administration, double-check Health Check and a prompt appears asking for the host to check and whether to automatically fix any issues. Regretfully, some issues, such as file permissions, cannot be fixed with this process.

Plus Technologies support representatives may ask for this command to be executed and for any error messages that appear to be relayed in order to help resolve problems.

The following is an example OM Plus Health Check screen:




```
OM Plus DM - Health Check (centos74)
Hosts
Checking 37 of 31 files in /usr/lpplus
/usr/lpplus/attach missing
/usr/lpplus/exceptions missing
/usr/lpplus/ffe missing
/usr/lpplus/ffeconfig missing
/usr/lpplus/help missing
/usr/lpplus/lists missing
1 files in /usr/lpplus/omplusjava contain 6 bytes in 0 blocks
/usr/lpplus/bundle missing
/usr/lpplus/satelliteFiles missing
23 files in /usr/lpplus/save contain 10775 bytes in 184 blocks
/usr/lpplus/template missing
3 files in /usr/lpplus/tmp contain 3622621 bytes in 7088 blocks
Checking 5 of 12 files in /usr/lpplus/shells/
Checking 124 of 164 files in /usr/lpplus/bin/
```

## WORKING WITH REMOTE HOST SETUP

See the section Configuring Multiple OM Plus Installations in a Distributed Environment for more information about this feature.

## REGISTRATION STATUS

From the OM Plus Administration, click Registration Status, and then the following System Registration Status screen appears.



| Product             | Status | Queues | Expiration |
|---------------------|--------|--------|------------|
| OM Plus DM          | ✓      | 10000  |            |
| Archive             | ✓      |        |            |
| Web Interface       | ✓      |        |            |
| Report Distribution | ✓      |        |            |
| BC-XOM(SAP)         | ✓      |        |            |
| Report Bundler      | ✓      |        |            |
| Context Delivery    | ✓      |        |            |
| My Print Delivery   | ✓      |        |            |
| i-Sat               | ✓      |        |            |
| Stats Manager       | ✓      |        |            |

**Note:** If you are moving an OM Plus installation from one computer to another, contact Plus Technologies Support so they can create a new registration key for you.

## HOSTS

Allows you to select different hosts.

## TRP

Reports the number of Tamper Resistance Prescriptions queues.

## RID SPANS SETUP

See the section on R3/SAP Interface for more information about feature.

OM Plus DM - RID Span Maintenance (skarllap)

Hosts

Span Host:

| Host | Start | End |
|------|-------|-----|
|------|-------|-----|

Add Line Delete Line Edit Line Save File

The RID spans system is used to limit the range of RID numbers that a particular OM Plus server will use. When multiple servers are to be set up to use this system one of the OM Plus servers must be designated the span host. This is done by putting that host's own name in the Span Host field.

Add a line containing host, starting RID, and ending RID for each OM Plus server in the enterprise. Starting RIDs must be larger than ending RIDs. Ranges cannot overlap. The minimum range is 500, but it is highly recommended that the range be greater than the maximum number of requests allowed on that system (See System Defaults).

The system that is the Span Host is the only system that needs to be set up using this utility. Periodically the Span Host will publish the current file to all of the system listed. If a server that is not the Span Host is updated, the changes will be lost as soon as the real Span Host publishes its list.

## SYSTEM SETTINGS

The System Default component is similar to the Client Configuration component, except that it is used for the OM Plus Server. The settings include parameters that the OM Plus Server uses to operate. To access this component, from the OM Plus Administration, click System, System Settings and then the following System Default screen appears.

**Note:** The 'Maximum Requests' and 'Maximum Dests' are important sections in system tuning. If the Maximum Dest field is not set to greater than the license number of destinations, you will not be able to use that maximum number. If the 'Maximum Requests' are not set to exceed the number that would be expected to be listed in the "Status Screen" at a given time, the jobs exceeding that number will not de-pool.

## SYSTEM DEFAULTS

OM Plus DM - System Settings (skarllap)

Hosts

Destination System Extensions

**Server Role**

☒ Stand Alone ☐ Primary OMS ☐ Backup OMS

Primary OMS Name

**Shared Memory**

Maximum Destinations 200 Maximum Jobs 1100

Maximum Virtual Dests 3

System Notifications

Default Printer C7765dn

☒ Accounting

☒ Track Parent/Child

☐ Hold Jobs

☒ Purge Jobs

☐ Require Form Mounts

**Message Queue Keys (Unix/Linux Only)**

Destinations 33333 Jobs 33334

Save

To set the system defaults, complete these steps:

1. From the System Defaults screen, change the default options, as needed.
2. Click Save

**Stand Alone:** Is a server that runs alone and is not part of a group.

**Primary Server:** Is a server that acts as the first source for data and responds to queries.

**Backup Server:** Is a server that mimics the primary server.

**Maximum Destinations:** Enter the maximum number of destinations that will be defined on this system.

**Maximum Virtual Dests:** Enter the maximum number of virtual destinations that will need. (minimum of 3)

**Maximum Jobs:** The number of concurrent requests (printed, interrupted, or otherwise) for which to reserve memory.

**System Notifications:** The email address to notify in case of system problems.

**Default Printer:** Select the destination to send spool requests if not destination is psecified on the spool command line.

**Accounting:** Select whether or not OM Plus will write records to the acctlog file each time a requests de-spools.

**Track Parent / Child:** Should OM Plus keep track of any parent/child relationships between requests.

**Hold Jobs:** Select a global setting to ensure that all requests spooling to OM Plus spool with a Hold status.

**Purge Jobs:** Select whether or not to set all requests to purge automatically.

**Require Form Mounts:** Require that the form specified by the job matches the form mounted to the destination.

**Message Queue Keys (Linux/UNIX Only):** These are the keys that UNIX uses for identifying OM Plus message queues. These values should only be changed at the request of a Plus Technologies support person.



## DESTINATION DEFAULTS

OM Plus DM - System Settings (skarllap)

Hosts

Destination System Extensions

☒ Initially Accepting ☒ Purge Jobs

☒ Initially Enabled ☐ Hold Jobs

☐ Fail-over Requests

Alternate Destination: none

**Timers**

Open Time: 180 Close Delay: 10

Write Time: 5399 Retry Time: 30

Purge Delay: 100 Metering: 0

**Options**

Type: none ☐ Line Feed Convert

Interface Model: omstandard.js ☐ Copy Break

Default Form: stock ☒ Filter Control File

Default Print Control: default ☐ PDF Capable

File Break: No ☐ Banner Page

Filter Program: none

Translation Table: standard

Support Person: none

Notifications: none

Save

**Note:** Changing the values of these settings does not change the values of any destination that has already been defined. Only newly added destinations will be affected.

**Initially Accepting:** Will a newly created destination automatically receive jobs?

**Initially Enabled:** Will a new destination automatically release jobs?

**Fail-Over Requests:** Will a new destination automatically fail over to a defined alternate destination?

**Alternate Destination:** The default alternate destination.

**Purge Jobs:** Will jobs sent to a new destination purge after completion by default?

**Hold Jobs:** Will jobs sent to a new destination be held for release by default?

**Open Time:** Enter the number of seconds OM Plus will use to try and open a connection to a network device.

**Write Time:** Enter the number of seconds OM Plus requires to try to write data to a destination before marking the request interrupted and disabling the destination. A successful write to the destination resets this timer.

**Purge Delay:** Enter the amount of time in seconds to keep a printed request before purging or archiving it. It has a value range of 0-99999.

**Close Delay:** Enter the number of seconds OM Plus holds the connection to this device open to allow it to flush its buffers.

**Retry time:** Number of seconds allowed between attempts to deliver a job.

**Metering (CPS):** Enter the number of characters per second to transfer to the target device. This is useful if there is limited bandwidth.

**Type:** The default type to use when creating a new device. For more information, see Types.

**Interface Model:** This setting is what model to use for a printers interface script. Most implementation use the model that the system selects based on the destinations's mode.

**Default Form:** Which form to use as the default for a new destination. A request will default to the form specified for its destination unless a different one is specified on the command line.

**Default Print Control:** Which print control to use by default on a new device.

**File Break:** Should OM Plus append a form feed at the end of each request. To always add a form feed, select "always." To add a form feed only when one is not detected, select "conditional."

**Filter Program:** Indicates the default user filter for a new destination.

**Translation Table:** Which translation table to use by default with a newly defined destination. These tables will translate one sharacter into another. They will not translate strings.

**Support Person:** Indicates the default support person for a new destination.

**Notifications:** The default email address to notify in case of problems with a device.

**Line Feed Convert:** Should the OM Plus convert all line feeds to carriage return line feed.

**Copy Break:** Select whether or not to append a form feed between each copy in a request.

**Filter Control File:** Should the control file be added to the job before or after processing through a user filter?

**PDF Capable:** Should a new device be assumed to be capable of printing a PDF file?

**Banner Page:** Should an OM Plus banner page print before each request.


---

## EXTENSIONS

This screen can be used to define a set of Extensions to pass on to any newly created destination. These can be used to configure additional functionality as needed for custom solutions.

## SYSTEM STATUS

The System Information component can be used to provide a summary of information about the OM Plus system. To access this component, from the OM Plus Administration, click System Tab, click System Status and then the following System Information screen appears.




This screen is informational only. It can be very helpful for problem resolutions as it shows disk space and number of destinations defined. OM Plus support may ask for version number from this screen.

## CLIENT

### CLIENT SETTINGS

It is possible to establish standards for the interface installation that will not impact the Server settings or installs of the interface on other computers.

### HOSTS



The OM Plus client can connect to multiple servers in a distributed printing environment. These hosts can be added and managed through this screen. To add a new host to the list, select “Add” and then input the host name for that server. To remove a server, select it and then click “Remove.”

To select which servers the client will automatically connect to on startup, make sure a check is present in the box to the left of the host name for each desired server.

For large implementations with multiple servers, the “Use Host Selection Dialog” option is provided. This will present a selectable list of servers rather than the drop down menu. This option will automatically be enabled for clients connecting to more than 15 OM Plus servers.

For all changes to be finalized, they must be saved using the “Save” button in the lower left corner.

---

## OPTIONS

---

### AUTO UPDATE

Should the request status screen automatically update?

---

### AUTO UPDATE INTERVAL

The time, in seconds, that will elapse between updates when auto update is turned on. The minimum value is 5.

---

### SORT PARENT / CHILD

When sorting requests, child requests will be grouped with their parent requests. This is helpful in seeing a family tree of requests if the system has spooled requests in between the parent and child requests.

---

### SHOW EPS MAP

If this box is checked, the “Epic Print Records” tool will be selectable in the OM Plus Administration screen.

---

### REQUESTS PER PAGE

The number of requests the client will display in the status screen. More lines will use more memory, but the effect is not substantial.

---

### MESSAGE FILE EXTENSION

If different language files have been installed for the GUI, this provides the option for selecting those files.

---

### INITIAL CONNECTION

The amount of time, in seconds, for the client to attempt to connect to the server.

---

### INITIAL CONNECTION

The amount of time, in seconds, for the client to attempt to connect to the server.

---

### RECORD PREFERENCES

When should OM Plus record the changes made to the request status screen?

---

### TRANSACTION

The amount of time, in seconds, the client will wait while attempting to communicate with the server.

---

### STATUS SERVICE

The port number for Background Status to use. Default is 53971.

## ADMIN SERVICE

---

The port for Background Administration to use. Default is 53974.

---

## VIEWERS

On this page, the viewers used by different file types can be defined. OM Plus included a viewer for some PCL types, but additional third party viewers may be required for other types. This field must contain a fully qualified path to the desired viewer.

## SECURITY

With so much functionality and ease of access with printing reports, security in OM Plus becomes more of an issue than with standard Windows spooling or UNIX lp systems.

OM Plus security uses destination permissions models and groups of users. If the user does not appear in the security system, they will be assigned to the “guest” group and assigned the privileges given to that group. When OM Plus is first installed, the default permissions model allows unrestricted use. If a user is added to the security system, that user can only access destinations to which their group is assigned and only perform functions in the permissions model applied to the destinations. A user can only be in one security group at a time, but a group can consist of one or many users.

Before attempting to set up security, Plus Technologies recommends that note is taken of each user, the destinations to which they need access, the functions they need to perform, and any other users, if any, with similar needs. It will then be possible to apply this information to OM Plus security. We also recommend backing up the “security” folder in the OM Plus installation directory before any modifications to security roles in order to provide a working environment that can be restored easily in case of an unintended lock out.

For information on the applications and their functions, refer to the following table:

| Tab          | Function                                                                                                               |
|--------------|------------------------------------------------------------------------------------------------------------------------|
| Hosts/Domain | Displays the users from remote computers that are associated with a local user.                                        |
| Groups       | Displays the name of the group, the destinations in the group, and the security models that apply to each destination. |
| Logins       | Displays the login IDs that are associated with a local user. This is used primarily with the HTML interface.          |
| Models       | Displays the name of the model and the permission levels to which it is associated.                                    |
| User List    | Displays the local users and the group to which they are assigned.                                                     |

## USING SECURITY GROUPS

Group Maintenance is used to group the OM Plus users that have common destination and access needs. A permissions model is applied to each destination.

To set up security groups, complete these tasks in the order they appear.

1. Set up permission models.
2. Create new security groups.
3. Select destinations for the groups.
4. Assign proper permission models to each destination.
5. Assign proper administrative privileges.
6. Assign users to groups.

## SETTING UP PERMISSION MODELS

OM Plus security uses permission models to determine the rights a user has to a destination and the jobs spooled to that destination.

From the OM Plus Security Maintenance tab, select Model to determine the level of access desired for this model, per item.

**Note:** The “Status” option determines which requests a user can see in the Request Status screen. “View” determines whether or not the user may view the request in one of the viewers.

**Information on the other request actions can be found in the Request Actions section.**

For information about the access levels and their descriptions, refer to the following table.

| Access (Windows) | Access (UNIX)           | Description                                                                            |
|------------------|-------------------------|----------------------------------------------------------------------------------------|
| None             | 0 = No Access           | Cannot perform the function.                                                           |
| Owner            | 1 = User Access         | Can perform the function only if the user owns the output job.                         |
| Security Group   | 2 = Group Access        | Can perform the function only if the user or another group member owns the output job. |
| All              | 3 = Unrestricted Access | Can perform the function regardless of job ownership.                                  |

Once the permissions model is saved it can be applied to a destination when defining groups of users in Group Maintenance.

**Note:** User access means it is possible to perform the action on requests belonging to the user ID. Group access means group members can only perform the action on requests belonging to their group ID.

We recommend that you set up a permission model for users and one for administrators.



## CREATING SECURITY GROUPS

Group Maintenance is used to group OM Plus users that have common destination and access needs. A permissions model is applied to each destination.

To add security groups, complete these steps:

1. From the OM Plus Security Groups screen file menu, select “New Group”.

A prompt appears asking for a name for the new group.

2. In the Enter New Group Name field, enter the new group name, and then click OK.

The new group name is now available in the Security Group drop down menu.

## SELECTING A DESTINATION FOR THE GROUP


After adding a group, one must add destinations to the security group, and then assign the proper permissions model to the destination.

**Note:** Once you add all the destinations to the group, it is possible to add user. Users can only belong to one group. OM Plus uses the name you enter. If you are on UNIX, the name should match the login user ID to the host on which OM Plus is installed.

To add a destination, complete these steps:


1. From the OM Plus Security Group screen, select “Add” from the bottom Destination and Models pane.

The Destinations screen appears.



2. Select the destination to add, and then click OK.

The Models screen appears.



3. Select the permission model this group should use for this destination, and then click OK.

The Destination and its associated security model appear.

OM Plus DM - Security Groups (skarllap)

File Hosts

Security Group: guest

Administrator Level: Full Admin

Users

Add Remove

Destinations and Models

☒ All Destinations default ☐ Archive default

| Destination | Model   |
|-------------|---------|
| C7765dn     | default |

Add Edit Remove

Save

A group of printers can be added by clicking the printer icon in the lower left. This will bring up a group selection screen.

Select Destination

Select a Printer Group

NewGroup

OK Cancel

Selecting a group and model will add all printers in that group to this security group.

A group must also be assigned an administrative level.

The administrative levels are:

**None:** Users may not use any of the printer level or server level functions in OM Plus.

**Printer Admin:** Users may use printer level functions of OM Plus (adding or removing destinations, changing destination settings, etc) but not any of the server level functions of OM Plus.

**System Admin:** Users may use printer and system level functions in OM Plus but may not edit the security profiles.

**Full Admin:** These users may change any setting in OM Plus.

## ADDING USERS TO GROUPS

Local, remote, and login users can be added to a group, but first local users must be added. If a user is added to the security system, that user can only access destinations to which their group is assigned and only perform functions in the permissions model applied to the destinations. A user can only be in one security group at a time, but a group can consist of one or many users. OM Plus uses the name entered. In UNIX, the name should match the login user ID to the host on which OM Plus is installed. For information on adding remote and login users, refer to Adding Remote Users and Adding Login Users.

To add local users to a group, complete these steps:

1. Navigate to the OM Plus Security Maintenance Groups screen.

2. Click Add User
3. In the Enter User Name field, enter a new user name.

The user appears in the list for this group.

**Note:** Users cannot be added to the group “guest” as this is the default group for any unresolved users.

## ADDING REMOTE USERS (HOST/DOMAIN)


When a spool request comes in from another host system, either via LPD or a linked Windows printer, OM Plus will attempt to resolve a 'local' user name so that it can apply security measures. Remote users are how this is done. If a request comes in and a local user is not resolved, the request will get whatever the permissions the 'guest' security group has.

Remote user are also used to resolve command requests from the OM Plus Client. The client will send the user name that is logged in to the client system and the host name (or Windows domain name) of that system whenever it processes a command. Again, if there is no resolved local user, the security permissions will be as the 'guest' group.

The local user will be resolved from the combination of what host the remote request came from and what the user ID from that host was given. For computers connected to a Windows domain, the Host will be the base domain name (as stored in the USERDOMAIN environment variable).

1. From the OM Plus Security Maintenance Host/Domain screen Click Add User (*bottom left button*) to define a remote user to correspond with a pre-defined local user.

The New Login screen appears.




The image shows a 'New Login...' dialog box with a close button (X) in the top right corner. It contains three text input fields: 'Host/Domian:', 'User ID:', and 'Resolved User:'. At the bottom, there are two buttons: 'OK' and 'Cancel'.

2. In the Host/Domain, enter the hostname, IP address, or Windows domain name of the computer on which the user will work. If an asterisk character (\*) is entered in this field, the local user will be resolved based only on the remote user name.
3. In the User ID field, enter the name the user will enter when logging into the remote system or Domain. If an asterisk character (\*) is entered in this field, the system will not care what the user ID was. It will apply the local user field to all users ID's from the associted domain.
4. In the Resolved User field, enter the name of the user to associate, as it appears on the User List tab, and then click OK. If an asterisk character (\*) is entered in this field, the system will use whatever Remote Users was sent by the system as the local user name.

If an asterisk is put in both the Remote User and Local User Fields, the system will use as the local user the user ID that the user logged into their session with. They can then be added to the Security groups by their operating system login ID.

## USER LIST

The user list screen is designed to provide a quicker tool for identifying and modifying users and their groups. Clicking on the headers allows the list to be sorted based on either the group or user name.



In addition, the users list can be edited from this screen. To edit an existing user or users, select the desired users and then right click and select “Change Group.” A dialog box will appear asking for the new group.

To delete users using this screen, select the users and then right click and select “Delete User.”

This screen also provides two ways to add users to the list. The first is to right click and select “Add User.” A dialog will appear asking for the user name and the group to which they should be assigned.

The second method is to perform a batch load. This can be especially useful if loading a large number of users at once. Select “Batch Load” from the Commands menu. An open file dialog will appear. From there, select a comma separated file that contains the user names and group names to be added to the users list. After selecting a file, a dialog will appear with two options. To add the new users select “Add/Update.” To clear out the current list and use only the names in the new list, select “Replace All.”


**Note:** Be careful when modifying the users list. If you remove your own name from the list or otherwise exclude yourself from an administrative group you can effectively lock yourself out of the system. OM Plus will attempt to warn you if this is about to happen, but there are still ways a determined user can circumvent these measures. If this happens, contact another administrative user or, if there is not one, please contact Plus Technologies support.

## ADDING LOGIN USERS

The Logins screen makes it possible to set up the user name and password to associate with a specific local user user ID. This is primarily used for the web interface. If OM Plus recognizes the user name and password upon login, it uses the local user to which it is associated and not the remote ID.

1. From the OM Plus Security Users screen select Add to add a login user.

The Add Login User screen appears.

A screenshot of a 'New Login...' dialog box. The dialog has a title bar with 'New Login...' and a close button (X). It contains four text input fields: 'User ID:', 'Resolved User:', 'Password:', and 'Confirm Password:'. At the bottom, there are two buttons: 'OK' and 'Cancel'.

2. In the available fields, enter the login user name, the resolved user name, password, and then click OK.

When a user submits a job, OM Plus checks the user ID that is associated with the request and verifies that the user has permissions to the destination and to the options they selected. If they do, the request proceeds normally. If they do not, OM Plus rejects the request.

## SECURITY IN DISTRIBUTED ENVIRONMENT

As of OM Plus version 2.6.1, security profiles and settings can be broadcast and synched between OM Plus servers. For information and training on configuring these settings, please contact OM Plus support.

## OM PLUS STATUS SCREEN

The most commonly used component of the Client is the Request Status screen. From this screen, it is possible to view the status of and modify all requests and destinations. To access these components, from the OM Plus Administration, select the **Status** tab, click **Request Status**, and the following OM Plus Request screen appears.

| RID   | Host      | Title            | User       | Dest              | Form  | P | Date  | Time  | Pages | Stat  |
|-------|-----------|------------------|------------|-------------------|-------|---|-------|-------|-------|-------|
| 04862 | localhost | Web Interfa...   | labartlett | DevHP19           | stock | Y | 03/24 | 14:26 | 54/0  | activ |
| 04863 | localhost | TPS Cover.pdf    | Imbolton   | DevX12            | stock | Y | 03/24 | 14:26 | 18/0  | ready |
| 04864 | localhost | i-Sat.pdf        | Ikreinig   | SalesL543         | stock | Y | 03/24 | 14:26 | 8/0   | ready |
| 04865 | localhost | OM_Plus_DM...    | labartlett | DevHP19           | stock | Y | 03/24 | 14:26 | 12/0  | prntd |
| 04866 | localhost | Client Interf... | labartlett | SupportL855       | stock | Y | 03/24 | 14:26 | 64/0  | intrd |
| 04867 | localhost | Prescription ... | Itimiller  | SalesD223         | stock | Y | 03/24 | 14:26 | 2/0   | ready |
| 04868 | localhost | Web Interfa...   | Itimiller  | SalesL543         | stock | Y | 03/24 | 14:26 | 8/0   | held  |
| 04869 | localhost | Translating ...  | labartlett | ompdemo20...stock | stock | Y | 03/24 | 14:26 | 2/0   | held  |
| 04870 | localhost | Secure Print ... | labartlett | ompdemo20...stock | stock | Y | 03/24 | 14:26 | 12/0  | held  |
| 04871 | localhost | RAW TCP Ad...    | labartlett | ompdemo20...stock | stock | Y | 03/24 | 14:26 | 2/0   | held  |
| 04872 | localhost | OM Plus Rep...   | Irhill     | DevX12            | stock | Y | 03/24 | 14:26 | 77/0  | fpnd  |
| 04873 | localhost | OMStats Co...    | Irhill     | ompdemo20...stock | stock | Y | 03/24 | 14:26 | 54/0  | prntd |
| 04874 | localhost | PC Load Lett...  | blumbergh  | ompdemo20...stock | stock | Y | 03/24 | 14:26 | 65/0  | held  |

Total Requests 13 | Sorted Ascending by RID

*OM Plus indicates the Host and Destination status by color, and the Request status via text in the Stat field. Requests sometimes change color, thus indicating a status alert.*

## UNDERSTANDING CLIENT SPECIFIC INFORMATION

The Request Status screen that appears in the Client differs from the screens in the Character-based and Browser interfaces in the following ways.

In the Client, it is possible to view both the request and queue status, which means it is not necessary to have to access another screen to view or change the status of a destination queue. Text for a host, request, or queue appears as bold or in color to indicate its status.



| Host Color Code     | Status                                                                                                                |
|---------------------|-----------------------------------------------------------------------------------------------------------------------|
| Black               | Operation is normal.                                                                                                  |
| <b>Red and Bold</b> | Scheduler service is not running.                                                                                     |
| Red                 | Warning indicating Max Requests is over 80% of maximum value.                                                         |
| Queue Color Code    | Status                                                                                                                |
| Black               | Queue is enabled and ready to de-spool.                                                                               |
| Green               | Request is de-spooling on this queue.                                                                                 |
| Blue                | Queue is disabled and will not de-spool until it is enabled.                                                          |
| Red Box             | Queue is rejecting requests and initial spooling will not occur.                                                      |
| <b>Red and Bold</b> | Request active on this destination reflects a retry status. For information, refer to Understanding Request Statuses. |
| Blue Outline        | Destination is redirecting to another destination.                                                                    |
| Request Color Code  | Status                                                                                                                |
| Black               | Request is enabled and ready to de-spool                                                                              |
| Green               | Request is de-spooling.                                                                                               |
| Red                 | Request is interrupted. For errors pertaining to this request, refer to the log.                                      |
| <b>Red and Bold</b> | Request is de-spooling, but is in a retry state. If the retry condition persists, the job will be interrupted.        |

**Warning:** When destinations are rejecting, data may be lost. Make sure the application checks for this condition.

## USING THE HOSTS MENU

In several of the Client components a **Hosts** menu appears. There are two types of these menus, Absolute and Concurrent. In the **Absolute** menu, a list of hosts defined in the configuration appears. Selecting a host removes the previous selection. It is to use this in areas where one is working with one host at a time and is the more prevalent of the two menus. The **Concurrent** menu makes it possible to select more than one host at a time. It is used primarily on the Request Status Screen.

## SORTING REQUESTS


The requests showing on the current screen can be sorted by a specific column by double-clicking on the column header. This will sort on that column in ascending order. Double click again for descending order.

If the column selected is the RID column, then a dialog displaying sorting options will be presented. The sort sequence is whether to sort the RID number in ascending or descending order. The Display Children option is where to sort child request in the system. If the 'With Parent' option is selected, a request will have a 'P' next to the RID Number if it is a parent and a 'C' next to it if it is a child. If a request is both a parent and a child it will have a 'PC' next to it. Parent and Child RID numbers will be displayed a bold.

## VIEWING REQUESTS

Before jobs can be viewed the appropriate viewer for the data type must be configured in the Client Configuration screen. OM Plus includes a viewer that can display PCL, Postscript, and other type of documents such as simple, PDF graphics, etc. For these data types, OM Plus defaults to the DccView (our File View) viewer. To view in the Request Status window, from the **Request Cmds** menu, select **View Requests**.

***Note:** When in the File View Window, placing the cursor on a character shows a row/column location. This useful for determining locations for Report Distributor.*



The request appears in the selected application.

## USING DCCVIEW (FILE VIEW)


DccView displays the data one page at a time. Use the following options to view, locate, and print specific information.

- On the DccView screen, click **Next Page** to move to the next page or **Previous Page** to return to the previous page
- From the **Commands** menu, select **Find** to specify a search.
- From the **Commands** menu, select **Find Next** to move to the next instance of the searched item.
- From the **Commands** menu, Select **GoTo Page** to jump to a specific page.
- From the **Commands** menu, Select **Print** to specify a new range of pages.

## VIEWING REQUEST STATUS AND DESTINATION DETAILS

It is possible to view the details of any request status and destination by double-clicking the specific request or destination. Double-click a request and a screen similar to the following appears.

**Note:** To view this screen from the Character-based interface, on the Request Status screen, select Request Status Detail Screen, or on the keyboard, press i




RID00618

|              |                      |            |        |
|--------------|----------------------|------------|--------|
| Status:      | Held                 |            |        |
| Title:       | notices.txt          |            |        |
| Source:      | SKARLLAP             |            |        |
| Destination: | Dell_S5840           |            |        |
| User:        | skarll               |            |        |
| Date:        | 2/27/20, 10:19:46 AM |            |        |
| Pages:       | 2 / 2                | Priority:  | 11     |
| Copies:      | 1 / 1                | Data Type: | simple |
| Form:        | stock                |            |        |
| Options:     | purge                |            |        |

Tracking No skarllap15828167864242\_skarllap00618

Double-click a destination and a screen similar to the following appears.



Details

|                  |                                     |
|------------------|-------------------------------------|
| Device           |                                     |
| Address          | 192.168.244.129                     |
| Port             | 9100                                |
| Poll Group       |                                     |
| Use SNMP         | <input checked="" type="checkbox"/> |
| Confirm Delivery | <input type="checkbox"/>            |
| Hold Default     | <input type="checkbox"/>            |
| Purge Default    | <input checked="" type="checkbox"/> |
| URL              | -                                   |
| Type             | none                                |

Fail-over

☐ none

|             |      |
|-------------|------|
| Timers      |      |
| Open Timer  | 180  |
| Purge Delay | 100  |
| Write Timer | 5399 |
| Retry Timer | 30   |

Comment none

Support none

Model omstandard.js

Form Mounted stock

Form Feed after each job ☐

Form Feed after each copy ☐

Add Carriage Returns to Line Feeds ☒

Print Banner ☐

## UNDERSTANDING REQUEST STATUSES

Request statuses appear in the **Stat** field. For information on the status messages and their definitions, refer to the following table.

| Status | Definition                                                                                                                                                                                                                                                                                                                                                         |
|--------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| activ  | Output request is de-spooling or being transferred to another host.                                                                                                                                                                                                                                                                                                |
| busy   | Queue file for this output request is in use by another OMPlus application.                                                                                                                                                                                                                                                                                        |
| can    | Output request is canceled and after the purge delay time, will be removed from the queues.                                                                                                                                                                                                                                                                        |
| cmplt  | Request for an OMPlus mode destination completed successfully. A parent RID whose children have all finished printing.                                                                                                                                                                                                                                             |
| faild  | Fax or email report failed.                                                                                                                                                                                                                                                                                                                                        |
| faxed  | Fax has been sent.                                                                                                                                                                                                                                                                                                                                                 |
| fpend  | Request is waiting for the proper form to be mounted on the destination.                                                                                                                                                                                                                                                                                           |
| held   | Output request is on hold.                                                                                                                                                                                                                                                                                                                                         |
| intrd  | Output request failed while spooling or de-spooling (printing).                                                                                                                                                                                                                                                                                                    |
| maild  | Email report was delivered to the email subsystem.                                                                                                                                                                                                                                                                                                                 |
| partl  | Group fax has been partially sent (some faxes failed). Look at the fax status to determine which failed.<br>A parent RID whose children have not all finished printing.                                                                                                                                                                                            |
| printd | Output request has de-spooled successfully.                                                                                                                                                                                                                                                                                                                        |
| proc   | Output request is processing.<br><i>"proc" usually indicates a status change is occurring.</i>                                                                                                                                                                                                                                                                     |
| purg   | Output request has been purged from the queue system.                                                                                                                                                                                                                                                                                                              |
| ready  | Output request is ready to de-spool.                                                                                                                                                                                                                                                                                                                               |
| retry  | On UNIX this state occurs if the OM Plus server has not been able to get a connection or write to the device for more than 30 seconds. On a Windows server the amount of time can be configured in the Timeouts settings of the main server interface (not the Client).<br><i>"retry" can occur if the destination is off-line when OM Plus tries to de-spool.</i> |
| sent   | Report has been sent to an OMPlus or fax mode destination and the final result is not yet known.                                                                                                                                                                                                                                                                   |
| spool  | Output request is spooling (moving into the queue).                                                                                                                                                                                                                                                                                                                |
| susp   | Output request has been suspended and must be released to de-spool.                                                                                                                                                                                                                                                                                                |
| timed  | Output request is set to de-spool at a future date and time.<br><i>The future date and time can be seen from the output requests detailed information.</i>                                                                                                                                                                                                         |
| xfer   | Output request has been transferred to another host over the network or to disk.                                                                                                                                                                                                                                                                                   |
| 2big   | Report contains more pages than are permitted for delivery to this destination. The request will either need to be moved to a suitable destination for printing or the destination will need to be modified.                                                                                                                                                       |
| 2dumb  | Destination will not handle this type of data (for example, PCL or PostScript). The request will either need to be moved to a suitable destination for printing or the destination will need to be modified.                                                                                                                                                       |

## ACCESSING COMMAND SELECTIONS

| Commands Menus  | Accessing Method                                                                                                                                                                                       |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | Press <b>F6</b> for the command menu. If viewing the Request Status screen, the <b>Request Commands</b> menu appears. If viewing the destination Status screen, the <b>Dest Commands</b> menu appears. |
| Client          | Select <b>Requests</b> or <b>Destinations</b> from the menu bar. Alternately, many operations are available through the right click context menu.                                                      |

## USING REQUEST COMMANDS

It is possible to display, copy, cancel, or change a request or group of requests. The “Requests Commands” menu in the Client can be accessed either at the top of the screen in the menu bar or by right clicking on the destination list.

## CANCELING REQUESTS

It is possible to cancel selected requests and then purge them immediately or allow the purge time to elapse. For instructions on canceling requests, refer to the following table. For instructions on canceling requests, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                                                                                                                                                                                                                |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Cancel</b> , or on the keyboard, press <b>c</b> .                                                                                                                                                                                                                                                                                                                                                       |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Cancel Request</b> , when the Cancel Request screen appears, select either <b>Use Purge Delay</b> or <b>Cancel Immediately</b> , and then click <b>Yes</b> . If the selected request is a parent of other requests (see Displaying Parent/Child Information below) options to cancel just the selected job, the job’s children, or the whole family of jobs will be available. |

**Note:** *Purging immediately will delete all data associated with that request and cannot be undone. Only use this option if you are absolutely sure the request can be deleted.*

## CHANGING PRINT CONTROL FILES

A print control file is a set of instructions sent to the destination. The file is appended to the data. These instructions tell the printer to perform a behavior, such as printing landscape or duplex (or both). It is possible to change the associated print control file for a request, but a request can only have one print control file. For instructions on changing print control files, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                      |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Change Control File</b> , and then from the list, select the print control file.                                              |
| Client          | From the <b>Requests</b> menu, select <b>Change Print Control File</b> , when the Select Print Control File screen appears, select a file, and then click <b>OK</b> . |

## COPYING REQUESTS

It is possible to copy a request in full or a range of pages from that request (providing that OM Plus could count the pages for that data type). After selecting this, a prompt will appear asking for the starting and ending page number, whether or not to spool the new request on hold, and to which destination it should spool. For instructions on copying requests, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                              |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Copy Request</b> , all selected requests are copied with the same parameters.                                                                                                                         |
| Client          | From the <b>Requests</b> menu, select <b>Copy Request</b> , when the Print Report screen appears, enter the starting and ending pages, what destination to spool to, and whether or not to spool the new copy on hold. Then click <b>OK</b> . |

## CHANGING DESTINATIONS

It is possible to change the request Status Screen to a different destination. For information on changing destinations, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                               |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Destination Change</b> , or on the keyboard, press <b>d</b> , and then from the list, select the new destination.                                                                                                      |
| Client          | On the <b>Requests</b> menu or the right click menu, select <b>Destination Change</b> , when the Select Destination screen appears, select the destination, and then click <b>OK</b> , or left-click the request to move, and then drag it to the destination. |

***Note:** Drag-and-drop is only available for a single request at a time. To move multiple requests, use the command menu.*

## CHANGING EMAIL ADDRESSES

It is possible to change the email addresses that are associated with a request for an email mode destination. For instructions on changing email addresses, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select Email Addresses, press <b>F5</b> to add and <b>F6</b> to delete addresses, and then press <b>F3</b> to update the request. |
| Client          | From the <b>Requests</b> menu, select <b>Email Address</b> , when the Addresses screen appears add or delete an address, and then click <b>Save</b> .           |

## CHANGING FAX NUMBERS

It is possible to change the fax numbers associated with a request for a fax mode destination. For instructions on changing fax numbers, refer to the following table.

| Interface       | Accessing Method                                                                                                                                          |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the request Status screen, select Fax Numbers, press <b>F5</b> to add and <b>F6</b> to delete numbers, and then press <b>F3</b> to update the request. |
| Client          | From the <b>Requests</b> menu, select <b>Fax Numbers</b> , when the Fax Numbers screen appear add or delete a fax number, and then click <b>Save</b> .    |

## CHANGING FORM FILES


It is possible to change the form that is associated with any request. It does not affect the destination (mount). For instructions on changing forms, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                                                                             |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Form Change</b> , and then from the list, select the form to apply.                                                                                                                                                                                                  |
| Client          | From the <b>Requests</b> menu or right click menu, select <b>Form Change</b> , when the select Form screen appears, select a form, and then click <b>OK</b> . If the form does not appear, select <b>Enter Form Name</b> , click <b>OK</b> , when prompted enter a new form name, and then click <b>OK</b> . |

**Note:** “Change Form” changes the form that the print job requires. To change the form mounted on the printer, use the “Mount Form” command from the request menus to change the destination to use that request’s form.

## DISPLAY PARENT/CHILD INFORMATION

Sometimes a print job generates additional requests (such as a job sent through Report Distributor). OM Plus retains the relationship information about each family. If the request that is selected is either a parent request (has generated other requests) or a child (was generated by another request), the option to display the entire family tree is available.



The destination commands menu is available from this dialog by right-clicking on a request.

| Interface       | Accessing Method                                               |
|-----------------|----------------------------------------------------------------|
| Character-based | This feature not available.                                    |
| Client          | From the <b>Requests</b> menu, select Display Parent/Children. |

## HOLDING REQUESTS

It is possible to place all selected requests on hold, which prevents a job from de-spooling to the destination. For instructions on holding requestings, refer to the following table.

| Interface       | Accessing Method                                                                        |
|-----------------|-----------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Hold</b> , or on the keyboard, press <b>h</b> . |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Hold</b> .             |

## KEEPING REQUESTS

If a request is set to **Keep**, it does not purge until a purge command is issued. For information, refer to Purging Requests. For instructions on keeping requests, refer to the following table.

| Interface       | Accessing Method                                                                        |
|-----------------|-----------------------------------------------------------------------------------------|
| Character-based | On the Request Status Screen, select <b>Keep</b> , or on the keyboard, press <b>k</b> . |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Keep</b> .             |

## LOGFILE DISPLAY

OM Plus retains a log of all the transactions it performs with the most recent entries displaying first. For information, refer to Working with the Logfile. For instructions on displaying the logfile, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                     |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, or on the keyboard, press <b>l</b> . Then, press -- (minus) to move backward and + (plus) to move forward.                                                                                                             |
| Client          | From the Administration menu select <b>Logfile Display</b> or right click on the server names in the destination panel. If multiple hosts are selected or if multiple log files are available for any hosts, a logfile selection screen will appear. |

## MOUNTING FORMS

It is possible to mount a form on a destination so jobs in an fpend status will de-spool. When specifying a form mount, the destination continues to de-spool the active form. When it completes, the mounted form changes, all requests specifying the newly mounted form become enabled, and all other requests reflect a status of fpend (form pending). For instructions on mounting a form, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                                                                                      |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Mount Form</b> to mount the form for the request. A prompt will appear asking whether or not to disable the destination when changing the physical form. If yes, the destination will need to be re-enabled.                                                                  |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Mount Form</b> , when the Form Mount screen appears, confirm mounting the form for this request. A prompt will ask whether or not to disable the destination while the physical form is changed. If yes, the destination will need to be re-enabled. |

**Note:** When a form is changed on a destination, the system prompts the user whether to place that destination in a disabled state to give the user time to change the paper if needed.



## CHANGING COPY COUNTS

The number of copies that have been requested for a specific request can be increased or decreased before the job actually prints. Once it has printed it can only be increased. For instructions on changing copy counts, refer to the following table.

| Interface       | Accessing Method                                                                                                                               |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Number of Copies</b> , or on the keyboard, press <b>n</b> .                                            |
| Client          | From the <b>Requests</b> menu, select <b>Number of Copies</b> , when prompted, enter the number of copies to print, and then click <b>OK</b> . |

## CHANGING PRIORITIES

The priority of an output job refers to its position in the queue. If all output jobs have the same priority, then the order reflects the time they spooled (first in, first out). The priorities range from 0 to 39 with 0 being the lowest priority. The default priority is 20. For instructions on changing the priorities, refer to the following table.

| Interface       | Accessing Method                                                                                                                 |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen select priority change from the Command menu, enter the priority number.                            |
| Client          | From the <b>Requests</b> menu, select <b>Priority Change</b> , when prompted, enter the new priority, and then click <b>OK</b> . |

## PURGING REQUESTS

When setting a request to purge, OM Plus will remove it from the system after it has printed. There is a delay between the actual printing and the purging that equates to the purge delay setting for the destination. For information, refer to Using Define Destination. For instructions on purging requests, refer to the following table.

| Interface       | Accessing Method                                                                                                             |
|-----------------|------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Requests Status screen, select <b>Purge</b> , or on the keyboard, press <b>p</b> .                                    |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Purge</b> , and when prompted, confirm purging the request. |

## RELEASING REQUESTS

If a request is released, the status changes to ready and will be scheduled to de-spool. If a request reflects the Suspend status, the Restarting Requests command can be issued to start it where it stopped. For instructions on releasing requests, refer to the following table.

| Interface       | Accessing Method                                                                           |
|-----------------|--------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Release</b> , or on the keyboard, press <b>r</b> . |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Release</b> .             |

**Note:** For Raw TCP network destinations configured to use either unidirectional or bidirectional PJJ or Stream, OM Plus can perform a 'Printer Restart'. OM Plus will send the entire print job down to the printer with instructions to start printing on the designated page. This is useful for data types that OM Plus cannot do a restart on a page other than one (i.e. pcl-graphics, PDF, etc.) Unfortunately, not all printers that support PJJ support this feature.

## RESTARTING REQUESTS

Restarting a request will cause it to start printing on its current destination. Not all data types can be restarted on a specific page. If OM Plus cannot start from the indicated page it will restart from the beginning automatically. For instructions on restarting requests, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                                       |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Restart</b> , or on the keyboard, press <b>o</b> , and then when prompted, indicate the page on which to restart the request. If the number given ends in a lowercase P (p) character, OM Plus will attempt a Printer Restart. |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Restart</b> , when prompted, enter the page on which to restart the request, and then click <b>OK</b> . If the 'Use Printer Restart' box is checked OMPlus will attempt a Printer Restart.            |

## PRINTER STATUS

It is possible to retrieve the status of any printer configured to use SNMP. The current SNMP status of the printer and the last 100 entries in the log pertaining to the printer, appear. For instructions on retrieving a printer status, refer to the following table.

| Interface       | Accessing Method                                                                                                             |
|-----------------|------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Destination Status</b> , or on the keyboard, press <b>s</b> .                    |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Printer Status</b> , and the Printer Status screen appears. |

## SUSPENDING REQUESTS

It is possible to suspend a request to stop it from printing as if it had been interrupted by the system. Suspending a request does not disable the destination and the next request in the queue will start to de-spool. For instructions on suspending requests, refer to the following table.

| Interface       | Accessing Method                                                                                                                       |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Suspend</b> , or on the keyboard, press <b>s</b> .                                             |
| Client          | From the <b>Requests</b> menu or the right click menu, select <b>Suspend</b> , and then when prompted, confirm suspending the request. |

**Note:** Any data already delivered to the printer's buffer will still print.

## TRACING STATUS REQUESTS

It is possible to trace the status of a request that has been transferred to another OM Plus Server. For instructions on tracing status requests, refer to the following table.

| Interface       | Accessing Method                                                                                                                       |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Trace</b> .                                                                                    |
| Client          | From the <b>Requests</b> menu, select <b>Trace</b> , when the Trace screen appears, review the information, and then click <b>OK</b> . |

## VIEWING REQUESTS

It is possible to view any request. The application to use to view a request depends on the data type, therefore requests are not always viewable. For instructions on viewing the requests, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                                                             |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>View Request</b> , or on the keyboard, press <b>v</b> , and the file content will appear in text format. Most data types, other than simple data types, will not be legible.                                                                         |
| Client          | From the <b>Requests</b> menu, select <b>View Request</b> , when prompted, enter the starting and ending pages to view, and then click <b>OK</b> . The application that has been associated with the data type on the client configuration screen will launch, and then request will appear. |

## CHANGING THE BANNER STATUS

It is possible to change the flag that represents whether or not a banner page prints before a request. If the printer is set with the default banner value, it is not affected by this command because it only affects the banner OM Plus appends. For instructions on changing the banner status, refer to the following table.

| Interface       | Accessing Method                                                                                                   |
|-----------------|--------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select either <b>Banner On</b> or <b>Banner Off</b> .                                |
| Client          | From the <b>Requests</b> menu, select <b>More</b> , and then select wither <b>Banner On</b> or <b>Banner Off</b> . |

**Note:** The standard OM Plus banner includes the name of the user who spooled the request, the title of the request, the print control and form name used, the date printed, the Request ID, the hostname of the originating computer and whether or not this print is a restart or a reprint and if so, which pages are used. This can be customized to show more or less data if desired.

## CHANGING ADVANCED FORM FILES

It is possible to change the advanced form associated with the requests. For instructions on changing advanced form files, refer to the following table. See the section on Advanced Forms for more details on working with this tool.

| Interface       | Accessing Method                                                                                                                                                                |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Change to Advanced Form</b> , and then from the list, select the appropriate form.                                                      |
| Client          | From the <b>Requests</b> menu, select <b>More</b> , <b>Change Advanced Form File</b> , and then when the Select Advanced Form screen appears, select the appropriate form file. |

## SETTING SCHEDULED PRINTING

It is possible to set a future day and time to de-spool a request. When the scheduled time arrives, the status changes from Timed to Ready and it de-spools when the destination becomes available. For instructions on setting scheduled printing, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                      |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Time for Delay Printing</b> , and then when prompted, enter a future date and time to de-spool.                                                               |
| Client          | From the <b>Requests</b> menu, select <b>More</b> , <b>Time for Delayed Printing</b> , when the Set Time for Printing screen appears, enter the date and time to de-spool, and then click <b>OK</b> . |

## CHANGING TITLES

It is possible to change the title of all the selected requests to a new title, truncated to the first 50 characters. For instructions on changing request titles, refer to the following table.

| Interface       | Accessing Method                                                                                                                 |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Title Change</b> , and then in the field, enter the new title.                           |
| Client          | From the <b>Requests</b> menu, select <b>More, Title Change</b> , when prompted, enter the new title, and then click <b>OK</b> . |

## UPDATING OPTIONS

It is possible to update the -o options of a request. For instructions on updating options, refer to the following table.

| Interface       | Accessing Method                                                                                                                         |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, select <b>Update Options</b> , and then in the field, enter an option.                                     |
| Client          | From the <b>Request</b> menu select <b>More</b> , then <b>Update Options</b> . When prompted, enter an option and then click <b>OK</b> . |

## USING DESTINATION COMMANDS

### ACCEPTING REQUESTS

It is possible to set a queue (default option) requests. If the queue is set to accept requests, spooling is enabled to the target queue. For instructions on accepting requests, refer to following table.

| Interface       | Accessing Method                                                                                                          |
|-----------------|---------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Accept Requests</b> , and then click <b>Execute</b> .                         |
| Client          | From the <b>Destinations</b> menu, select <b>Accept Requests</b> , and then when prompted, confirm accepting the request. |

### ATTACHING TERMINALS (UNIX ONLY)

It is possible to attach a terminfo file to a destination. For instructions on attaching requests, refer to the following table. For information about terminfo files, refer to Using Advanced Destination Options.

| Interface       | Accessing Method                                                                                                                    |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On Destination Status screen, select Attach <b>Host/Terminal</b> .                                                                  |
| Client          | From the <b>Destinations</b> menu, select <b>Attach Terminal</b> , when prompted, enter the device name, and then click <b>OK</b> . |

## DISABLING DESTINATIONS

When a destination is set to disable, it continues accepting requests but does not de-spool (print) the request to the destination device. For instructions on disabling destinations, refer to the following table.

| Interface       | Accessing Method                                                                                                                                          |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Disable Destination</b> , or on the keyboard, press <b>d</b> .                                                |
| Client          | From the <b>Destinations</b> menu or the right click menu, select <b>Disable Destination</b> , and then when prompted, confirm disabling the destination. |

## DYNAMIC CLASS MAINTENANCE

Users in a security group assigned to a dynamic class can change destinations in the class. For instructions on accessing dynamic class maintenance, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                       |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | This feature is not available.                                                                                                                                                                         |
| Client          | From the <b>Destinations</b> menu, select <b>Dynamic Class Maintenance</b> , and the Dynamic Class Maintenance screen appears. It is possible to change any of the destinations in the security group. |

## ENABLING DESTINATIONS

When a destination is set to enable, it accepts requests and de-spools (print) the request to the destination device. For instructions on enabling destinations, refer to the following table.

| Interface       | Accessing Method                                                                                                                                        |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Enable Destination</b> , or on the keyboard, press <b>e</b> .                                               |
| Client          | From the <b>Destinations</b> menu or the right click menu, select <b>Enable Destination</b> , and then when prompted, confirm enabling the destination. |

## GETTING DAEMON/SERVICE INFORMATION

If the item selected in the destination tree is an OM Plus server (one of the root nodes of the tree) it is possible to display the status of the Daemons/Services.

| Interface       | Accessing Method                                                   |
|-----------------|--------------------------------------------------------------------|
| Character-based | Open <b>DCCADMIN</b> , then check <b>Services</b> menu.            |
| Client          | Right click on the host name and then select "Daemon Information". |

## MOUNTING FORMS

It is possible to mount a form on a destination so that jobs in a fpend status (form pending) will de-spool. When a form mount is specified, the destination continues to de-spool the currently active form. When it completes, the mounted form changes and all requests specifying the newly mounted form become ready and all other requests reflect a status of fpend. For instructions on mounting a form, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                                                                                                                                   |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Form Mount</b> , and then from the list, select the form.                                                                                                                                                                                                                                                              |
| Client          | From the <b>Destinations</b> menu or the right click menu, select <b>Form Mount</b> , when the Select Form screen appears, select a form, click <b>OK</b> , and when prompted confirm the mounting of the form. If the form does not appear, select <b>Enter Form Name</b> , click <b>OK</b> , when prompted enter a name for the form, and then click <b>OK</b> . |

## LOGFILE DISPLAY

OM Plus retains a log of all the functions it performs with the most recent entries displaying first. For information, refer to Working with the Logfile. For instructions on displaying the logfile, refer to the following table.

| Interface       | Accessing Method                                                                                                                                                                                                                                                |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Request Status screen, or on the keyboard, press <b>I</b> . Then, press – (minus) to move backward and + (plus) to move forward.                                                                                                                         |
| Client          | Select the <b>Logfile Display</b> option from the Administration menu or right click on a server name in the destination pane and select “Logfile Display”. If the client is connected to more than one host, a prompt will appear asking for host log to view. |

## PRINT TEST PAGE

For some solutions (most notably the Prescription Printing solution) a test page is used to configure the printer. To force a test page to be printed on the device, refer to the following table.

| Interface | Accessing Method                                                             |
|-----------|------------------------------------------------------------------------------|
| Client    | From the <b>Destinations</b> menu or the right click menu, select Test Page. |

## PRINTER STATUS

It is possible to retrieve the status of any destination configured to use SNMP. The current SNMP status of the destination and the last 100 entries in the log pertaining to the destination, appear. For instructions on retrieving a destination status, refer to the following table.

| Interface       | Accessing Method                                                                                                              |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Destination Status</b> , or on the keyboard, press <b>s</b> .                     |
| Client          | From the <b>Destinations</b> menu or the right click menu, select <b>Status</b> , and then the Printer Status screen appears. |

## PRINTER PROPERTIES

An administrator can pull up the 'Define Destination' screen for a specific destination directly from the request status screen by selecting the properties of the printer.

| Interface       | Accessing Method                                              |
|-----------------|---------------------------------------------------------------|
| Character-based | This feature is not available.                                |
| Client          | From the <b>Destinations</b> menu, select <b>Properties</b> . |

## REJECTING REQUESTS

It is possible to set a destination to reject requests. If the destination is set to reject requests, it is not possible to spool anything to this destination. For instructions on rejecting requests, refer to the following table.

| Interface       | Accessing Method                                                                                                            |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Reject Requests</b> , and then click <b>Execute</b> .                           |
| Client          | From the <b>Destinations</b> menu, select <b>Reject Requests</b> , and when prompted, confirm the rejecting of the request. |

***Note:** Be careful when setting a destination to reject requests. Destinations in this condition will ignore any jobs sent to them and, for that reason, data can be lost. To keep jobs from printing from a device, it is usually preferable to set that destination to "Disabled" so that jobs will come in, but not out and the data will be preserved.*

## SELECTING TRANSLATION TABLES

It is possible to add a translation table to a destination for character translation. This can be especially useful for transforming text for a destination, such as an older line printer, that may not be able to recognize all characters. For instructions on selecting a translation table, refer to the following table.

| Interface       | Accessing Method                                                                                                                          |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| Character-based | On the Destination Status screen, select <b>Translation Table Select</b> , from the list, select the table, and then press <b>Enter</b> . |
| Client          | From the Destinations menu, select Translation Table Select, when the Translation Table Select screen appears                             |

## LAUNCHING DESTINATIONS URLS

It is possible to launch the web browser that is set up in the Client Configuration and connect to the destination's URL. The URL must be in a valid URL format, i.e. <http://IPADDRESS>. For instructions on launching a destination URL, refer to the following table.

| Interface       | Accessing Method                                                               |
|-----------------|--------------------------------------------------------------------------------|
| Character-based | This feature is not available.                                                 |
| Client          | From the <b>Destinations</b> menu or the right click menu, select <b>URL</b> . |

## USING LOOKUP COMMANDS

The number of requests that appear on the Request Status screen can be limited by using the Lookup commands.

| Interface       | Accessing Method                                                                                                   |
|-----------------|--------------------------------------------------------------------------------------------------------------------|
| Character-based | From the Status screen, press the '3' key, <b>Lookup</b> . Select from the list displayed and press <b>Enter</b> . |
| Client          | From the <b>Request Status</b> screen, select <b>Lookup</b> . Select from the list displayed and press <b>OK</b> . |

### ALL REQUESTS FOR ALL DESTINATIONS

Displays all the requests.

### DISABLED DESTINATIONS (CLIENT ONLY)

Displays all the disabled destinations and the requests on those destinations.

### FORM

Displays all the requests with a specific form specified.

### GROUPS (CLIENT ONLY)

Displays all the destinations in a specific group and their requests. See Group Maintenance.

### REQUESTS FOR SELECTED DESTINATIONS

Displays all the currently selected destinations and the requests for those destinations.

### STATUS

Displays all the requests with a specific status.

### TITLE

Displays all the requests with a specific title.

### USER

Displays all the requests with a specific user.

### GOTO PAGE (CHARACTER-BASED ONLY)

Displays the specified page of a multiple page status screen.



## REMOTE HOSTS

(Character-based only) Displays the status information from another OM Plus host.

## OM PLUS ARCHIVE SYSTEM

OM Plus Archive is a module that stores and retrieves documents spooled through OM Plus. In UNIX, the archived reports can also be compressed. Reports are indicated to be archived with a command line option or from the Status screen of OM Plus. After the standard purge delay interval, the report is stored for later display. When a report is retrieved, it is displayed in the OM Plus report viewer and can be viewed or printed.

## ACTIVATING AND CONFIGURING OM PLUS ARCHIVE

From the OM Plus Administration, select Archive Tab > Archive Settings

OM Plus DM - Archive Administration for (skarllap)

Hosts

Host skarllap

Archive System Enabled

Archive Directory C:\Plustech\OMPlus\Server\archive

Temporary Directory C:\Plustech\OMPlus\Server\archive\tmp

How long should archive files be kept? 1 Months

How often should a new archive subdirectory be created? Every 10 days

How long should files be kept in the temp directory? 7 Days

Save

## DAYS REMAINING IN THE TRIAL PERIOD

Specifies the time left in the trial period. After this time expires archiving will continue if the job indicates it but it will not be possible to view or reprint the archive files. Once the system has been licensed, the screen will display "System Licensed".

## ARCHIVE DIRECTORY

The directory used for archiving. This directory should be on file system that has enough space to do the desired archiving.

---

## TEMPORARY DIRECTORY

In UNIX, the OM Plus Archive system gives the option of compressing spool files as they are archived. These files must be uncompressed before they can be viewed or reprinted. The tmp directory is the directory where compressed archive files will be placed when they are uncompressed.

---

## HOW LONG SHOULD ARCHIVE FILES BE KEPT

The OM Plus Archive system gives the ability to automatically remove archived files after the specified amount of time has passed. This can help ensure that the file system does not fill up. The **dccasweep** program reads this parameter and removes archived files that are older than the specified age. Files marked **keep** will not be removed even if they are older than the 'archive age'. The 'archive age' is specified as a number of days, months, or years.

***Note:** If dccasweep does not run, then archived jobs will not be removed.*

---

## HOW OFTEN SHOULD A NEW ARCHIVE SUBDIRECTORY BE CREATED

The OM Plus Archive system creates subdirectories under the archive directory for keeping spool files. The purpose of this is to enhance performance when searching, etc. This parameter specifies how often subdirectory should be created. Valid values for these entries are:

- Create a new directory every day
- Create a new directory every 10 days
- Create a new directory once a month
- Create a new directory once a year

---

## HOW LONG SHOULD FILES BE KEPT IN THE TEMP DIRECTORY

The first time compressed file is accessed it is uncompressed into the archive tmp directory. This parameter tells the **dccasweep** program how many days (0-365) to leave the file in the tmp directory before removing it. The file is not removed after each access to minimize the number of times that it is uncompressed. This value should be set to a number of days to maximize performance, but not so high as to create space problems.

## ARCHIVING REPORTS

Archiving spool files takes place at purge time after the report is printed. Marking a spool file to be archived can be accomplished in any of the following ways:

### FROM THE COMMAND LINE

The first method is to flag the spool file when it is submitted to OM Plus (spooled to dcclp). Setting an “-o” command line parameter does this. After the report is printed and the purge delay time period has expired, the spool file is then archived. The Archived command line options for dcclp are described below:

- **-o arch** – Archive this request and compress the file\*.
- **-o archu** – Archive this request but do not compress the file\*.
- **-o archk** – Archive this request but do not allow the sweep program to delete it.
- **-o archuk** – Archive this request, do not compress it, do not sweep\*.
- **-o noarch** – Do not archive this request (default).

***Note:** The compression options (\*) are available only on UNIX systems.*

On OM Plus for Windows systems, archive files are never compressed. These commands are effectively the same from a compression standpoint.

***Note:** On Windows, you must reboot the system after setting this variable in order for it to take effect.*

### THE LPPARCHIVE ENVIRONMENT VARIABLE

The second method is to set the **LPPARCHIVE** environment variable. This will cause all output jobs to be archived in one of two ways. If **LPPARCHIVE** is set to ‘y’, it is the same as having the ‘-o arch’ command line option of dcclp set. **LPPARCHIVE** set to ‘u’ is the equivalent to ‘-o archu’. **LPPARCHIVE** set to ‘yk’ is the equivalent to ‘-o archk’. **LPPARCHIVE** set to ‘uk’ is the equivalent to ‘-o archuk’.

### FROM THE REQUEST STATUS SCREEN

Another method is from the Request Status Screen. After an output job is spooled it can be marked for archiving directly from the archive menu. The indication that the output job will be archived after printing is there will be an “A” in the “P” (Purge) column of the Status screen (dccstat).

- **View Archive File** – Displays the Archive Report Selection screen (next page).
- **Archive Request** – Archive this request. Do not compress the file.
- **Archive Request Keep** – Archive this request. Do not allow dccasweep to delete.
- **Archive Request Compressed** – Archive this request and compress the file.
- **Archive Request Compress Keep** – Archive this request. Do not allow delete.
- **Do not Archive** – Do not archive this request.

### QUERYING ARCHIVED REPORTS

After reports have been archived, they can be retrieved and then viewed, printed, or deleted. From the 'Archive' menu in the Request Status screen or the 'Archive' Tab in the OM Plus Administration.

Fill in any combination of report attributes and press the 'OK' button.

- **From Date** – The starting spool date range to search.
- **To Date** – The ending spool date range to search.
- **Title** – All or part of the title of a report.
- **User** – The user who spooled the report.
- **Destination** – The destination where the report was spooled.
- **Text** – A text string within the report.

When the query is complete, a listing (above) of reports that match the query is displayed. From this screen single or multiple reports can be viewed or deleted by pressing , or printed.

***Note:** The Text field searches all the data within a report. The time to complete this will vary based on the size and quantity of reports searched and whether or not those reports are compressed.*

### CLEANING UP THE ARCHIVE AND TEMPORARY DIRECTORIES

The program **dccasweep**, can be executed at any time to clean up the archive directories and the temporary directories. When executed with no parameters the **dccasweep** program, using the values set with Archive Administration, removes the archived files in both the archive directories and the temporary directory used for repeated report viewing. To only clean up the temporary directory use a -t option.

**dccasweep** can be executed manually whenever it is necessary to clean up the archive directories, or executed automatically from the UNIX cron system or Windows' scheduled tasks program. The LPHOME environment variable must be set for **dccasweep** to function correctly. A script should be created that first sets LPHOME, then executes **dccasweep**.

## DOCUMENT CONDITIONING COMPONENTS

Standard OM Plus functionality can be complemented and extended through the use of one or more optional modules. For information about purchasing these optional components, contact a Plus Technologies Account Manager.

## CONTEXT DELIVERY

Context Delivery is an application that fits between the user or another application and OM Plus. Its purpose is to evaluate the request for user-defined criteria, and then make decisions based on rules entered by the administrator. Context Delivery is available as an add-on application to OM Plus. For information, contact a Plus Technologies Account Manager.

***Note:** On a Windows-based computer, Context Delivery is installed by default, and you only need an activation key to use it.*

*To use Context Delivery on UNIX-based computer, complete these steps:*

- *Obtain an activation key.*
- *Log in as root.*
- *From the \$LPHOME/bin path, run the following script: `# ./installcdplus`*

## SPOOLING WITH CONTEXT DELIVERY

Once Context Delivery is installed and activated it automatically checks for criteria in each spooled file without specific commands provided by the user.

## DEFINING SEARCH CRITERIA IN CONTEXT DELIVERY

Context Delivery is structured in levels and can be set up to make document delivery decisions based on multiple triggers. All level 1 decisions are independent from each other, all level 2 under the same level 1 are independent, and so forth.

The screenshot shows the 'OM Plus DM - Context Delivery' window. It has a 'Parameters' tab and a 'Hosts' tab. The 'Parameters' tab is active, displaying a table of criteria. The table has columns: Value, Type, Regular Expression, Search Amount, and Search Units. The criteria listed are:

| Value                             | Type             | Regular Expression | Search Amount | Search Units |
|-----------------------------------|------------------|--------------------|---------------|--------------|
| NO RECORDS MATCHING PRINT REQUEST | Data Contains    | No                 |               | 50 Lines     |
| UNRECONCILED RECEIVINGS REPORT    | Data Contains    | No                 |               | 50 Lines     |
| RPTECEU                           | Title            | No                 |               |              |
| MONTH VS. YEAR USAGE REPORT       | Data Contains    | No                 |               | 10 Lines     |
| BURST                             | Destination Name | No                 |               |              |
| CONSOLIDATED INVOICE              | Data Contains    | No                 |               | 20 Lines     |
| CONSOL ENERGY                     | Data Contains    | No                 |               | 20 Lines     |
| DUQUESNE LIGHT COMPANY            | Data Contains    | No                 |               | 20 Lines     |

Below the table are navigation arrows (up and down). Further down are configuration fields:

- Destination: [Dropdown]
- User: [Text Field]
- Title: [Text Field]
- Form: [Dropdown]
- E Form: [Dropdown]
- Print Control: [Dropdown]
- Data Type: [Dropdown]
- Hold: [Dropdown]
- Options: [Text Field] ☐ Replace
- Priority: [Spin Box, 0]
- Copies: [Spin Box, 0]
- ☐ Timed 03:34
- ☐ Record Only

A 'Save' button is at the bottom right.

To define a new criterion, complete these steps:

1. Select the upper level on which to add a new piece of criteria and select **Add Branch** from the commands menu.
2. From the Type list, select one of the following types of criteria.

| Criteria                    | Function                                                                                                                      |
|-----------------------------|-------------------------------------------------------------------------------------------------------------------------------|
| Copies                      | Checks the number of copies requested on the dclp command line (-n).                                                          |
| Data Type                   | Checks the OM Plus data type as specified with the -T switch on the command line. This will not change the default data type. |
| Destination                 | Checks the destination to which the request is being spooled (-d).                                                            |
| Data Contains               | Searches the file for the specified criteria.                                                                                 |
| Data Contains (remove)      | Searches the file for the specified criteria and removes it, if found.                                                        |
| Data Contains (remove line) | Searches the file for the specified criteria and removes the entire line, if found.                                           |
| Advanced Form               | Checks the electronic form file specified (-F).                                                                               |
| Form                        | Checks the standard or advanced form specified (-f).                                                                          |
| Hold                        | Checks to see if the hold flag was specified (-h).                                                                            |
| Options                     | Checks the -o command line options.                                                                                           |
| Priority                    | Checks the value of the requests priority (-q).                                                                               |
| Time                        | Checks to see the future time for de-spooling, if set (-w).                                                                   |
| Title                       | Checks the title of the request (-t or default).                                                                              |
| User                        | Checks the user ID of the user submitting the request.                                                                        |

**Note:** For the “Data Contains” types, an additional set of options appears. These options allow the lookup to be limited to a set number of bytes or lines. In the case where a match is not guaranteed, this keeps a potentially large file from being scanned in its entirety, which could take both time and resources. Limiting the search, if possible, is considered a best practice approach, but is not required.

3. In the Search Criteria field, enter the value to be compared. This can be a plain text, direct match or, if desired, a regular expression. If a regular expression is used, make sure Regular Expression is selected.

Once Context Delivery locates a match, it can change various parameters of the request. Context Delivery sets the parameters to the level of the most detailed match. If the request matches a level 2, but not an associated level 3, it will be spooled with level 2 settings.

Once the system reaches a match, the job's options can be modified. Leaving an entry blank will keep any settings currently set for that job. Otherwise, the data may be modified. For Priority and Copies, a different number may be entered. For User and Title, text may be entered. For Timed a time delay may be entered. For the rest, either text may be entered or, for convenience, an item may be selected from the drop down menu.

In addition, any Regular Expression match may be used as an input in a text field. Entering \$MATCH1 will enter the test that matched the first level's Regular Expression match. \$MATCH2 will return the second level's match, \$MATCH3 will return the third level's match.

**Note:** *The Regular Expression matching is probably one of the most powerful things in CD Plus. Say you have a text document with "FirstName:Frank" and "LastName:Smith". Entering a regular expression to match – for example: "(?<=FirstName:). \*" for the first parameter and "(?<=LastName:). \*" for the second would then allow you to enter "\$MATCH\$MATCH2" as the user name to return "FrankSmith" as the user. This would be accurate for any names entered in the document. This can be used in any text field, for any text in the document, in the title, in the destination name or anywhere else CD Plus can see text.*

## DECREASING SPOOLING TIME

While the above information dictates how CD Plus *does* work, it is important to take a minute to discuss how CD Plus *should* work. CD Plus will look at every file coming into OM Plus. As such, if it is not configured to be as efficient as possible, undesired printing delays can result. To see how this plays out, let's set up an example.

Consider a case where print jobs are being written to a folder and picked up for spooling by the Scan Service. These jobs contain a destination name at the beginning of the title that CD Plus must find and use. The naming convention for these destinations is a letter followed by a two digit number (for example A56, K78, Z99). There are, indeed, 2600 destinations.

The first thing is to **fail early and fail often**. Set up one quick test will save any non-CD Plus jobs from traveling through the entire list of parameters. In this case, the easiest thing would be to have the first level filter by spooling destination. Doing so means that only jobs coming in through the Scan Service would go on for additional testing while all other jobs immediately fail out and exit CD Plus unchanged. That could significantly reduce the processing times required for any job that doesn't need CD Plus.

Next, **think in terms of levels**. It would be tempting\* to set up 2600 second level parameters to test these jobs, but think about a job headed for destination Z99. That job would have to pass through all 2600 definitions before it finally matched. This would take time and resources. It would be more efficient to set up 26 second level parameters to catch jobs by their starting letter, then define things further in a third in a third level parameter that matches the numbers. This way job Z99 would only check against 126 parameters. In fact, every job for a destination starting with a letter except "A" would see significant gains, while "A" printers would only see a slight loss. There would, though, be 2323 (26 second level and 100 each 3<sup>rd</sup> level) parameters that need to be configured.

***Note:** "Tempting" may not be the right word. However, it is useful to think about the CDPlus configuration file as a text file (which it is). If you need to enter 2600 different lines, let us know. We have some ways to programmatically enter that data and create the CD Plus configuration file without typing all that in by hand. In that way, it could be at least simple.*

Even better, think about **Regular Expressions**. Thinking ahead can save a lot of time. If the printers are defined in OM Plus using the same naming convention, then a simple regular expression like "[A-Z]\d+" would catch the destination name and \$MATCH# could be used to enter that in the destination field. That could condense 2600 lines of parameters into one. That would be a significant performance gain all around, to say the least.

Finally, if possible, **use properties, not data**. This whole exercise is looking just at the job title. That is one of the properties that we can see easily. If CD Plus needs to look into the file using one of the "Data Contains" matches, try to make that a final step and one only used if every other step has failed. Opening the file to read the data takes time and resources. It can be done if there's no other way, but it is, by far, the least efficient thing CD Plus does. If a file must be opened, limit the reading to as few lines or bytes as possible. If a 400 MB before it lets it fall through to the next test if it is not limited. If it's limited to the first 20 lines, then the test will go much faster. If CD Plus was able to take action before this based solely on the properties of the print job, that would be even better. This could require some modifications to the spooling process or application, but if thousands of jobs are affected, it could provide worthwhile.



## REPORT BUNDLER

Report Bundler is a module for OM Plus that allows for the creation of a single print job document from multiple print job documents. The bundled document ensures all information is delivered at the same time in a single print job to the desired destination.


While there are many applications for Report Bundler, users will benefit most from its ability to aggregate print jobs and optimize the performance of their printer hardware. Report Bundler is available as an add-on module to OM Plus. For more information, contact a Plus Technologies Account Manager.

### CONFIGURING REPORT BUNDLER

To configure Report Bundler, first create a local destination using the “Bundle” mode. At this stage, the bundle type can be determined.

For information on the four bundling type options, refer to the following table.

| Option | Description                                                                                  |
|--------|----------------------------------------------------------------------------------------------|
| Bundle | Bundles reports based on a user defined parameter that must be included on the command line. |
| Form   | Bundles reports based on the selected form.                                                  |
| UserId | Bundles reports based on the submitter's user ID.                                            |
| Title  | Bundles reports based on the report title.                                                   |



After creating a bundle destination, the parameters for that bundle must be defined. To access the Bundle Parameters screen, click “Report Bundler” from the “Document Conditioning” section of the Control Panel.

On the **Bundle Parameters** field, each line of the parameter list represents a match to the value in **Bundle Type** field defined in the destination definition screen. For information on each value and their definitions, refer to the following table.

| Value          | Definition                                                                                                                                 |
|----------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| Resolved Value | Value to match for this parameter.                                                                                                         |
| Destination    | Destination to where to spool bundled requests for this parameter.                                                                         |
| User           | User ID to use when spooling this bundle. This allows unique security setups.                                                              |
| LP Options     | Options to use for this bundle. These options are command options for dclp command. For information, refer to Using the Command Reference. |

From the **Bundle Parameters** window, select the **Parameters** menu, **Add Parameter**, and then select each field to enter a value. While each bundle printer can only bundle on one parameter, it can have multiple value matches for that parameter. If a request is spooled to the bundle printer that does not match any of the resolved values, the request is marked interrupted. There can be multiples of the same resolve value configured. In this case, the request will be put into a separate bundle for each of the matching parameters.

The bundler can be configured to bundle all matching jobs for a resolved value that is not defined. By adding a line that has a resolved value of ‘default’ the system will still bundle like jobs together even if their specific value is not listed. It will then apool them to whichever destination with whatever options are associated with the default value.

### SPOOLING WITH REPORT BUNDLER PLUS

Jobs are spooled to the Report Bundler destinations just like any other OM Plus destination. All jobs spooled to the destination will be bundled until a bundle terminating request is submitted. There are two methods for terminating a bundle.

- Spool the last request with a '--o trailer' option on the command line. For information, refer to dcclp in Using the Command Reference.
- Spool a job that contains only the word BUNDLETRAILERRECORD with no spaces and in all capital letters.

Once the bundle is terminated all documents spooled since the last terminating request are appended together in the order received, and they are submitted as one request.

***Note:** If the system is set to display parent/child relationships the new bundle request will be shown as a child of the trailer request.*

## REPORT DISTRIBUTOR

Report Distributor is an application for OM Plus allows users to burst large enterprise reports into individualized sub-reports based on triggers in the document's meta data or the document text. These individual sub-reports can then be sent directly to specific end user requested destinations such as printers, fax machines, email systems, Web sites, and Intranet sites. Report Distributor is available as an add-on application to OM Plus. For information, contact a Plus Technologies Account Manager.

OM Plus customers will appreciate the automation of report burst and bind processes, which helps reduce errors inherent in traditional report distribution processes. Additionally, use of Report Distributor can result in reduced consumable costs and reduced information latency.

Report Distributor can burst requests only for the following data types:

- simple
- pcl-1

## UNDERSTANDING REPORT DISTRIBUTOR

Report Distributor compares each page of a request against a set of independent criteria. For each set of criteria a new request is generated. Once all the pages have been compared, the new requests are spooled to their destinations. The sets of criteria are called pages on the interface. If at the end of the compare a page's criteria returns true then the document page is added to that criteria's request. It is possible to add a document page to multiple requests by meeting multiple criteria. What this allows, for example, is to deliver to a user's printer or address only pages of a large report in which they are interested.

To use Report Distributor, a Report Distributor printer must be defined in Destination Configuration, and a path to a working directory put in the **Destination Device** field. The working directory is used as working space. When a report is burst into multiple spool files, this directory is used as the temporary working directory. Then in the Report Distributor Configuration menu, create a Report Distributor Script File. When a job is spooled to Report Distributor, this script file is used. If a name is not specified, it saves with the name **default**. The default file is used if no file is specified.

## DEFINING SEARCH CRITERIA IN REPORT DISTRIBUTOR

For each page, a set of compares must be defined. These compares will look at specifically defined location on the current document page. A range of rows between 1 and 99 and a range of columns between 1 and 256 define this location.

For lines other than the first, the location can be defined as relative to the previous line. By using `+[value]` or `-[value]` in the row and column fields.

Report Distributor will evaluate an area that has a position relative to the start point of previous match. This only works if the relative line uses the AND (&) logical operator.

Within the defined location, Report Distributor will look for a match to a specified string of characters or numbers. In addition, it can look for numbers larger or smaller than the specified value.

Each line of a page is defined by the following set of parameters.

- **Oper:** logical operator for the row. This is unavailable on the first row. See the list of logical operators below for more information.
- **Type:** type of data for which to scan.
  - **Text (text):** string of text.
  - **Numeric (num):** number or range of numbers.
  - **Nomatch: (-mat):** no match descriptor.
  - **Collate (coll):** collate type. It does not return a result for evaluation. Instead it looks in specified location and generates a separate report for each unique value. This avoids the need to define a trigger for each desired section. The unique value is available to the operation as a variable \$COLL (%COLL% on Windows).
- **Ignore:** Determines whether the text type trigger will be case sensitive. Alternately, up to 10 characters can be entered in this field. These characters will be ignored in a numeric trigger.
- **From Row:** line number on each document page in which to start the search. The values that start with a '+' character allow the row to be relative to match on the previous line.
- **To Row:** line number on each document page in which to end the search. The values that start with a '+' character allow the row to be relative to a match on the previous line.
- **From Col:** character column number on each document page in which to start the search. The values that start with a '+' character allow the column relative to a match on the previous line.
- **To Col:** character column number on each document page in which to end the search. The values that start with a '+' character allow the column relative to a match on the previous line.
- **<-->** (Numeric triggers only)
  - **=:** trigger on a number is equal to a specified number.
  - **<:** trigger on a number is less than a specified number.
  - **>:** trigger on a number is greater than a specified number.
  - **!:=:** trigger on any number that is not equal to a specified number.
- **String/Number:** specified text or number for which to scan.

For each page, an operation must be defined. Take this action in case the criteria evaluate is true. *If no operation is defined, the document page is discarded.*

- **Destination:** Destination to which to spool.
- **User:** User ID from which the request spools. This allows special security setups.

- **LP Options or Delivery:** The options for the dclp command. For information about dclp, refer to the Using the Command Reference.
  - Alternately a command can be used and Report Distributor will execute this command after all the pages have been evaluated and it has at least one matched document page.

All operations occur after the document has been completely processed. Any requests that are created here will be children of the original job sent to the repdist printer.

## NOMATCH OR LASTMATCH

Plus Technologies recommends that a page with a single line containing the nomatch type be used as the final test in the file. This will allow operation (or not) on any document page that has not had a match.

Each Report Distributor file must be set to either nomatch or lastmatch. Nomatch causes pages that do not match any of the criteria to be operated on by a page with a nomatch line defined. Lastmatch causes any page that does not match any of the criteria to be operated on by the last test that had a successful match.

## LOGICAL OPERATORS


The logical operators allow a row to correlate to a previous row. This allows for multiple criteria on a page for the purpose of triggering an operation. For information on the operators and their definitions, refer to the following table.

| Operator | Definition                                                                                                                                                                                                                                       |
|----------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| &        | Both this row and the previous row must resolve for this operation to happen.                                                                                                                                                                    |
|          | Either this row or the previous row must resolve for this operation to happen.                                                                                                                                                                   |
| &(       | A parenthetical compare begins where there are multiple lines within a single set. It compares the previous line to the result of all lines between this operator and the first parenthetical close. Both sets must be true for this to be true. |
| (        | Like the &( operator except that either the previous line or the set must be true to return a true value.                                                                                                                                        |
| &)       | A parenthetical compare closes. This line is the last line included in the compare and is evaluated like the & operator.                                                                                                                         |
| )        | A parenthetical compare closes. This line is the last line included in the compare and is evaluated like the   operator.                                                                                                                         |

## EXAMPLE

The following example scans each page of a document and looks for the word Print Manager defined by rows 1-10 and columns 60-80. If it finds a match it then looks in the next 10 lines in the same range of columns for either the number 9375551212 or 9375552121. If there are any dashes or parenthesis in the number they will be ignored. If either of these numbers is found then the compare has evaluated true. The current page spools to destination support with a form of letterhead.

If either the first line or both of the second lines fail it will be a nomatch. In this case it will spool to the nomatch destination selected on page 2.



The logic appears similar to the following.

if(firstline is true)

then

if(secondline is true OR thirdline is true)

then

spool page to lexmark with form letterhead

endif

endif

## CONFIGURING MULTIPLE OM PLUS INSTALLATIONS IN A DISTRIBUTED ENVIRONMENT

OM Plus can be set up to broadcast its destinations to other OM Plus systems. This allows users or applications on one server to spool to destinations defined on another OM Plus Server.

### STARTING REMOTE SERVICES

Before OM Plus installations can broadcast their defined destinations to one another, the proper services must be running.

#### STARTING ON WINDOWS

To start the remote service on OM Plus Server with a Windows operating system, from the OM Plus DM Server screen, select the **Services** tab, and then confirm that OM Plus Service, End-To-End Service, and Remote Service is installed and running.

#### STARTING ON UNIX

To start the remote service on OM Plus Server with a UNIX operating system, run the following command.

```
$LPHOME/bin/dccpingrem
```

***Note:** Unlike the other UNIX services, `dccpingrem` does not have a separate shut down command. See `dccshut` for more details.*

### BROADCASTING DEFINED DESTINATIONS

Before OM Plus can broadcast its defined destinations and standard classes, the following file must be created.

```
$LPHOME/system/sendHosts
```

The file should contain a list of names of all the other OM Plus Servers that should receive the broadcast destinations. After starting the service or adding or removing a destination, OM Plus will contact all the OM Plus Servers on this list and inform them of the destination list.



## RECEIVING BROADCASTED DESTINATIONS

Before an OM server can receive broadcasted destinations, the following file must be created.

```
$LPHOME/system/receiveHosts
```

The file should contain a list of the names of all the other OM Plus Servers that should have their destinations received by this server. When the remote service is started, it will poll all the servers in this file for their list of printers.

For Windows servers, the names need to be the same as the computers from the Computer Name tab of each systems **System Properties** dialog. If the entire domain name is included on the name presented there, use only the first portion that is the system's name.

For UNIX/Linux servers, the names need to match the result of a **uname -n** command executed from each system.

## ADVANCED SETTINGS

Two other files are used for determining additional settings for the OM Plus server. The first of these files is located at:

```
$LPHOME/system/pingParams
```

The file holds three lines options. The first is "ReceiveAny" which, if set to "y" will allow any host broadcasting its definitions to add its destinations to this server, regardless of whether or not that server is named in the receiveHosts file.

The second setting is "SendAny" which, if set to "y" will allow any OM Plus server requesting destinations from the server to receive those destinations.

"ProxyMode", if set, will allow an OM Plus server to transmit destinations it receives from other OM Plus servers as though they were its own. This can be useful in a secure environment where not all OM Plus servers needing to share destinations can be found by each other. A central proxy server can be used to relay the destinations from one to the other.

## SPOOLING TO REMOTE DESTINATIONS

OM Plus can spool to a remote destination the same way it is possible to spool to a local destination with one exception, different servers having destinations with the same name.

***Note:** If an OM Plus server has a local destination with the same name as a remote destination, OM Plus will spool the job to the local destination. To spool to the remote destination use the hostname in the destination field, i.e hostname!destination.*

## EDITING THE RECEIVE HOSTS AND SEND HOSTS FILES

The send and receive hosts files can be created and manipulated from the Remote Printing tab in the OM Plus Administration.

OM Plus DM - Remote Setup (skarllap)

Hosts

**skarllap**

Alias

Send

☒ Send to any ☐ Proxy

MPS

Add Remove

Receive

☒ Receive from any

Transform

Add Remove

Save

## ALIAS

OM Plus also has the option to broadcast its definitions under a different host name. This can be especially useful in a high availability solution where multiple hosts may exist and function as the same system.

In order to specify a different host name, or alias, enter the new host name in the alias field. This OM Plus server will now be seen as that host name when sending and receiving destinations.

## SEND TO ANY/RECEIVE FROM ANY

OM Plus can also receive and send destinations to servers not explicitly defined in the list. In this case, the server must be set to send to any or receive from any. In send to any, any other OM Plus server that connects to the server will be allowed to receive a list of destinations from any other server that contacts it. Both of these settings can be very useful in a large distributed environment, or an environment where print servers are being added or removed regularly.

## PROXY

Currently UNIX only, this option allows an OM Plus to broadcast destinations received from another OM Plus server as its own. This option would mostly be used in situations where one OM Plus server was serving as a bridge between two other OM Plus servers who are unable to connect due to security or logistical reasons.

### ADDING/REMOVING SERVERS

---

To broadcast destinations to a remote server, use the appropriate “Add” button to add that server to the “Send” list. To add a server to ask for destinations, use the “Add” button for the “Receive” list. Servers can be removed from either list using the corresponding “Remove” button.

### SAVE

---

To update the system, the configuration must be committed using the “Save” button. Closing the window or selecting a different host without saving will remove all changes.


## OM SCAN SERVICE

OM Scan is a utility that can monitor one or several folders in order to output any files written into those folders. This functionality is especially useful for capturing output from legacy applications that write data to a folder, but do not provide print spooling capabilities on their own.

**Note:** *The most important thing to remember is that OM Scan will deliver any file to OM Plus Delivery Manager exactly as it is written to the folder. And, by default OM+ DM will output whatever files it receives to a printer exactly as it receives them. Therefore, make sure that any file being processed by OM Scan Service can either be handled by the printer or that appropriate filters are in place to perform any necessary transformations of the data.*

## STARTING OM SCAN SERVICE

OM Scan Service can be started through OM Plus DM Server application.



## CONFIGURING OM SCAN SERVICE

From the OM Plus DM Server application, select the “Environment” tab and then select the “Settings” button. In the screen that pops up, select the “Scan Service Settings” tab and then press the “Configure Scan Service” button.

### INITIAL SETTINGS

| Property                   | Value |
|----------------------------|-------|
| Debug                      | False |
| <b>Email Configuration</b> |       |
| Cycle Time.                | 1     |
| Max Threads.               | 5     |
| Clear Messages.            | True  |

**Debug:** Should the scan service run in a debug mode?

**Cycle time:** Time, in seconds, to check the email server.

**Max Threads:** Maximum number of concurrent email connections.

**Clear Messages:** Should messages found in the target inbox be marked as read?

## FOLDER SCANS

OM Scan Service Configuration

General | **Folder Scans** | Email Scans | Database

| Folder | Property                       | Value |
|--------|--------------------------------|-------|
|        | Folder                         |       |
|        | Cycle time                     |       |
|        | Sorting                        |       |
|        | Process Sequentially           |       |
|        | <b>Sub Directories Options</b> |       |
|        | Process Sub-folders            |       |
|        | Max Threads                    |       |
|        | <b>Script Options</b>          |       |
|        | Script name                    |       |
|        | Script Parameter 1             |       |
|        | Script Parameter 2             |       |
|        | Files Removed                  |       |
|        |                                |       |

Apply Close

To create a new folder scan process, select the Folder icon from the top of the left pane and fill in the required fields.

**Folder:** The folder to monitor.

**Cycle time:** Frequency, in seconds, with which the scan service should check the target folder.

**Sorting:** In which order should files be spooled if found? Creation time and file name are options, the default is the order in which the files are found in the folder, which may not be reliable.

**Process Sequentially:** If a sort order is defined, should the files be processed in that order?

**Sub Directories Options:** by default the scan service will not scan directories below the target directory. These settings can modify that behavior.

**Process Sub-folders:** Should sub folders be processed or ignored?

**Max Threads:** Maximum number of concurrent threads to use to scan subfolders.

**Script Options:** Once a file has been found, the scan service uses a script to understand what to do with the file. The default behavior is to pass the job to the destination specified in Script Parameter 1 with the options specified in Script Parameter 2. To change the behavior, change the script specified in the Script Name to another script in the OM Plus userfilter directory.

**Files Removed:** After executing the script specified, should the file be removed? This can be turned off of the script is designed to do something different with the file, but otherwise should remain true.

## EMAIL SCANS

OM Scan Service Configuration

General | Folder Scans | Email Scans | Database

MailBox

| User    | Host    |
|---------|---------|
| Unknown | Unknown |

Property Value

|                       |                   |
|-----------------------|-------------------|
| <b>Mailbox URL</b>    |                   |
| Host                  | mailserver.com    |
| User                  | newuser           |
| Password              | *****             |
| Port                  | 535               |
| Authorization         | newuser           |
| User Definition       | Use email address |
| User Map File         |                   |
| Cycle time            | 60                |
| Enable SSL            | False             |
| Keep messages         | False             |
| <b>Script Options</b> |                   |
| Script name           | spoolmail.bat     |
| Script Parameter 1    |                   |
| Script Parameter 2    |                   |

Apply Close

**Host:** Web address of mail server.

**User:** User name with permissions to access the desired inbox.

**Password:** Password for user above.

**Port:** Port to use to connect to the mail server (optional).

**Authorization:** The authorization to uses to connect to the mailbox (optional).

**User Definition:** How should the system connect an email address to a user name. "Use Email address" will use the user name of the email address (everything to the right of the "@"). "Use File Lookup" uses a map file (specified in the next line) to match an email address with a user name. "Use Database lookup" uses the database configured in the next tab.

**User Map File:** This is complete pathname for a text file to be used to map email addresses to user names.

**Cycle Time:** How often to check this specific inbox.

**Enable SSL:** Is SSL required?

**Keep Messages:** Determines if the service should keep or delete messages on the server after retrieving them.

Script options are the same as before. The script defined in the "Script Name" field will be called and passed the parameters in Script Parameter 1 and Script Parameter 2. By default, the "spoolmail.bat" script will spool the body of the message as well as any attachments in supported formats.

## DATABASE

OM Scan Service Configuration

General | Folder Scans | Email Scans | Database

| Property                            | Value                    |
|-------------------------------------|--------------------------|
| Connection String Definition Method | Build connection string. |
| <b>Connection String Components</b> |                          |
| Server                              | dbserv                   |
| Driver                              | SQL Server               |
| Database                            | usemap                   |
| User                                | dbuser                   |
| Password                            | *****                    |
| Table                               | usetab                   |
| Email Field                         | usemail                  |
| User Field                          | username                 |

Apply Close

This configures the database to be used to resolve email address into usernames.

**Server:** The host name or IP address for the database server.

**Driver:** The type of database used. Currently supports SQL, Oracle and Firebird.

**Database:** The name of the database or schema that holds the user table.

**User:** User name allowed to access the database.

**Password:** Password for user specified above.

**Table:** The table holding the user name and email addresses.

**Email Field:** Field in the table that contains the email addresses.

**User Field:** Field in the database holding the user names.



## R-3/SAP BCXOM INTERFACE

OM Plus has two certified SAP interfaces that facilitate the submission of SAP output requests to OM Plus and the return of request status back to SAP. The older SAP Polling interface periodically queries OM Plus via command line to determine the status of outstanding requests. It is available for all OM Plus supported operating systems. The SAP Callback interface is a more efficient and tunable. In callback mode, OM Plus systems establish persistent connections back to the servers SAP over which request status changes are reported. The OM Plus Callback interface is only available on the following platforms: AIX, Linux86, HP-UX Itanium, Solaris SPARC and Windows.

There are three steps required to get the interface working properly:

1. Configuring ROMS, LOMS and device definitions in SAP.
2. Creating a sapconfig file in the OM Plus constants directory.
3. Setting up an enterprise RID span in OM Plus.

## CONFIGURING SAP

SAP configuration consists of defining a Real Output Management System (ROMS) definition, one or more Logical OMS (LOMS) definition(s), OM Plus commands to be used by SAP and Device definitions corresponding to OM Plus destinations. These definitions are all defined via the SAP Spool Administration (SPAD) transaction.

1. Go to the Spool Administration Screen (/nspad).
2. Click on Full Administration to make the Output management systems tab visible, if necessary.
3. From this SPAD Initial Screen, perform the following configurations.

## IMPORTING SAP CONFIGURATION

In lieu of creating the SAP OMS definitions from scratch, as described in the following sections, OM Plus provides a file (\$LPHOME/constants/sapxomcfg.txt) which provides a predefined ROMS (OMPLUS), a callback and a polling LOMS (OMPCB and OMPPOL) and command definitions corresponding to the configurations defined in the following sections.

1. From the SPAD Initial Screen, click Utilities > For output management system > import.
2. In File system info., enter the full path to the provided configurations file, substituting the proper value for \$LPHOME (eg. /usr/lpplus/constants/sapxomcfg.txt) then click Server.
3. In Operation, click Import
4. In Options, Click Perform Import (either one).
5. Click the Execute button. 

**Note:** Alternatively, you may transfer the file to your workstation, enter the full path to the file there and select Frontend computer.

If OM Plus has been installed in a non-default directory, edit the Command path in the Operating System Commands to reflect the path in the \$LPHOME environment variable. (Be sure to include the trailing slash character!) If callback is to be used, edit the callback LOMS definition (OMPCB) to enter the proper target SAP system names. Timing and other parameters may also be adjusted. (see SAP Logical OMS & Commands

Configuration) below. It may be useful to create additional callback LOMS definitions if it is desired to have groups of destinations with differing timing and callback event reporting levels.

If callback is not to be used, the definition for the callback LOMS, OMPCB, may be deleted. Similarly, if polling is not to be used, the polling LOMS (OMPPOL) definition may be deleted.

## SAP REAL OMS CONFIGURATION

The SAP Real OMS configuration defines an instance of an Output Management System, informing SAP of the OMS's capabilities. One ROMS definition for OM Plus is required.

1. From the SPAD Initial Screen, click on the Output Management Systems tab, then the Real Output Management Systems Display button.

2. To define a new ROMS, click on the Create  button. (Or double click on an existing ROMS entry to modify it.) This will bring up the ROMS definition screen.

3. Edit the ROMS definition as follows:

- a) Set ROMS Name and Description as desired.
- b) Select 'Command Line' under the Tasking attribute.
- c) Select all boxes under the Job Status attribute.

- d) Select 'Queue query' under the Device Status attribute.
- e) Enter a Reconfiguration Request delay. This is the interval at which OM Plus will perform an empty callback to check for SAP LOMS reconfiguration if there have been no request status callbacks.
- f) The remaining OMS attributes should be deselected and the remaining text fields should be left blank for possible future use.
- g) Click the Save button to save the ROMS definition.


---

### SAP LOGICAL OMS & COMMANDS CONFIGURATION

To use SAP BC-XOM, at least one LOMS to be defined. LOMS definitions support the two types of interfaces – polling or callback. (Callback, if available, is preferred due to its lower overhead and greater customization potential).

1. From the SPAD Initial Screen, click on the Output Management Systems tab, then the Logical Output Management System tab, then the Logical Output Management Systems Display button.
2. To define a new LOMS, click on the Create button. (Or double click on an existing LOMS entry to modify it.) This will bring up the LOMS definition screen.


## CONFIGURING A POLLING LOMS:




Set the logical OMS Name and Description as desired.

1. Select the OM Plus as the Real OMS.
2. Set a Command group letter to share a single set of command definitions (as defined below) across multiple LOMS definitions. All LOMS should reference this letter. Otherwise, leave the field blank. Enter the command definitions for each LOMS separately.
3. Select 'Polling' under the Jobs section.
4. If the 'No info = error' checkbox in the Jobs section is not visible, click on the 'Extended config'  button. Clear the 'No info = error' checkbox. (This prevents SAP from marking output requests in error if OM Plus does not respond to a status poll in a timely manner. This could happen due to network errors.)
5. Status Dialog boxes may be set as desired.
6. The entries on the OMS configuration tab should be left blank.

## CONFIGURING A CALLBACK LOMS:



1. Select the SAP configuration tab.
2. Set the Logical OMS Name and Description as desired.
3. Select the OM Plus ROMS as the Real OMS.
4. Select 'Callback' under the Jobs section. This should cause additional field(s) to display.
5. Enter the desired SAP instance in the Target for callback field.
6. Set a Command group letter to share a single set of commands definitions (as defined below) across multiple LOMS definitions. All LOMS should reference this letter. Otherwise, leave the field blank. Enter the command definitions for each LOMS separately.
7. Set 'Event report level' to the desired level of reporting (See text below).
8. Select Devices/Queue query and Jobs/Query and Jobs/Can be deleted if it is desired to make these functions available for this LOMS in the SAP user interface. The query options will cause a Tasking Target to be requested. Enter the desired SAP server instance.
9. Status Dialog boxes may be set as desired.



10. Select the OMS configuration.
11. Set Send Period to the maximum interval that OM Plus should accumulate status events for before returning them to the SAP callback target. (see below)
12. Set Number of Events to the number of status events that can be allowed to accumulate before OM Plus returns status earlier than the Send Period. (see below)
13. Set the Callback Restart Interval to the number of seconds OM Plus should wait before retrying a failed callback target.
14. Attribute Record and OMS Configuration should be left blank for future use.

The settings of Event report level, Send Period and Number of Events can have major impact on speed of update and overhead in SAP and OM Plus. An OM Plus node periodically scans for ready events at the Send Period interval of any LOMS which are accessing it. If multiple LOMS are accessing an OM Plus node, scans may occur more frequently to accommodate the requested timing of each LOMS. The scan interval is limited to a minimum of 5 seconds and a maximum of 30 seconds. When a request or its associated destination change status, this event is filtered by Event report level. If the event is at or above the reporting threshold, it is counted as ready. When a scan occurs, the event is reported to SAP if the Send Period has elapsed or the Number of Event has been reached.

The following describes the mapping of OM Plus request and destination status changes to SAP Event reporting level. Each successive reporting level allows additional triggering events for status callbacks to SAP, providing increased visibility for SAP users. The level of detail available for this processing depends on the configuration of the OM Plus destination. Maximum detail is provided by destinations configured in termserv mode, with SNMP and Bidirectional PJL protocols enabled.

### FINAL MESSAGES

---

SAP is only notified when a request completes successfully or is canceled. This setting (along with a Send Period of a minute or two) is appropriate when request and destination status is to be monitored solely in OM Plus and SAP needs no progress reporting, beyond a completion notification.

### ALSO PROBLEMS (INTERACTION REQUIRED)

---

Adds conditions, such as Offline, where request processing generally cannot continue without some form or intervention in OM Plus or at the printer.

### ALSO WARNINGS

---

As of OM Plus 2.4.0, this has no additional effect because SAP does not act sufficiently differentiate between Problem and Warning conditions and, in many cases, OM Plus cannot tell if a problem does or does not require intervention.

### ALSO STATUS CHANGES

---

Adds request status transitions such as “ready” to “activ” and “retry” conditions.

### ALSO INFORMATION

---

Adds changes in destination status.

### ALL AVAILABLE INFORMATION

---

Adds confirmed (PJL) page count change.

## SAP LOGICAL OMS & COMMANDS CONFIGURATION (CONTINUED)

**Spool Administration: Operating System Commands (Display)**

Real OMS: **OMPLUS** OM Plus Output Management System  
 Command group: **0**  
 Operating system: **Linux**

Command path  
 Path: **/usr/lppplus/bin/**

OMS commands

|             |                                                           |
|-------------|-----------------------------------------------------------|
| Submit      | dccsapsub "&EI" &EG &P &F &o "&T" &C &Y &U "&E2" "&Es" "& |
| Polling     | dccsapstat &P &EL                                         |
| Queue query | dccsapstat -d &P                                          |
| Job cancel  | dccsapstat -c &EL                                         |
| Job query   | dccsapstat -j &EL                                         |

1. Save the LOMS definition. The above steps may be repeated to define multiple LOMS if desired.
2. From either a LOMS definition or the List of LOMS screen, Select the Commands  button. Select the entry corresponding to your system's operating system. (All Windows systems are considered to be 'Windows NT'.)
3. Enter (or verify/correct) the OS Commands fields:

Set a Command group letter to share this set of command definitions across multiple LOMS definitions. All LOMS should reference this letter. (Otherwise, enter the command definitions for each LOMS separately.)

- a) Operating system should be that of current OS.
- b) Enter the fully qualified path to the OM Plus bin directory in the command path. The defaults paths for Unix-based and Windows systems are:

Unix: /usr/lppplus/bin/

Windows: C:\plustech\omplus\server\bin\

**\*\*In Both cases, make sure to include the trailing slash or backslash\*\***

- c) Enter the dccsapsub command as shown below into the Submit line:

dccsapsub "&EI" &EG &P &F &o "&T" &C &Y &U "&E2" "&Es" "&E1"



(It is harmless to use quotes around all parameters. The ones shown are required.) The “&E1” parameter is new as of OM Plus release 2.3.2. It is required for callback, allowing dccsapsub to distinguish between polling and callback mode requests. If absent, polling will be assumed.

d) Enter the dccsapstat commands shown below into the remaining lines:

|              |                                        |
|--------------|----------------------------------------|
| Polling:     | <code>dccsapstat &amp;P &amp;EL</code> |
| Queue query: | <code>dccsapstat -d &amp;P</code>      |
| Job cancel:  | <code>dccsapstat -c &amp;EL</code>     |
| Job query:   | <code>dccsapstat -j &amp;EL</code>     |

***\*\* Do NOT use quotes around the \$EL parameter\*\****

e) Save the Commands.

## SAP DEVICE CONFIGURATION FOR OM PLUS

1. From the main Spool Administration Initial Screen, select the Devices/servers tab and click the Output Device Display button.
2. Select an existing device to edit or click the Create button to define a new one.
3. Device configuration is the same as for other non-OM Plus devices except on the Access Method tab:
  - a. Set the 'Host Spool Access Method' to 'E: External Management System'.
  - b. Enter the OM Plus destination queue name into the 'Host printer' field.
  - c. Change the Logical OMS to the desired OM Plus LOMS defined previously.
  - d. If configuring a polling LOMS, do NOT select the 'Do Not Query Host Spooler for Output Status' checkbox.
  - e. Once all configuration for the device is complete, click save.
4. Return to the List of Output Devices and repeat steps 2 and 3 for all SAP output devices which should be handled by OM Plus.

The SAP devices are now configured to submit requests to OM Plus for printing and to receive request status from OM Plus. A job submitted via the OM Plus BCXOM interface will not purge from OM Plus until it has a final status (prntd, cmplt, xferd, etc.) and SAP has been informed that the request has completed.


## SETTING UP THE OM PLUS RID SPAN

The RID span is a method by which each server uses a unique range of RID numbers when request are spooled to it. OM Plus uses the RID span to know what OM Plus server a request was spooled on. This is important for SAP because an environment may have more than one SAP server. Any SAP server can query for the status of any request spooled by any of the SAP servers in the enterprise. The dccsapstat program uses the RID span to determine which host to connect to in order to get the accurate status.

One OM Plus server needs to designated the span host. It is the span host's responsibility to publish the RID span file out to all of the servers.

**Note:** *Even if this is the only server in your enterprise, the SAP interface still requires that the RID spans be properly set up.*

To edit the RID Spans using the Client interface, open the OM Plus Administration > System > RID Spans.




Add a line containing host, starting RID, and ending RID for each OM Plus server in the enterprise. Starting RIDs must be larger than ending RIDs. Ranges cannot overlap. The minimum range is 500, but it is highly recommended that the range be greater than the maximum number of requests allowed on that system (see System Defaults).


The system that is the Span Host is only system that needs to be set up using this utility. Periodically the Span Host will publish the current file to all of the systems listed. If a server that is not the Span Host is updated, the changes will be lost as soon as the real Span Host publishes its list.

## WINDOWS

Open the OM Plus DM Server application on the OM Plus server that is going to host the RID span file and select the 'Environment' tab.



Select the 'Settings' button and locate the 'SPAN Host RID Ranges' tab.



Select the 'Current Host' check box.

For each OM Plus server in the enterprise a line in the RID Span Control needs to be entered. Type each host name and a range of RID numbers into the Fields near the bottom of the window and select the add button. Don't forget to include the Span Host server. The program will not allow overlapping ranges. Once done, select the 'Close' button and this server will propagate the correct RID spans file out to each server in the list.

## UNIX

On a Unix server, the Span file needs to be created manually on the span host. Make the following files:

```
$LPHOME/constants/spanhost
```

This file should contain the hostname of the span host:

```
$LPHOME/constants/ridspans
```

This file should contain an entry for each server in the enterprise. The format of the file is as follows:

```
hostname, starting_rid, ending_rid
```

starting\_rid is the first RID number in that's host's range.

ending\_rid is the last RID in that host's range.

Example:

```
ibm1, 10000, 50000
```

```
solaris33, 50001, 99999
```

Take great care to make sure that none of the RID ranges overlap.

## CONFIGURING OM PLUS FOR SAP CALLBACKS

In order to make callbacks, OM Plus must have an initial contact SAP target address as well as login ID(s) and password(s) for any SAP callback target instances OM Plus may establish contact with. Additionally, if multiple OM Plus systems are communicating with the same SAP system, they must be made aware of each other so as to be able to pass updates amongst themselves.

This configuration information is provided by the file sapconfig.NODE file in the \$LPHOME/constants directory. ("NODE" is the name of the host as returned by `uname -n`.) A sample version of this file, with comments, is provided as sapconfig.example file may be saved as sapconfig.NODE. Because this file contains login information, make sure to set the permissions to 0600 and the owner to 'ompsys2'.

The sapconfig file is a text file with lines of comma separated values. Lines that are blank or begin with a '#' character are ignored. The first field is a single letter record type which determines which parameter field(s) follow. The L and A records provide login and audit information for SAP target instances not defined in this file by T records. Thus new targets may be defined in SAP LOMS definitions without having to modify this file. One or more T records may be added to explicitly define targets and their information. This is useful when targets differ from the default. The R record(s) define the ROMS this OM Plus node is serving as. If an OM Plus system is serving multiple independent SAP systems, they must each access OM Plus using a different ROMS name and there would be multiple entries here. The N records are needed if there is more than one OM Plus system serving an SAP system. Although the name of the local system is not required, including it means that one can replicate this configuration file to all the named systems.

| Type                                                                                          | Parms          | Meaning                                                            |
|-----------------------------------------------------------------------------------------------|----------------|--------------------------------------------------------------------|
| <b>L</b><br><br>Default login parameters for SAP targets not explicitly defined by T records. | ID             | SAP login ID                                                       |
|                                                                                               | Password       | password for SAP login                                             |
|                                                                                               | Client         | client number for SAP login                                        |
| <b>A</b><br><br>Default SAP Log Audit level for targets not explicitly defined by T records.  | Level          | 0 (min) – 3 (max), default 0                                       |
| <b>T</b><br><br>Explicit SAP session target definition(s).                                    | Target host    | SAP target instance in the form host_sys_nnn.                      |
|                                                                                               | ID             | SAP login ID                                                       |
|                                                                                               | Password       | password for SAP login                                             |
|                                                                                               | Client         | client number for SAP login                                        |
|                                                                                               | Audit Level    | 0 (min) – 3 (max), 0 default                                       |
| <b>R</b><br><br>The Real Output Management System(s) OM Plus is providing to SAP.             | ROMS ID        | The name of the ROMS.                                              |
|                                                                                               | Initial Target | The SAP instance OM Plus should contact on startup.                |
|                                                                                               | Retry Seconds  | The retry interval after a connection failure.                     |
| <b>N</b><br><br>The hostname(s) of OM Plus systems (nodes).                                   | Host           | Hostname of another OM Plus system serving the same SAP system(s). |

## SAMPLE

```
#-----
# Sample SAP callback configuration file for OM Plus
#
# An edited copy of this file should be installed as
# $LPHOME/constants/sapconfig.NODENAME, where NODENAME
# is the node name of the OM Plus host (uname -n). It should be owned by
# omphysys2, permissions 600.
#
# The presence of constants/sapconfig.NODENAME will activate the SAP callback
# feature of dcce2enot. Changing
# (or just 'touch'ing) this file will cause a soft restart of the SAP
# callback interface.
#
```

```
# Lines beginning with '#' and blank lines are ignored.
#-----

# default login/audit parameters for targets without T entries below
#
# Login:
# L,id,password,clientL,defaultid,defaultpass,001

# Audit level (0-3, 0 default)
# A,level
# A,3

# callback target entry(s):
# T,saphost,login,password,client,audit lvl.

# ROMS entry(s):
# R,rom_id,initialtarget,retry secs.

R.OMPLUS,host1_N4S_42,120

# OM Plus SAP Nodes
# If OM Plus is installed on more than one mode(host) with SAP requests
# for being forwarded, the OM Plus nodes must be aware of each other
# so that when SAP sends a configuration update to one node, that node
# can forward the information to the others. (These N entries are not
# needed if there is only a single OM Plus system.)
#
# N,hostname

N,host1
N,host2
N,prtserver
```

## COMMAND REFERENCE

## DCCSAPSUB

## DEFINITION

This Command Submits Requests to OM Plus SAP certified interface.

## FORMAT

dccsapsub

## PARAMETERS (ALL REQUIRED)

|     |                      |
|-----|----------------------|
| &EI | SAP Spool ID         |
| &EG | Reply message        |
| &P  | SAP Destination Name |
| &F  | File to be spooled   |
| &O  | SAP User ID          |
| &T  | Title                |
| &C  | Number of Copies     |
| &Y  | Priority             |
| &U  | Banner Flag          |
| &E2 | LOMS Flag            |
| &Es | SAP System ID        |
| &E1 | SAP R#LOMS flags     |

## EXAMPLE

dccsapsub "&EI" &EG &P &F &o "&T" &C &Y &U "&E2" "&Es" "E1"

**Note:** The presence or absence of the quotation marks in this command is very important. Failure to copy these commands exactly, with or without the appropriate quotation marks, could cause undesired behavior or, at the least, an inability to print.



## DCCSAPSTAT

### DEFINITION

This command requests status information from the OM Plus for its SAP certified interface and can also cancel one or more OM Plus request.

### FORMAT

`dccsapstat [ -d | -c | -j ]`

### PARAMETERS

`&P`      OM Plus Destination Name

`&EL`      Request ID(s) of Desired OM Plus Requests(s)

### EXAMPLES

`dccsapstat &P &EL` – Returns the status of a print job

`dccsapstat -d &P` – Returns the status of a print queue

`dccsapstat -c &EL` -- Cancels a print job

`dccsapstat -j &EL` -- Gives a detailed report of a print job's status

**Note:** *It is very important that the &EL parameter is not encapsulated in quotes*

## COMMAND REFERENCE

### ARCADMIN

#### NAME

arcadmin

#### SYNOPSIS

Starts the OM Plus Archive administration screen.

#### SYNTAX

arcadmin

#### AVAILABILITY

UNIX

#### DESCRIPTION

archadmin allows the user configure the OM Plus Archive module.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

archadmin: Opens the OM Plus Archive administration screen.

### BUILDHTML

#### NAME

buildhtml

#### SYNOPSIS

Builds the web files necessary for the OM Plus web interface.

#### SYNTAX

buildhtml

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

buildhtml creates the files needed for the installation of the OM Plus web interface.

#### ARGUMENTS

None

#### Options

None

#### EXAMPLES

buildhtml: Creates the files for the web interface.

### DCCACCEPT

#### NAME

dccaccept

#### SYNOPSIS

Sets a destination to accept output jobs.

#### SYNTAX

dccaccept -d [destination]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccaccept sets a destination to accept jobs that are spooled to it. If a destination is not set to accept jobs, those jobs will be lost.

#### ARGUMENTS

<-d destination>: Selects destination to make active.

#### OPTIONS

[-r reason]: allows user to specify a reason for activating this destination.

#### EXAMPLES

dccaccept -dlp0: Sets destination "lp0" to active.

#### SEE ALSO

dccreject

### DCCADMIN

#### NAME

dccadmin

#### SYNOPSIS

Starts the OM Plus Administration program.

#### SYNTAX

dccadmin

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccadmin starts the OM Plus administration program that allows the user to modify many of OM Plus's settings, manage destinations, start and stop most daemons, etc.

#### ARGUMENTS

None

#### Options

None

#### EXAMPLES

dccadmin: Starts the OM Plus administration program.

### DCCASWEEP

#### NAME

dccasweep

#### SYNOPSIS

Checks the archive for files to be removed.

#### SYNTAX

dccasweep [option]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccasweep searches the archive for files that may be removed based on the archive settings and then removes them.

#### ARGUMENTS

None

#### OPTIONS

[t]: Checks and removes only the files in the tmp directory.

#### EXAMPLES

dccasweep: Clears expired file from the archive.

### DCCBKADMIN

#### NAME

dccbkadmin

#### SYNOPSIS

Enables the user interfaces to attach to OM Plus for administrative purposes.

#### SYNTAX

dccbkadmin

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccbkadmin enables the user interface to attach to the main programs for OM Plus.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccbkadmin: Enables the user interfaces to attach to the main programs for OM Plus.

## DCCBKST

### NAME

dccbkst

### SYNOPSIS

Starts the OM Plus Network Status Server.

### SYNTAX

dccbkst

### AVAILABILITY

UNIX

### DESCRIPTION

dccbkst starts the OM Plus Network Status Server.

### ARGUMENTS

None

### OPTIONS

None

### EXAMPLES

dccbkst: Starts the OM Plus Network Status Server.

### NOTES

You can use the OM Plus Network Status Server to accept and send OM Plus output queue and destination statuses and commands between OM Plus systems over a TCP/IP network. This must be running on each system requiring centralized management. OM Plus does not require the Network Status Server to send delivery requests to other systems or applications supporting the LPD/LPR Protocol. The server listens to socket 53971 (the dccbkst 53971/tcp service in the etc/services file) by default for incoming OM Plus commands. It also uses this socket to send queue and destination commands to other OM Plus systems.

### SEE ALSO

dccbkshut

dccshut



### DCCBKSTSHUT

#### NAME

dccbkstshut

#### SYNOPSIS

dccbkstshut

#### AVAILABILITY

UNIX

#### DESCRIPTION

Stops the OM Plus Network Status Server.

#### ARGUMENTS

None

#### OPTIONS

[host\_name]: Defaults include the node name of the system for the host\_name. There must be an entry in the /etc/hosts file for host\_name and /etc/services file for dccbkst 53971/tcp.

#### EXAMPLES

dccbkstshut: Stops the OM Plus Network Status Server.

#### SEE ALSO

dccbkst

### DCCCANCEL

#### NAME

dcccancel

#### SYNOPSIS

Cancels an active output job.

#### SYNTAX

dcccancel [argument]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dcccancel cancels an active output job. Jobs that have not printed and have been canceled will not print and jobs currently de-spooling will stop.

#### ARGUMENTS

[-d destination\_name]: Cancels the currently active output job for destination\_name.

[-I RIDxxxxx]: Cancels the output job with Request ID (RID) RIDxxxxx.

#### OPTIONS

[-k]: Cancels the output job with immediate purge.

#### EXAMPLES

dcccancels -d destination6: Cancels the currently active (printing) output job on destination6.

dcccancel -I RID0023: Cancels output job RID0023.

### DCCDESTCHG

#### NAME

dccdestchg

#### SYNOPSIS

Moves all output jobs with a status of “ready” from one destination to another.

#### SYNTAX

dccdestchg [current\_destination] [new\_destination]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccdestchg moves all output jobs from one destination to another.

#### ARGUMENTS

current\_destination: Current destination.

new\_destination: New output destination.

#### OPTIONS

None

#### EXAMPLES

dccdestchg destination3 destination 9: Moves all output jobs currently queued in destination3 to destination9.

### DCCDISABLE

#### NAME

dccdisable

#### SYNOPSIS

Disables a destination from printing.

#### SYNTAX

dccdisable -d [destination]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccdisable disables a destination. Any job that spools into this destination will not de-spool. If this destination is defined in a class for load balancing, it will be skipped.

#### ARGUMENTS

<-d destination>: Destination to disable.

#### OPTIONS

None

#### EXAMPLES

dccdisable -d destination6: Disables destination6

#### SEE ALSO

dccenable

### DCCE2ENOT

#### NAME

dcce2enot

#### SYNOPSIS

Starts the “End to End” notification service that sends information regarding requests to a remote server.

#### SYNTAX

dcce2enot

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcce2enot starts the notification daemon that is used to communicate with other OM Plus servers about requests.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dcce2enot

#### NOTES

dcce2enot and dcce2eser are typically started and stopped by the scheduler.

#### SEE ALSO

dcce2eser

### DCCE2ESER

#### NAME

dcce2eser

#### SYNOPSIS

Starts the “End to End” service that receives information regarding requests from a remote server.

#### SYNTAX

dcce2eser

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcce2eser starts the daemon that handles communication between OM Plus servers about requests.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dcce2eser

#### NOTES

dcce2enot and dcce2eser are typically started and stopped by the scheduler.

### DCCENABLE

#### NAME

dccenable

#### SYNOPSIS

Enables a destination for printing.

#### SYNTAX

dccenable -d [destination]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccenable enables printing a destination. Jobs will now de-spool (print) from this destination.

#### ARGUMENTS

<-d destination>: Destination to enable.

#### OPTIONS

None

#### EXAMPLES

dccenable -d destination6: Enables destinations6.

#### SEE ALSO

dccdisable

### DCCFREE

#### NAME

dccfree

#### SYNOPSIS

Controls the licensing process in OM Plus.

#### SYNTAX

dccfree

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccfree allows the user to license their system or display the product status.

#### ARGUMENTS

None

#### Options

None

#### EXAMPLES

dccfree enable\_file: Apply enable codes from file.

dccfree -le: List enable file codes.

dccfree -l: List product enable state.



### DCCGDISABLE

#### NAME

dccgdisable

#### SYNOPSIS

Disables all destinations.

#### SYNTAX

dccgdisable

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccgdisable disables all destinations.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccgdisable: Disables all destination queues.

#### SEE ALSO

dccgenable, dccdisable, dccenable

### DCCGENABLE

#### NAME

dccgenable

#### SYNOPSIS

Enables all destinations.

#### SYNTAX

dccenable

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccgenable enables all destinations.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccgenable: Enables all destination queues.

#### SEE ALSO

dccgdisable, dccdisable, dccenable

## DCCGRP

### NAME

dccgrp

### SYNOPSIS

Performs a specified function on a group of output jobs.

### SYNTAX

dccgrp [command] [groups]

### AVAILABILITY

UNIX/Windows

### DESCRIPTION

dccgrp performs a specified function on a group of output jobs.

### ARGUMENTS

Cancel: Cancels all output jobs in the group.

Form[new\_form]: Changes the form for all output jobs in the group to new\_form.

Dest[dest2]: Changes the destination for all output jobs in the group to dest2.

Release: Releases all output jobs in the group from hold.

Purge: Sets the purge flag for all output jobs in the group.

Restart [n=+x]: Restarts all output jobs in the group at last page + x.

Pr=x: Sets job to priority x.

### OPTIONS

[pr=x]: All output jobs with the priority x.

[unit=destination]: All output jobs for the destination.

[owner=user\_id]: All output jobs for the user [user\_id].

[status=job\_status]: All output jobs with the OM Plus status [job\_status].

[date=job\_date]: All output jobs with queue date job\_date in the form of YY/MM/DD.

[mine]: All output jobs in the OM Plus queues.

[all]: All output jobs in the OM Plus queues.

[n=new\_form]: Selects the new form when the form command is used.

[n=new\_destination]: Selects the new destination when the dest command is used.

[list]: Provides a list of RID numbers that match the given criteria.

[time=num]: Matches any job that is that many days old or older (counted in 24 hour increments). To specify time in minutes or seconds , add an “m” or “s” immediately after the number.

[ldate=mm/dd/yyyy]: Returns any jobs spooled on or before the given date.

### EXAMPLES

dccgrp dest status=fpend n=destination3: Moves all output jobs with a status of fpend (form pending) to destination3.

dccgrp cancel unit=destination6: Cancels all output jobs for destination6.

dccgrp hold all: Places all output jobs on hold.

dccgrp restart st=intrd n=+0: Restarts all interrupted output jobs where they stopped.

dccgrp cancel time=86400: Cancel all jobs older than 24 hours.

### NOTES

Syntax for changing destination is dccgrp dest [groups] n=[new\_dest]

Syntax for changing form is dccgrp form [groups] n=[new\_form]

Syntax for restart is dccgrp restart [group] n=+x where x is the number of pages after the interruption to start.

Priority does not work as a criteria.

### DCCGSUSPEND

#### NAME

dccgsuspend

#### SYNOPSIS

Suspends (stops printing) all actively printing jobs on all destinations.

#### SYNTAX

dccgsuspend

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccgsuspend suspends (stops printing) all actively printing jobs on all destinations. Jobs will need to be released manually.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccgsuspend: Suspends (stops printing) all actively printing jobs on all destinations.

### DCCHEALTH

#### NAME

dcchealth

#### SYNOPSIS

Checks OM Plus install and outputs discrepancies.

#### SYNTAX

dcchealth

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcchealth checks to see if OM Plus is installed correctly and outputs any found discrepancies. This program can quickly determine and display many basic problems with the OM Plus system, such as permission settings and corrupted queue entries.

#### ARGUMENTS

[-c] Display a formatted screen to view progress and results.

[-f] Fix problems, where possible.

#### OPTIONS

None

#### EXAMPLES

dcchealth -cf: Displays a formatted screen along with fixing problems, if possible.

### DCCINFO

#### NAME

dccinfo

#### SYNOPSIS

Lists important information about OM Plus and the system on which it is installed.

#### SYNTAX

dccinfo

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccinfo lists important information regarding OM Plus and the system on which it is installed.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccinfo: Outputs information regarding the system.

#### NOTES

Version = Displays version number.

LPHOME = Shows the OM Plus home directory.

PatchLevel = Shows the current patch applied to OM Plus, if applicable.

Current Spool Files = Number of files currently spooling.

Maximum Spool Files = Maximum number of spooling files.

Printers Configured = Number of printers configured in the system.

License = Number of printers allowed in the system.

Message Log Size = Size of message log (in bytes).

Accounting Subsystem is (ENABLED or DISABLED) = Status of Accounting subsystem.

Accounting Log Size = Accounting log size (in bytes).

File System Free Bytes = Free space in file system (in bytes).

File System % Freespace = Percentage of free space in the file system.

Archive System is (ACTIVE or INACTIVE) = Status of archive system.

Archive Free Blocks = Number of free blocks in archive system.

Archive % Freespace = Percentage of free space in archive system.

Tracking Number = newnum



### DCCLOGMSG

#### NAME

dcclogmsg

#### SYNOPSIS

Generates an entry in the log.

#### SYNTAX

dcclogmsg [text]

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcclogmsg creates a new entry in the log.

### DCCLOGREP

#### NAME

dcclogrep

#### SYNOPSIS

Generates a formatted error log report.

#### SYNTAX

dcclogrep [options]

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcclogrep generates a formatted error log report.

#### ARGUMENTS

pw=w Page width. W=100-255. Default is 78.

pl=l Page length. l=10-90. Default is 50.

df=filename Fully qualified destination file name. Default is log.rep.

sf=filename Fully qualified source file name. Default is log.

raw Print raw mode – no headers.

-c Use above arguments if any, but stay in interactive curses screen.

#### OPTIONS

[n]: Specifies the number of columns to use for this field.

Leave out spaces between parameter and = .

day=n

date=n

time=n

year=n

lpxnum=n

ridnum=n

message=n

program=n

### EXAMPLES

`dccloggrep -c date=6 time=8 lpxnum=7 rid=8 message:` Starts an interactive program that will allow setup of the report format with columns for date, time, lpxnumber, rid and message.

### NOTES

Columns appear in the order they are listed in the command line.

### DCCLP

#### NAME

dcclp

#### SYNOPSIS

Main spooling command for OM Plus.

#### SYNTAX

dcclp [argument] file\_name

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dcclp submits output jobs to destinations and changes output jobs after they are in the output queue.

#### ARGUMENTS

[-d destination]: Desired destination, if not specified the default destination is used.

[-f form\_id]: Changes the form ID.

[-F eform]: Designates an electronic form to be used with the request.

[-h]: Places a job on hold.

[-H hold/resume]: Holds a job or releases it from hold.

[-i request\_id]: Selects a currently queued job by RID.

[-n copies]: Sets number of copies.

[-o option(s)]: Used for passing a variety of data to the program. Often used in custom solutions.

[-p print\_control]: Changes the print control.

[-q priority]: Changes priority.

[-s]: Silent option. The command will put out no messages.

[-S character\_set]: Specifies an optional character set to use. Not available on HP or AIX systems.

[-t title]: Changes title of the job.

[-T {graphics/simple/post/postNR/ postDSC/pcl-1/pcl-2/pclxl/zpl}]: Specifies the file type for the output job. The default is for OM Plus to attempt to determine what type of file is being spooled. This can be overwritten by specifying the file type. See the File Types reference for more information.

[-W MM/DD/YY,HH:mm]: Future time for printing a job.

### COMMON OPTIONS

Archive, arch, archk, archivek, archu, archiveu, archuk, archiveuk: Archives the request when it purges. U means uncompressed, k means keep regardless of retention time.

Banner, ban: Prints banner before output.

continue: Restarts report at current page.

copybreak, cb: Form feeds between copies in a report.

dist=[file]: Select the .dst file to use for Report Distributor.

noarchive, noarch: Does not archive (default).

nobanner, nob, nb: Does not print banner.

nocb, noc, nocopybreak: No form feeds between copies in a report.

nofilebreak, nofb, nof, minusff: Turns off form feeds after each file.

nolfconv, nolfc: Does not do line feed to line feed carriage return conversion.

nopurge, nop: Job will not purge after completion.

purge: Deletes request after printed and purge time expires.

raw, -raw, r, -r: When printing in lpd/lpr mode this tells receiving end not to manipulate data.

restart=nnnnnnn[p]: Restarts at page nnnnnnn. If the [p] option is added to the end of the page number, OM Plus will attempt a printer level restart.

tran=afile: Tells OM Plus that the translate table file should be used.

ufilt=aprogram: Tells OM Plus that a program should be used as a userfilter program.

### EXAMPLES

dcclp -d destination9 /usr/files/file4: Sends job to destination9.

dcclp -d destination2 -f checks /usr/files/file2: Allows desired standard form. May be a custom form created through OM Plus administration or any form name. If not specified, the default form is used.

`dcclp -d destination5 -h /usr/files/file9`: Places the job currently printing on destination5 on hold.

`dcclp -i RID0217 -f checks -d dstination3 -n 3`: Changes job 0217 output destination to destination3, changes the required form to checks and changes the number of copies to 3.

`dcclp -d destination2 -o banner /usr/files/file2`: Turns banner on for the print file.

`dcclp -d destination4 -o banner /usr/files/file3`: Turns off purge for this print job.

`dcclp -d destination2 --p landscape /usr/files/file1`: Sends the preload and optional postload file `$LPHONE/prtcntl/landscape/preload` to the destination before the print request.

`dcclp -d destination7 -q 1 /usr/files/file2`: Changes priority to 1.

`dcclp -d destination1 -s /usr/files/file10`: Turns off the verbose information provided when the output job is submitted.

`dcclp -d destination8 -t report6 /usr/files/file6`: Changes the title of output job. The default is the file name or STDIN if piped into `dcclp`.

`dcclp -d destination7 -T postDSC /usr/files/file2`: Tells OM Plus that the file is a PostScript file that conforms to the Document Structuring Conventions (DSC).

`dcclp -d destination9 -W 11/30/12,03:10 /usr/files/file4`: Sets the job to print at 3:10 AM on the 30<sup>th</sup> of November 2012.

***Note:** `dcclp` has more options than are discussed in this section. For more information on other `dcclp` options, please see the “`dcclp` options” appendix to this manual.*

## DCCLPDSER

### NAME

dcclpdser

### SYNOPSIS

Starts the OM Plus Line Print Daemon (LPD) Server.

### SYNTAX

dcclpdser hostname service\_name

### AVAILABILITY

UNIX

### DESCRIPTION

dcclpsder starts the OM Plus Print Daemon (LPD) Server. Must be an entry in the /etc/hosts file for host\_name and /etc/services file for service\_name.

### ARGUMENTS

[host\_name]: Default is node name.

[service\_name]: Default is printer.

### OPTIONS

None

### EXAMPLES

dcclpdser: Starts the OM Plus LPD Server with default settings.

dcclpdser bighost destination: Starts the OM Plus LPD Server using the host\_name, bighost and service destination, from the /etc/services file.

### NOTES

OM Plus uses the LPD Server to accept output jobs from other applications that support the LPD/LPR Protocol over the TCP/IP network. OM Plus does not require the LPD Server to send output requests to other applications supporting the LPD/LPR Protocol. The LPD Server listens to socket 515 by default (destination service in the /etc/services file) for incoming output jobs. Because only one application can listen to a socket at a time, if the Unix lp line print daemon is already listening to socket 515 (destination tcp/515 in the /etc/services file) the OM Plus dcclpdser will fail. Consult your Network Administration documentation for information on stopping the Unix line print daemon.

### DCCLPDSHUT

#### NAME

dcclpdshut

#### SYNOPSIS

Stops the OM Plus Line Printer Daemon (LPD).

#### SYNTAX

dcclpdshut hostname service\_name.

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcclpdshut stops the OM Plus Line Print Daemon (LPD) Server.

#### ARGUMENTS

[host\_name]: Default is node name.

[service\_name]: Default is destination.

#### OPTIONS

None

#### EXAMPLES

dcclpdshut: Stops the OM Plus LPD Server with default settings.

dcclpdshut bighost destination: Stops the OM Plus LPD on host bighost and service called destination.



### DCCLPLINK

#### NAME

dcclplink

#### SYNOPSIS

Replaces the native UNIX lp command with dcclp command.

#### SYNTAX

dcclplink

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcclplink archives the current UNIX lp command and replaces it with a symlink pointed to dcclp. It also provides the option to start the lpd daemon on automatically and to capture lpd requests.

#### SEE ALSO

dcclpunlink

**Note:** When upgrading the OS on a system it is imperative that you run `DCCLPUNLINK` prior to the upgrade. Failure to do so may overwrite key OM Plus files. After the upgrade has completed you may run `dcclplink` again to restore the links.

### DCCLPR

#### NAME

dcclpr

#### SYNOPSIS

Provides LPR functionality and compatibility to dcclp.

#### SYNTAX

dcclpr -PQueue\_Name [-S Server\_Name] File\_Name

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcclpr accepts traditional lpr commands and transform them into dcclp commands.

#### ARGUMENTS

-PQueue\_Name: Desired queue

[-S Server\_Name]: Name of server containing that queue.

#### EXAMPLES

dcclp -PPrint1 -SOMServ file.txt to the queue "Print1" on "OMServ"

#### SEE ALSO

dcclpd

### DCCLPUNLINK

#### NAME

dcclpunlink

#### SYNOPSIS

Unlinks dcclp from the native UNIX lp command.

#### SYNTAX

dcclpunlink

#### AVAILABILITY

UNIX

#### DESCRIPTION

dcclpunlink removes any links created by dcclplink.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dcclpunlink: unlinks lp from dcclp.

#### SEE ALSO

dcclplink

### DCCMOUNT

#### NAME

dccmount

#### SYNOPSIS

Mounts a form on a destination.

#### SYNTAX

dccmount -d destination\_name -f form\_name

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccmount mounts a form on a destination.

#### ARGUMENTS

[-d destination]: Destination to mount form.

[-f form]: Form to be mounted.

#### OPTIONS

None

#### EXAMPLES

dccmount -d destination3 -f checks: Mounts the form checks on destination3.

### DCCMSGHELP

#### NAME

dccmsghelp

#### SYNOPSIS

Decrypts message and error numbers from OM Plus.

#### SYNTAX

dccmsghelp

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccmsghelp runs the message and errno description program.

#### ARGUMENTS

[message number]: Writes the text about this message number to stdout.

[-n#]: Writes a description of the errno# to stdout.

#### OPTIONS

None

#### EXAMPLES

dccmsghelp LPP376E: Looks up and displays the help text about message LPP363E.

dccmsghelp -n131: Looks up and displays the description of an errno 131 for your OM Plus Server's operating system.

### DCCNETSTAT

#### NAME

dccnetstat

#### SYNOPSIS

Check destination and queue status on LPD/LPR systems without OMP installed.

#### SYNTAX

dccnetstat -d destination\_name

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccnetstat uses the LPD/LPR protocol to receive status information if OM Plus is not installed on that system.

#### ARGUMENTS

[-d destination\_name]: Specifies destination to check.

[-h Host\_Name]: Checks for the presence of the given host and whether or not the scheduler is running on that host.

#### OPTIONS

None

#### EXAMPLES

dccnetstat -d destination3: Displays the remote systems queue information for the local destination destination3.

#### NOTES

OM Plus uses the Network Server Status program to receive status information from systems supporting the LPD/LPR Protocol. The destination\_name must be a valid OM Plus destination with the netprint or system mode. The information returned displays as it is received from the remote system.

### DCCPRTVAL

#### NAME

dccprtval

#### SYNOPSIS

Programmatic way to get information from a printer configuration file.

#### SYNTAX

dccprtval printer\_name tag

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccprtval looks up the value of given tag in destination's configuration file.

#### ARGUMENTS

printer\_name: Name of destination.

tag: Data tag requested.

#### OPTIONS

None

#### EXAMPLES

dccprtval Printer Device: Returns the device information for the destination "Printer".

### DCCQVAL

#### NAME

dccqval

#### SYNOPSIS

Returns information from a print queue file.

#### SYNTAX

dccqval RID##### tag

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccqval returns information from a given request's queue file when given the proper tag.

#### ARGUMENTS

RID#####: The RID of the request to query.

tag: The tag for the information requested.

#### OPTIONS

None

#### EXAMPLES

dccqval RID01717 ST: Returns the status of request 01717.



## DCCRANGE

### NAME

dccrange

### SYNOPSIS

Prints a range of pages from an existing OM Plus job.

### SYNTAX

dccrange RIDxxxx r=sssss-eeee

### AVAILABILITY

UNIX/Windows

### DESCRIPTION

Prints a range of pages from an existing OM Plus job. Spools another output job consisting of pages ssss to eeee.

### ARGUMENTS

RIDxxxx: Requests ID for the output job.

R=sssss-eeee: Range of pages to print from the output job. Spools another output job consisting of pages ssss through eeee.

### OPTIONS

[d=destination\_name]: Specifies destination.

[f=form\_name]: Specifies a form for the new file.

### EXAMPLES

dccrange RID00024 r=10-235: Prints pages 10-235 from RID0024 on the same destination.

dccrange RID0024 r=10-235 d=destination3: Sends the range of pages to a new destination.

dccrange RID0024 r=10-235 d=destination3 f=checks: Sends the range of pages to another destination and specifies the form "checks".

### DCCRDEDIT

#### NAME

dccredit

#### SYNOPSIS

Opens the Report Distributor editor.

#### SYNTAX

dccredit

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccredit opens the Report Distributor configuration screen.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccredit: Opens the Report Distributor screen.

### DCCREJECT

#### NAME

dccreject

#### SYNOPSIS

Sets a destination to reject output jobs.

#### SYNTAX

dccreject -d destination\_name

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccreject sets a destination to reject output jobs. While the destination is rejecting, no output jobs will spool.

#### ARGUMENTS

[-d destination\_name]: Selects the destination to set to reject.

#### OPTIONS

None

#### EXAMPLES

dccreject -d destination6: Sets destination6 to reject output jobs.

### DCCRESET

#### NAME

dccreset

#### SYNOPSIS

Resets portions of the destination's status.

#### SYNTAX

dccreset -d printername [-s -l -a -r]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccreset allows portions of a destination's status to be reset.

#### ARGUMENTS

-d printername: The name of the destination on which to act.

[-s]: Reset the SNMP flags.

[-l]: Reset the lock flags.

[-a]: Reset to inactive and stop any actively request.

[-r]: Cause the active request on this destination to become interrupted.

#### EXAMPLES

dccreset -d printer -sa: Resets the known SNMP status of "printer" while stopping the currently active request and setting its status to "interrupted".

### DCCSAPSTAT

#### NAME

dccsapstat

#### SYNOPSIS

Requests status information from OM Plus for its SAP certified interface.

#### SYNTAX

dccsapstat

#### AVAILABILITY

UNIX

#### DESCRIPTION

This command requests status information from OM Plus for its SAP certified interface.

#### ARGUMENTS

&P: SAP Destination Name.

&EL: Request ID of Desired Request.

#### OPTIONS

None

#### EXAMPLES

dccsapstat "&P" &EL

#### NOTES

It is very important that the &EL parameter is not encapsulated in quotes.

### DCCSAPSUB

#### NAME

dccsapsub

#### SYNOPSIS

Submits requests to OM Plus's SAP interface.

#### SYNTAX

dccsapsum <arguments>

#### AVAILABILITY

UNIX

#### DESCRIPTION

This command submits requests to OM Plus's SAP certified interface.

#### ARGUMENTS

&EI: SAP spool ID

&EG: Reply message

&P: SAP Destination name

&F: File to be spooled

&o: SAP user ID

&T: Title

&C: Number of copies

&Y: Priority

&U: Banner flag

&E2: LOMS Flag

&Es: SAP system ID

#### OPTIONS

None

#### EXAMPLES

dccsapsub "&EI" "&EG" "&P" "&F" "&o" "&T" "&C" "&Y" "&U" "&E2" "&Es"

## DCCSCAN (UNIX)

### NAME

dccscan

### SYNOPSIS

Looks at a specified directory for files to print.

### SYNTAX

dccscan directory\_path cycle\_time delay\_time dcclp\_options

### AVAILABILITY

UNIX

### DESCRIPTION

dccscan looks at a specified directory for files to print.

### ARGUMENTS

directory\_path: Full pathname to an existing directory to scan for files.

cycle\_time: cycle\_time refers to the number of seconds between scans to see if a file is in the directory.

delay\_time: Amount of time in seconds to delay after the file is no longer being written before spooling begins. This ensures that the application is finished writing the file before OM Plus spools the output job.

dcclp\_options: Text that will complete the rest of the dcclp command executed when a file is found.

### OPTIONS

None

### EXAMPLES

dccscan /tmp/dir 30 5 "-d destination -h -s onopurge": Scans /tmp/dir every 30 seconds. The delay\_time is 5 seconds, which means the amount of time in seconds to delay writing the file before OM Plus spools the output job. The dcclp options for the scanned files are getting routed to a destination with a hold option (-h) and silence option (-s) the -o option set to no purge.

### DCCSCAN (WINDOWS)

#### NAME

dccscan

#### SYNOPSIS

Starts the OM Scan Service

#### SYNTAX

dccscan

#### AVAILABILITY

Windows

#### DESCRIPTION

dccscan looks at a specified directory for files to print.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccscan



### DCCSCHED

#### NAME

dccsched

#### SYNOPSIS

Starts the OM Plus scheduler service.

#### SYNTAX

dccsched

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccsched starts the OM Plus output scheduler. If the scheduler is not running, no jobs will print through OM Plus.

Also starts the End to End status and notification services (dcce2e and dcce2enot) to allow communication between OM Plus servers.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccsched: Starts the scheduler.

### DCCSHUT

#### NAME

dccshut

#### SYNOPSIS

Stops the OM Plus scheduler.

#### SYNTAX

dccshut

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccstop stops the scheduler after all currently printing jobs are finished. No new jobs will de-spool.

#### ARGUMENTS

[all] : Shuts down all running OM Plus processes.

[-i] : Shut down immediately without waiting for jobs to complete.

[-d destination] : Stops a PJI streaming mode destination.

[service\_name]: Specify a specific service to shut down only that service.

[-t <service>] : Test. This function checks to see if the service is running, but does not issue a shut down command.

#### OPTIONS

None

#### EXAMPLES

dccshut: Shuts down the scheduler after the completion of any active print jobs.

dccshut all: Stops all services.

dccshut -i: Stops the scheduler even if there are active jobs.

dccshut bkst: Shuts down the OM Plus background status service.

### DCCSTAT

#### NAME

dccstat

#### SYNOPSIS

Starts the OM Plus Status and Control program.

#### SYNTAX

dccstat

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccstat starts the OM Plus Status and Control program in request mode and displays all output jobs and destinations.

#### ARGUMENTS

None

#### OPTIONS

[-d destination]: Starts the OM Plus Status and Control program and only displays output jobs for the specified destination.

[-u user\_id]: Starts the OM Plus Status and Control program and displays only the requests for the specified user ID.

#### EXAMPLES

dccstat: Starts the OM Plus Status and Control program in request mode and displays all request and destinations.

dccstat -d destination2: Starts the OM Plus Status and Control program in request mode and displays only the request and print destinations for destination2.

dccstat -u bob: Starts the OM Plus Status and Control program in request mode and displays only the requests for the user bob.

dccstat -u \$LOGNAME: Starts the OM Plus Status and Control program in request mode and displays only the requests for the user currently logged in.

### DCCSTATDEF

#### NAME

dccstatdef

#### SYNOPSIS

Allows the administrator to set up the Status screen.

#### SYNTAX

dccstatdef

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccstatdef opens an editor that allows the administrator to customize the Status screen.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccstatdef: Opens the Status screen editor.

### DCCSUSPALL

#### NAME

dccsuspall

#### SYNOPSIS

Suspends all print jobs in OM Plus.

#### SYNTAX

dccsuspall

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccsuspall suspends all print jobs in OM Plus.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

dccsuspall: Will display a y/n prompt asking if all print jobs should be suspended. If “y” is selected, then all print jobs will be suspended.

### DCCSUSPEND

#### NAME

dccsuspend

#### SYNOPSIS

Suspends currently printing output job.

#### SYNTAX

dccsuspend

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

dccsuspend will suspend (stop printing) a currently printing output job.

#### ARGUMENTS

[-d destination\_name]: Suspends the currently printing output job for destination\_name.

[-I RIDxxxxx]: Suspends the output job with Request ID RIDxxxxx.

#### OPTIONS

None

#### EXAMPLES

dccsuspend -d destination6: Suspends currently printing output job on destination6.

dccsuspend -I RID00029: Suspends output job RID00029.

## DCCSWITCH

### NAME

dccswitch

### SYNOPSIS

Routes output job from one destination to a new destination to a new destination.

### SYNTAX

dccswitch original\_destination new\_destination.

### AVAILABILITY

UNIX/Windows

### DESCRIPTOIN

dccswitch will route jobs intended for a specified destination to another destination.

### ARGUMENTS

original\_destination new\_destination: All requests waiting to print on original\_destination to be delivered on new\_destination.

### OPTIONS

None

### EXAMPLES

dccswitch destination2 destination8: Switch request from destination2 to destination8.

dccswitch destination2: Switch request from destination2 to destination found in ALT\_des in the destination2 configuration file.

dccswitch destination2 none: Allow request to print on destination2, no switch.

### NOTES

The status information will still show the requests with their original destinations. The actual switching occurs at de-spooling not at spooling. To switch back after the original destination is again able to print, switch the destination to none. This action can have unintended results if extreme caution is not taken. Please contact support before using this command as there may be other, safer methods to achieve the same effect.

### DCCVIEW

#### NAME

dccview

#### SYNOPSIS

Executes the OM Plus viewer.

#### SYNTAX

dccview RIDxxxxx

#### AVAILABILITY

UNIX

#### DESCRIPTION

dccview executes the OM Plus file viewer. This is usually accomplished through the Status and Control program dccstat.

#### ARGUMENTS

[RIDxxxxx]: Refers to the Request ID number for the output job to view.

#### OPTIONS

None

#### EXAMPLES

dccview RID00233: Views report with the Request ID of RID00233.



### DISABLE

#### NAME

disable

#### SYNOPSIS

Disables a destination from printing.

#### SYNTAX

disable -d [destination]

#### AVAILABILITY

UNIX

#### DESCRIPTION

“disable” disables a destination. Any job that spools into this destination will not de-spool. If this destination is defined in a class for load balancing, it will be skipped.

#### ARGUMENTS

<-d destination>: Destination to disable.

#### OPTIONS

None

#### EXAMPLES

disable -d destination6: Disables destination6

#### SEE ALSO

enable, dccdisable, dccenable

### ENABLE

#### NAME

enable

#### SYNOPSIS

Enables a destination for printing.

#### SYNTAX

enable -d [destination]

#### AVAILABILITY

UNIX

#### DESCRIPTION

“enable” enables printing on a destination. Jobs will now de-spool (print) from this destination.

#### ARGUMENTS

<-d destination>: Destination to enable.

#### OPTIONS

None

#### EXAMPLES

enable-d destination6: Enables destination6.

#### SEE ALSO

disable, dccenable, dccdisable

### HEXDUMP

#### NAME

hexdump

#### SYNOPSIS

Takes data entering the program and outputs it as hex.

#### AVAILABILITY

UNIX

#### SYNTAX

hexdump file\_out

#### DESCRIPTION

hexdump takes data entering the program either as a specified file or through standard in outputs it as hex.

#### ARGUMENTS

file\_out: The file to write the contents of the hex dump to.

#### OPTIONS

None

#### EXAMPLES

hexdump output: The file "output" from the current directory will be opened and reported as hex.

### INSTALLCDPLUS

#### NAME

installcdplus

#### SYNOPSIS

Installs the Content Delivery component.

#### SYNTAX

installcdplus

#### AVAILABILITY

UNIX

#### DESCRIPTION

installcdplus create and moves into place the files required for the Content Delivery module.

#### ARUGMENTS

None

#### OPTIONS

None

#### EXAMPLES

installcdplus: Installs Content Delivery Plus.

## LPADMIN

### NAME

lpadmin

### SYNOPSIS

Add, modify, and delete the OM Plus destination configuration.

### SYNTAX

lpadmin -p destination\_name

### AVAILABILITY

UNIX/Windows

### DESCRIPTION

lpadmin allows the user to add, modify, and delete the OM Plus destination configuration.

### ARGUMENTS

[-c class]: Changes class for destination.

[-h device]: Changes device name.

[-i interface]: Changes interface for destination.

[-m interface]: Same as -i.

[-p printer\_name]: Sets printer name.

[-r class]: Same as -c.

[-T terminfo]: Changes the terminfo file.

[-v device]: Same as -h

[-x]: Deletes a destination.

[-z device]: Do not verify device when adding.

[-o]: Refer to options.

### OPTIONS

[-o altdest=<dest>]: Sets the alternate destination.

[-o banner]: Include banner.

`[-o close=x]`: Sets close delay timeout.

`[-o cmd1=command]`: Secure Queue Release (SQR) label to show on the printer panel if the SQR version of My Print Delivery (MPD) is being used. If SQR of MPD is not being used, then field should be set to none although any value is acceptable.

`[-o cmnt=description]`: Sets the comment field in the printer configuration.

`[-o copybreak]`: Puts a form feed between copies.

`[-o filebreak]`: Puts a form feed after files.

`[-o filesometimes]`: Inserts a form feed at the end of a file if one is not already there.

`[-o filter2=filtername]`: Filter the print job goes through.

`[-o filter3=filtername]`: Another filter the print job may go through.

`[-o form=form_name]`: Select a different form.

`[-o purgetime=seconds]`: Sets purge time.

`[-o lfc]`: LF to CR/LF on.

`[-o metering=characters_per_second]`: Set throttling to a specific rate.

`[-o mode=mode]`: Mode for print queue.

`[-o nobanner]`: No banner selected.

`[-o nocopybreak]`: Turns off form feeds between copies.

`[-o nofilebreak]`: Turns off form feeds between files.

`[-o nolfc]`: LF to CR/LF off.

`[-o noteinfo]`: Text for the note field.

`[-o opentime=x]`: Sets connection open timeout.

`[-o pagelimit=x]`: Sets page limit.

`[-o Pcap=Pcap_name]`: Select a different Pcap file.

`[-o protadd]`: This should be set to the snmp community string value if snmp is turned on.

`[-o purgetime=x]`: Sets purgetime.

`[-o restore]`: Restore previous configuration.

`[-o sleep=seconds]`: Sets sleep time.

`[-o support=<text>]`: Places text in the “support” information field.

`[-o swdest]`: Switches a destination to another destination.

`[-o trantable=translation_name]`: Select a different translation table.

`[-o types]`: Data types allowed for this printer.

`[-o url=<url>]`: Inputs the url of the printer’s internal web server.

`[-o url_address]`: Inputs the url of the printer’s internal web server.

`[-o usrfilter]`: Designates a user defined program through which to pass data. This must be a fully defined path to a local file.

`[-o writetime=x]`: Sets write timeout.

### EXAMPLES

`lpadmin -plaser -vhost!9100 -o mode=termserv -oolfc`: This adds a network destination named “laser” and translate line feeds to carriage return line feeds.

### LPLINKONLY

#### NAME

lplinkonly

#### SYNOPSIS

Creates a symlink redirecting the system's native lp command to dcclp.

#### SYNTAX

lplinkonly

#### AVAILABILITY

UNIX

#### DESCRIPTION

lplinkonly creates a symlink redirecting native lp to dcclp. This differs from dcclplink in the number of options available when running.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

lplinkonly: Creates a symlink redirecting native lp to dcclp.

**Note:** When upgrading the OS on a system it is imperative that you run `DCCLPUNLINK` prior to the upgrade. Failure to do so may overwrite key OM Plus files. After the upgrade has completed you may run `lplinkonly` again to restore the links.



### LPPUSERS

#### NAME

lppusers

#### SYNOPSIS

Places a list of users into groups.

#### SYNTAX

lppusers [-c] file\_name

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

lppusers takes a comma separated file and saves the values as users and associated groups.

#### ARGUMENTS

File\_name: The name of the file to be used to create or append the new user list.

#### OPTIONS

[-c]: If used, the current user list will be deleted and a new list created.

#### EXAMPLES

lppusers -c file\_name: Deletes the current user list, then imports the contents of "file\_name" as the new list.

#### SEE ALSO

omplogusers, ompremusers

### LPSTAT

#### NAME

lpstat

#### SYNOPSIS

Reports the status of jobs and queues in OM Plus.

#### SYNTAX

lpstat [arguments]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

lpstat can report the status of jobs and destinations in OM Plus.

#### ARGUMENTS

[-a]: Shows whether destinations are currently accepting or rejecting requests (UNIX only).

[-a destination]: Displays if a destination is accepting or rejecting requests (UNIX only).

[-d]: Displays the default destination for the server.

#### EXAMPLES

lpstat: Returns a list of requests in the standard lpstat format.

lpstat -a destination: Reports whether or not a destination is accepting or rejecting requests.

### OMLOGUSERS

#### NAME

omlogusers

#### SYNOPSIS

Updates the login users list.

#### SYNTAX

omlogusers [-c] file\_name

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

omlogusers takes a comma separated file and uses that to update the list of login users.

#### ARGUMENTS

file\_name: The name of the file to be used to create or append the login users list.

#### OPTIONS

[-c]: If used, the current login users list will be deleted and a new list will be written using the file.

omlogusers file\_name: Appends the contents of file\_name to the login users lists.

#### SEE ALSO

lppusers, ompremusers

### OMPREMOVE

#### NAME

ompremove

#### SYNOPSIS

Removes the OM Plus system and its components.

#### SYNTAX

ompremove

#### AVAILABILITY

UNIX

#### DESCRIPTION

ompremove removes the OM Plus system and its components.

#### ARGUMENTS

None

#### OPTIONS

None

#### EXAMPLES

ompremove: Removes OM Plus and its components.

### OMQDEPTH

#### NAME

omqdepth

#### SYNOPSIS

Returns the number of jobs currently in the queue for a given destination.

#### SYNTAX

omqdepth [-hHost] -dDestination

#### AVAILABILITY

Windows

#### DESCRIPTION

omqdepth returns the number of requests currently queued for a destination.

#### ARGUMENTS

-dDestination: The name of the destination.

#### OPTIONS

[-hHost]: The name of a remote host containing the destination.

#### EXAMPLES

omqdepth -hPServer -dBundle: Will return the number of requests in the queue for the destination "Bundle" on the host "PServer".

## OMREMSETUP

### NAME

omremsetup

### SYNOPSIS

Configures the remote services.

### SYNTAX

omremsetup [-s host] [-r host] [-x] [-d] [-h pinghost] [-a y/n] [-t y/n] [-f] [-p]

### AVAILABILITY

UNIX/Windows

### DESCRIPTION

omremsetup allows for the configuration of the OM Plus remote services allowing destinations shared across OM Plus servers.

### OPTIONS

[-s host]: Adds an additional send host.

[-r host]: Adds an additional receive host.

[-x]: Designates a delete function for the correct file.

[-d]: Designates a deny host for the specified file.

[-h pinghost]: Designates the alias hostname to use in advertising dests.

[-a y/n]: Sets receive any.

[-t y/n]: Sets send any.

[-f]: Forces the server to send an update to all send hosts.

[-p]: Sets the server to broadcast destinations using proxy mode.

[-c]: Tells the server to send the printer type configuration file with the destination list.

### EXAMPLES

omremsetup -s host1 -f: Will add host1 to the sendHosts file and forces an update to be sent to all servers in the sendHost file.

omremsetup -r host2 -d: Will delete host2 from the recieveHosts file.

omremsetup -h sendServer: Sets the broadcast name for this server to sendServer.

### OMRESOLVE

#### NAME

omresolve

#### SYNOPSIS

Resolves the IP address for a given hostname.

#### SYNTAX

omresolve [hostname]

#### AVAILABILITY

UNIX/Windows

#### DESCRIPTION

omresolve returns the IP address and domain name of a system.

#### ARGUMENTS

[hostname]: Hostname to be resolved. If this is not given, omresolve will report information for the local system.

#### OPTIONS

NONE

#### EXAMPLES

omresolve server1: Returns the IP address and domain for server1.



## OM PLUS EVENT PROCESSING

OM Plus has the ability to watch for specific events to occur in the printing process and then take action based on that event. Specific events have been set up so that when they occur, variables are passed and a shell script executes (%OMHOME%\event\script\_name for Windows and \$LPHOME/event/script\_name for UNIX). These shell scripts are tied directly to an event.

The event scripts are completely customizable so that there is flexibility with what can be done when an event occurs. The following table describes each event and the shell scripts executed when they occur. The event scripts are located in the %OMHOME%\event folder for Windows and the \$LPHOME/event directory for UNIX.

For clarity, the descriptions of the events have been divided by operating system. These scripts are designed so the OM Plus administrator can modify them as needed.

*Note: On UNIX systems the file permissions of these scripts is very important. If the file is writeable by anyone but the owner the script will not be executed and an error will be recorded in the log.*

## USING WINDOWS EVENT SCRIPTS

For information on the event scripts in a Windows environment and their descriptions, refer to the following table. Event scripts for Windows are in batch (.bat) files.

| Script             | Executes                                                                                                                                                                             |
|--------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| accept.bat         | When a destination is set to accept.                                                                                                                                                 |
| arch_err.bat       | When a request failed to archive correctly.                                                                                                                                          |
| archiveLog.bat     | When a log file is archived to the ..\messages\log_archive directory.                                                                                                                |
| cancel.bat         | When a job is canceled.                                                                                                                                                              |
| connectfail.bat    | When a network destination has failed its connection.                                                                                                                                |
| demon.bat          | When any OMPlus demon is started or stopped.                                                                                                                                         |
| destchg.bat        | When a destination is added, modified, or deleted.                                                                                                                                   |
| disable.bat        | When a destination is disabled.                                                                                                                                                      |
| enable.bat         | When a destination is enabled.                                                                                                                                                       |
| formmount.bat      | When a new form has been mounted on a destination.                                                                                                                                   |
| formpending.bat    | When an output job requires a form that is not mounted on the destination. The output job reflects a status of form pending (fpending).                                              |
| lpdfail.bat        | When an error occurs during an LPD/LPR transfer using netprint, system, or LPPLUS mode destinations. This script contains the error retry/recovery/failure logic for LPD.            |
| openfail.bat       | When a non-network destination has failed its connection.                                                                                                                            |
| prepurge.bat       |                                                                                                                                                                                      |
| prtunavail.bat     | When a destination request is queued for a disabled printer.                                                                                                                         |
| purge.bat          | When an output has been purged from the OM Plus queue system. This happens after an output job is canceled or has printed, and after the destination's purge delay time has elapsed. |
| rcvhostremoved.bat | When the specified host is removed from the list of hosts from which destination are received.                                                                                       |
| reject.bat         | When a destination is set to reject.                                                                                                                                                 |
| remotedest.bat     | When remote destinations are either sent or received.                                                                                                                                |
| retry.bat          | When a request gains a retry status.                                                                                                                                                 |

|               |                                                                                                                                   |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------|
| spooler.bat   | When the job has been spooled into OM Plus.                                                                                       |
| streamerr.bat | When there is an error with a job using the 'Stream' confirmation type.                                                           |
| toobig.bat    | When a job with more than the maximum allowed pages is spooled.                                                                   |
| typemm.bat    | When the data type of the request differs from data types defined supported by the destinations.                                  |
| writefail.bat | When an output job fails during printing. The output job will be marked interrupted (intrd) and the destination will be disabled. |

## USING UNIX EVENT SCRIPTS

For information on the event scripts on all supported UNIX and Linux operating system and their description, refer to the following table.

| Script           | Executes                                                                                                                                                                         |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| arch_err.sh      | When a request failed to archive correctly.                                                                                                                                      |
| cancel.sh        | When a job is canceled.                                                                                                                                                          |
| connectfail.sh   | When a termserv or OMPLUS mode destination has failed to make a network connection.                                                                                              |
| demon.sh         | When any OM Plus daemon is started or stopped.                                                                                                                                   |
| disable.sh       | When a destination has been disabled.                                                                                                                                            |
| destchg.sh       | When a destination is added, changed or deleted.                                                                                                                                 |
| destsync.sh      | When a destination is added, change or deleted the destinations will be updated on another server.                                                                               |
| enable.sh        | When a destination has been enabled.                                                                                                                                             |
| formmount.sh     | When a form has been mounted on a destination.                                                                                                                                   |
| formpending.sh   | When an output job requires a form that is not mounted on the destination. The output job reflects a status of form pending (fpend).                                             |
| initialized.sh   | When the master server syncs destinations, classes, and models with a backup server.                                                                                             |
| interface.sh     | When a destination interface script completes. This occurs for all destinations when any job attempts to print (de-spool).                                                       |
| logsize.sh       | When the \$LPHOME/messages/log.<hostname> 'log file' increases to 10 megabytes. This script will rename the current log to log.old and the system will create a new working log. |
| lpdfail.sh       | When an error occurs during an LPD/LPR transfer using netprint, system, or LPPLUS mode destinations. This script contains the error retry/recovery/failure logic for LPD.        |
| sysnotify.sh     | When a destination upon an error sends an email/alert.                                                                                                                           |
| sysnotifytext.sh | When a destination upon an error sends an email/alert where you can customize the header and message of the email.                                                               |
| openfail.sh      | When a non-network destination has failed its connection.                                                                                                                        |
| prtunavail.sh    | When an output job has been submitted to a disabled destination.                                                                                                                 |
| purge.sh         | When an output is to be purged from the OM Plus queue.                                                                                                                           |
| remotedests.sh   | When remote destinations are either sent or received.                                                                                                                            |
| spooler.sh       | When the spooling process ends.                                                                                                                                                  |
| toobig.sh        | When a job with more than the maximum allowed pages is spooled.                                                                                                                  |
| toodumb.sh       | When the data type of the request differs from data types defined supported by the destination.                                                                                  |
| writefail.sh     | When an output job fails during printing. The output job will be marked interrupted (intrd) and the destination will be disabled.                                                |

## ENVIRONMENT VARIABLES

There are several environment variable that can be set that will affect how the OM Plus system performs in one way or another.

### ACCEPTUNKNOWN

#### Windows and UNIX

Possible Values: y or Y

Set so that it is in the environment of the LPD Service.

If this variable is set it will cause the LPD listening service to accept an incoming request that specifies a destination that is not defined to OM Plus. The request will appear in the Request Status with a status of ready and a destination of 'Unknown'.

### COPYBREAK

#### UNIX

Possible Values: y or n

Set so that it is in the user's environment.

If set, this will cause dcclp to automatically append the copybreak or no copybreak command line parameter to all jobs spooled.

### DATATYPE

#### UNIX

Possible Values: any valid data type (see Data Types)

Set so that it is in the user's environment.

If set, this will cause dcclp to automatically assign the specified data type to all spooled requests.

### FILEBREAK

#### UNIX

Possible Values: y or n

Set so that it is in the user's environment.

If set, this will cause dcclp to automatically append the filebreak or no filebreak command line parameter to all jobs spooled.

## HOLDPRINTED

### UNIX

Possible Values: y or n

Set so that it is in the user's environment.

If set, this will cause dclp to append a hold command to all jobs entering the system.

## LPDEST

### Windows and UNIX

Possible Values: Any valid destination name

Set so that it is in the user's environment.

Sets the default printer for the user in the case that none is specified on the command line.

## LPDGRAPHICS

### UNIX

Possible Values: N or n

Set so that it is in the environment of the LPD service.

If this variable is set, then OM Plus will attempt to do a data type selection regardless of the presence of the 'raw' attribute in the control file, which would normally result in OM Plus setting the datatype to "graphics."

## LPPATTR

### UNIX (Specifically SCO OpenServer)

Possible Values: B, b, R, r, N, n

Set so that it is in the user's environment.

Sets the highlighting attribute of the 'dccstat' program. Use LPPARRT for a user's preference or when there are problems with terminals supporting the defaults. Without being set, dccstat displays the OM Plus version number and the command options in reverse video and the current cursor position is displayed in bold. Based on these default settings, the valid options are:

B – bold is bold – reverse is reverse (same as defaults)

b – bold is bold – reverse is bold

R – bold is reverse – reverse is bold

r – bold is reverse – reverse is reverse

N or n – no highlighting

### LPPAUTO

#### UNIX

Possible Values: any number from 5 to 600

Set so that it is in the user's environment.

Sets the update and refresh interval for the 'dccstat' program. Values are in seconds.

### LPPAUTOMODE

#### UNIX

Possible Values: U or R

Set so that it is in the user's environment.

Sets the mode that the 'dccstat' program uses to automatically update the screen.

U – Update OM Plus queues in real time. New jobs appear and purged jobs disappear.

R – Refresh OM Plus queues. Only updates the current screens information (job status and page counts).

### LPPCONFIRM

#### UNIX

Possible Values: Y

Set so that it is in the user's environment.

Causes 'dccstat' not to prompt for conformation when performing a command.

### OMPLUSACK

#### UNIX

Possible Values: Y

Set in the interface model for an email mode printer.

Causes the email mode printer to make the data of the spool file the body of the email generated by an email mode printer instead of an attachment.

### PRTCNTL

UNIX

Possible Values: Any valid print control

Set so that it is in the user's environment.

If set, this will cause dcclp to automatically set the print control (-p) option for all jobs spooled.

### PTPARENT

**Windows and UNIX**

Possible Values: The RID number of any current job.

Set so that it is in the user's environment.

If set, this will cause any jobs spooled to be marked as children of the RID number that it is set to.

### SILENT

**UNIX**

Possible: Y

Set so that it is in the user's environment.

If set, this will cause dcclp to not display any message (including error messages) back to the command line. This is the same as a "-s" option on the dcclp command line.

### VIEW80

**UNIX**

Possible Values: Valid ASCII representation of the hex control codes to place the users terminal into 80 column mode.

Set so that it is in the user's environment.

Used by the OM Plus report viewing program to put the user's terminal into 80 column mode.

### VIEW132

#### UNIX

Possible Values: Valid ASCII representation of the hex control codes to place the users terminal into 132 column mode.

Set so that it is in the user's environment.

Used by the OM Plus report viewing program to put the user's terminal into 132 column mode.

### VIEWCOL

#### UNIX

Possible Values: 132

Set so that it is in the user's environment.

Automatically puts the user's terminal into 132 column mode when viewing a report in the 'dccstat' program.

### WHEN

#### UNIX

Possible Values: A date in the following format, yy/mm/dd,hh:mm

Set so that it is in the user's environment.

Sets the OM Plus print time for all jobs spooled. This is the same as using the "-W" option on the command line.



## WORKING WITH THE LOGFILE

OM Plus retains detailed logfiles of messages and request activities. The behavior and number of each logfile depends on which operating system that is running. OM Plus retains a log of each system function. The location of that file.

| Operating System | Logfile Location                   |
|------------------|------------------------------------|
| Windows          | %OMHOME%\messages\log              |
| UNIX             | \$LPHOME/messages/log.[servername] |

**Note:** This file is a text file that can be opened with any text editor. There is also a Windows based log file that has many helpful functions for viewing, sorting and searching an OM Plus log. This file can be found in the Windows OM Plus Server install under %omhome%\bin\ompluslog.exe. If you are using a UNIX/LINUX version of the software, a version of this utility can be provided by Support for use on a Windows system.

## VIEWING THE LOGFILE DISPLAY

OM Plus retains a log of all the functions it performs. It is possible to view the main OM Plus logfile from all OM Plus interfaces. To view the logfile from the Request status screen, right click the server name and select “Logfile Display.” The logfile appears displaying the most recent entries.

```

OM Plus DM - log (rockford)

Cmds Refresh

06-05-2020 09:36:03.613(5456:14156)LPP098IU Enable message for destination Dell_S5840cdn sent to scheduler.
06-05-2020 09:36:04.145(9920:11580)LPPNT2041I-(dcpprint)Filter running in termserv Mode for 'RID00138' on 'Dell_S5840cdn'
06-05-2020 09:36:04.145(9920:11580)LPP233I RID00138/rockford15913641634442_rockford00138 starting on destination Dell_S5840cdn.
06-05-2020 09:36:04.223(4544:10528)LPPNT2042I-Filter(GC) running in Termserv Mode for 'RID00138' on 'Dell_S5840cdn'
06-05-2020 09:36:04.302(4544:10528)LPP818W RID00138 Dell_S5840cdn SNMP: warning/idle: low toner
06-05-2020 09:36:16.848(4544:10528)LPPNT2280I-RID00138 PUL job end confirmed by destination 'Dell_S5840cdn', pages printed = 3
06-05-2020 09:36:16.927(4544:10528)LPPNT2036I-Filter(GC) program ending (RID="RID00138",RC=0)
06-05-2020 09:36:17.020(9920:11580)LPPNT2036I-(dcpprint)Filter program ending (RID="RID00138",RC=0)
06-05-2020 09:36:17.020(564:3048)LPPNT0063I-Print Job (Job: RID00138) completed on printer 'Dell_S5840cdn', exit code 0
06-05-2020 09:36:23.489(1204:7672)LPPNT5522I-dccpl command line: '-iRID00138 -Rhold'
06-05-2020 09:36:23.489(1204:7672)LPPNT5603I-dccpl: security host='PLUSTECH' security user='skarl'
06-05-2020 09:36:23.521(1204:7672)LPP113I RID00138 on destination Dell_S5840cdn modified (PLUSTECH\skarl(skarl) - hold).
06-05-2020 09:36:23.521(1204:7672)LPPNT5609I-dccpl: Starting (modify-mode) spooler.bat
06-05-2020 09:36:23.521(1204:7672)LPPNT5509I-<unknown>: Finished.
06-05-2020 09:36:23.521(1204:7672)LPP991IU skarl held RID00138
06-05-2020 09:36:36.771(14008:10748)LPPNT5522I-dccpl command line: '"C:\Plustech\OMPlus\Server\bin\dccpl" "-dDell_S5840cdn" "-trx_test" "-onob" "C:\Plustech\OMPlus\Server\userfilter\LE'
06-05-2020 09:36:36.771(14008:10748)LPPNT5603I-dccpl: security host='rockford' security user='skarl'
06-05-2020 09:36:36.771(14008:10748)LPPNT5502I-Server/bin/dccpl: Processing file list from command line.
06-05-2020 09:36:36.771(14008:10748)LPPNT5510I-Server/bin/dccpl: Trying new job name C:\Plustech\OMPlus\Server\reports\RID00139.
06-05-2020 09:36:36.771(14008:10748)LPPNT5512I-Server/bin/dccpl: Trying new cntl name C:\Plustech\OMPlus\Server\queues\RID00139.
06-05-2020 09:36:36.802(14008:10748)LPPNT5518I-Server/bin/dccpl: Spooling C:\Plustech\OMPlus\Server\userfilter\LEXMARK_PRESCRIPTION_TEST.pcl.
06-05-2020 09:36:36.818(14008:10748)LPPNT5057I-Server/bin/dccpl: Queueing rx_test from rockford\skarl to Dell_S5840cdn as RID00139/rockford15913641967482_rockford00139; pcl-2, 3 pages
06-05-2020 09:36:36.818(14008:10748)LPPNT5610I-dccpl: Script skipped on new request
06-05-2020 09:36:36.834(14008:10748)LPPNT5508I-Server/bin/dccpl: Finished.
06-05-2020 09:36:36.849(3328:4348)LPP098IU Enable message for destination Dell_S5840cdn sent to scheduler.
06-05-2020 09:36:37.381(5428:9024)LPPNT2041I-(dcpprint)Filter running in termserv Mode for 'RID00139' on 'Dell_S5840cdn'
06-05-2020 09:36:37.381(5428:9024)LPP233I RID00139/rockford15913641967482_rockford00139 starting on destination Dell_S5840cdn.
06-05-2020 09:36:38.427(4480:11164)LPPNT2042I-Filter(GC) running in Termserv Mode for 'RID00139' on 'Dell_S5840cdn'
06-05-2020 09:36:38.490(4480:11164)LPP818W RID00139 Dell_S5840cdn SNMP: warning/idle: low toner
06-05-2020 09:36:50.209(4480:11164)LPPNT2280I-RID00139 PUL job end confirmed by destination 'Dell_S5840cdn', pages printed = 3
06-05-2020 09:36:50.287(4480:11164)LPPNT2036I-Filter(GC) program ending (RID="RID00139",RC=0)
06-05-2020 09:36:50.319(5428:9024)LPPNT2036I-(dcpprint)Filter program ending (RID="RID00139",RC=0)
06-05-2020 09:36:50.319(564:3048)LPPNT0063I-Print Job (Job: RID00139) completed on printer 'Dell_S5840cdn', exit code 0
06-05-2020 09:36:59.178(1204:7920)LPPNT5522I-dccpl command line: '-iRID00139 -Rhold'
06-05-2020 09:36:59.178(1204:7920)LPPNT5603I-dccpl: security host='PLUSTECH' security user='skarl'
  
```

## VIEWING WINDOWS LOGFILES

It is possible to view three logfiles on a Windows operating system , the main OM Plus system log, the accounting log, and the port monitor log.

### SYSTEM LOG

OM Plus stores the system messages in %OMHOME%\message\log. The system log contains all the messages issued by any of the multiple programs contained in OM Plus, and each message is separated into the following fields.

1. Date of Message
2. Time of Message
3. Process ID Information
4. Message Number
5. Message Text

### UNDERSTANDING THE LOG DETAILS

OM Plus for Windows provides the user with the ability to set the level of detail to record for an entry. It is possible to set log details from the OM Plus Server, from the Windows **Start** menu, by selecting **Plus Technologies OM Plus DM, Server, OM Plus DM Server**, and then selecting the **Environment** tab. Click **Set Log Details** to select the following additional items that can be recorded in the log.

### SCHEDULER SERVICE

Ensures that messages issued by the Scheduler Service are logged in the OM Plus system log. The number of messages the Scheduler Service issues can cause the logfile to expand rapidly. This selection should only be used for debugging purposes.

### ADMIN SERVICE

Ensures that messages issued by the Admin Service are written to the OM Plus system log. When performing many administrative functions, such as defining a new destination, several messages may appear in the log.

### END-TO-END SERVICE

Ensures that messages issued by the Distribution Service are written to the OM Plus system log.

## OM TRANSFER SERVICE

Destinations with a mode of OM Plus and multiple OM Plus servers working together use this service extensively. The number of extra messages that appear in the log depends on the number of destinations using this mode.

## iSAT SERVER SERVICE

Ensures that messages issued by the iSAT are written to the OM Plus system log.

## REMOTE SERVICE

Ensures that messages issued by the Remote Service are written to the OM Plus system log.

## FILTER

Ensures that messages issued by the filter will be written to the OM Plus System log. The filter runs every time a request de-spools. This option causes the logfile to expand quickly; therefore use this only for debugging purposes.

## DCCLP

Ensures that dclp command line issued or generated by the port monitor will be written to the OM Plus system log. This adds an extra line to the log for each spooled item. This feature is useful for debugging purposes.

## SOCKET TRANSACTIONS

Ensures that OM Plus logs all types of TCP/IP socket activity, such as connection openings and closings. If the system has network printers or remote destinations, a large number of entries will appear in the log, therefore this should only be used for debugging purposes.

## SOCKET DATA TRACE

Writes a hex dump of all data passed through a TCP/IP socket. Any network access by OM Plus adds large numbers of lines to the log. Before selecting this option, contact Plus Technologies Support for instructions.

## SECURITY

Logs information pertaining to the OM Plus Security system. This creates large numbers of entries in the log. Unlike the other selections, turning this off removes all messages pertaining to the Security system from the log.

## IPP SERVICE

Configures the Internet Printing Protocol for secure network printing.

---

## TLS SETTINGS

Configures whether OM Plus Delivery Manager will refuse, accept or require TLS connections.

---

## UNDERSTANDING LOGFILE LIMITS

On a Windows Server, the logfile truncates when it reaches a certain size (default 1.5 MB). If it is larger than 1.5 MB, it is renamed with a date stamp, and then a new log starts.

---

## SETTING LOGFILE LIMITS

It is also possible to set limits for how large the logfile can expand. In the **Maximum Log Size (in Bytes)** field, enter the size at which OM Plus should truncate the file. In the next field, enter the minimum log size. When OM Plus truncates the file it retains this number of bytes in history instead of truncating them all. If OM Plus should save previous logfiles, select **Save Log Files**, and then in the **Save Under Directory** field, enter the location.

---

## VIEWING PORT MONITOR LOGFILES

If the OM Plus for Windows Server is set to use the OM Plus port monitor, a second log retains information about the starting and stopping of the port monitor. Logfile limits do not affect this log.

## VIEWING UNIX OR LINUX LOGFILES

It is possible to view two logfiles on a UNIX operating system. They include, the main OM Plus system log and the accounting log.

***Note:** The accounting log is identical for both Windows and UNIX operating systems. For information, refer to [Viewing Accounting Logfiles](#).*

---

## SYSTEM LOGS

OM Plus records all messages in the main OM Plus log, log.[servername], where [servername] is the hostname of the OM Plus Server.

The main log contains all the messages issued by any of the multiple programs contained in OM Plus, and each message is separated into the following fields.

1. Date
2. Time
3. Year
- 4 Message Number
5. Message Text
6. [program that sent message]

---

## CUSTOMIZING THE LOGS

OM Plus for UNIX allows for the customization of the logs. In all cases, the main OM Plus log contains all the messages. If OM Plus creates a secondary log, it contains copies of the messages.

The most likely type of secondary log is a separate error log. It is possible to create a log for all error messages by creating a new file with the name `log_errors` in `$LPHOME/constants`. As long as this file exists, copy of all error messages are saved in the file `$LPHOME/messages/Emsg.[servername]`.

---

## UNDERSTANDING UNIX LOGFILE LIMITS

OM Plus checks the sizes of all the OM Plus logfiles at boot time. Any that are greater than or equal to 10 megabytes cause the **logsize.sh** event from the events directory to run. By default this script will copy the current log file to `logfile.old`. This script can be modified to perform log pruning as desired by the administrator.

---

## VIEWING SYSTEM MESSAGES

The entries in the logs are all associated with a message number. Many of these messages are documented for later reference. It is possible to use the Client interface to search for the definitions of system messages on the Request Status screen, from the **Help** menu, by selecting **System Messages**, entering the message number, and then pressing Enter.

***Note:** To search for the definitions of system messages in a Character-based interface, from the command line, run `dccmsgshelp`. For information, refer to *Using the Command Reference*.*

---

## VIEWING ACCOUNTING LOGFILES

On the System Defaults screen, if Enable Accounting is set to Yes, the accounting log retains entries of every print job. This log resides in Windows in `%OMHOME%\messages\acctlog` and in UNIX in `$LPHOME/messages/acctlog`. The accounting log contains the following 12 string fields delimited by a comma. In the Classic File format `ACCT_LOG="Y"`

1. Date and Time Stamp
2. Request ID
3. Host!Userid
4. Destination
5. Report Title
6. Form Name
7. Number of Pages (zero if page counting is not done)
8. Number of Bytes (characters)
9. Print Time in seconds
10. Exit Code (exit codes are listed below)
11. Group
12. Banner

Additional fields in extended format: ACCT\_LOG"E"

- 13.** Datatype (from env DATATYPE)
- 14.** Sent flag if available (see dccfilter exit\_func comments)
- 15.** Confirmed pages from printer, if available
- 16.** Confirmed sheets from printer, if available

Additional fields for new reports: ACCT\_LOG="X"

- 17.** WouldHaveBeen destination
- 18.** WouldHaveBeen print control
- 19.** WouldHaveBeen form
- 20.** Original destination
- 21.** Original Print Control
- 22.** Original Form

New filed filter print control which was never originally captured

- 23.** Print Control

Post 2.5.0 additions for getting counts from the printer

- 24.** Meter mono usage
- 25.** Meter color usage

| Exit Code | Description                                                                                                                                     |
|-----------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| 0         | Good – The request has processed correctly.                                                                                                     |
| 1         | Bad Input – No standard in.                                                                                                                     |
| 2         | Bad Output – No standard out.                                                                                                                   |
| 3         | Read Fail – OM Plus was unable to open the file.                                                                                                |
| 4         | Bad Env – Something in the environment is wrong.                                                                                                |
| 5         | Write fail – OM Plus was unable to create a new file, overwrite an existing file or transfer a file to a remote destination.                    |
| 7         | Dropped carrier (serial) – The serial connection failed unexpectedly.                                                                           |
| 8         | Interrupted – The request was not able to be completed due to a resolvable condition.                                                           |
| 9         | Bad parameter count – The parameters passed have caused an error in OM Plus.                                                                    |
| 10        | Canceled – The request was canceled by a user.                                                                                                  |
| 11        | Suspended – The request has been stopped by a user. Jobs in this state must be released.                                                        |
| 12        | Good (network destination – The transfer to the network destination has completed.                                                              |
| 13        | Unable to connect – OM Plus could not connect with the destination.                                                                             |
| 17        | Mailed – Email sent to server.                                                                                                                  |
| 18        | Failed – Failed Mail, Fax or FTP.                                                                                                               |
| 19        | Intrd, not Disabled – Request interrupted, but don't disable the destination.                                                                   |
| 20        | Ready, Disable – Mark the request as ready, but disable the destination.                                                                        |
| 21        | Ready, Not Disable – Mark request ready and leave the destination enabled but don't send for an interval.                                       |
| 22        | Ready, Not disabled – Mark request ready and immediately retry.                                                                                 |
| 23        | Interrupt – User filter non-0 exit code.                                                                                                        |
| 24        | Ready, Disable – Request OK, but disable the destination (for marking destination problem).                                                     |
| 25        | Not Ready – Destination not ready, disable and keep job ready.                                                                                  |
| 26        | Busy – Destination is busy, disable destination, keep job ready.                                                                                |
| 27        | Re-Run – Don't disable destination, set request to I_READY                                                                                      |
| 28        | Delay – Print Failed, set request to timed for delay and don't disable destination.                                                             |
| 29        | Unconfirmed – Data was sent, but can't confirm that. Don't disable.                                                                             |
| 71        | Bad Setup – Bad fax subprogram setup, missing ftp password                                                                                      |
| 72        | STTY Fail – Set Serial options failed.                                                                                                          |
| 73        | Open Fail – Could not open device/file.                                                                                                         |
| 74        | Print Control -- Missing or corrupt print file.                                                                                                 |
| 75        | Form Error – Missing or corrupt form.                                                                                                           |
| 76        | File Error – Missing or corrupt file.                                                                                                           |
| 78        | Illegal Data Type – Data type not allowed for destination.                                                                                      |
| 79        | Shared Memory Error – Error accessing system shared memory.                                                                                     |
| 80        | No Service – No service specified in /etc/services.                                                                                             |
| 81        | No Socket – Could not connect to system socket resource.                                                                                        |
| 82        | Bad Set Socket – Error to set options on the TCP/IP socket.                                                                                     |
| 83        | No Connection – Cannot connect to a host or destinations.                                                                                       |
| 84        | Bad Queue – Cannot access or read omplus queue files.                                                                                           |
| 85        | Bad Report – Cannot access or read omplus report files.                                                                                         |
| 87        | Validation Failure -- The system is not enabled for bundling or has expired, the filter will exit with this when running a bundle mode printer. |
| 89        | Internal Error – Internal Error to omplus process.                                                                                              |
| 90        | No Processes – Unable to fork at start of job.                                                                                                  |

For example: 06-05-2020 09.36.50.319(564:3048)LPPNT0063I-Print Job (Job: RID00139) completed on printer 'Dell\_S5840cdn', exit code 0

## SETTING EMAIL NOTIFICATION

Email notifications require that a sending email account be configured first. To configure this email account in OM Plus, open the OM Plus DM for Windows utility on the OM Plus server. Select the “Environment” tab and click the “Settings” button.

Select the Fax/Email Set Up tab.

The screenshot shows the 'Settings' window with the 'Fax/Email Set Up' tab selected. The window has a title bar with 'Settings' and a close button. Below the title bar is a tabbed interface with the following tabs: System Tuning, Accounting Log, Scripts In Use, SAP Settings, User Cross Reference, iSat Server, Service Exclusion Settings, Remote Host Lists, Time Out Values, Data Types, Remote Login, Span Host RID Ranges, Fax/Email Set Up (selected), LPD Service, OMPlus-Mode Service, and TermServ Settings. The main content area is divided into two sections: 'Email Setup' and 'Fax Setup'. The 'Email Setup' section contains five text input fields labeled 'Server:', 'Sender:', 'Username:', 'Password:', and 'Port:'. The 'Fax Setup' section contains a 'RightFax Setup' button and a 'Default Fax Server' dropdown menu currently set to 'None'. A 'Close' button is located at the bottom right of the window.

Once there, enter the email server’s address, the sender email address, the login username, the password and the port number for the server. Close this window to save changes.

**Note:** This interface is used for setting up a single email account to send emails. If, for some reason, you need to be able to send emails from multiple accounts, please contact OM Plus support.




**Note:** The tool OM Plus uses to send emails is not compatible with SSL connections without additional configuration. If your email server requires SSL, please contact OM Plus for additional assistance in setting up your server.


For the email notification to be applied to destinations, is a two step process.

First Open OM Plus Administration > Click the Destination Tab > Click Notification Addresses.

Select Commands > Add Address > Enter a Name > Click OK > Enter an Email Address > Click Save.



Second, while still in OM Plus Administration > Click on Destinations > Select the destination(s) that you would like to receive notifications from > Click on the Miscellaneous Tab > Use the drop box next to Notification and select the email address.



## DATA TYPES

There are 10 data types that are known to OM Plus. When a report is spooled, OM Plus interrogates the data in an attempt to determine what kind of file is being spooled. The data type determines the following five behaviors of the OM Plus system with regards to a specific request.

**Page Count:** Can OM Plus determine how many pages are contained within this file.

**Page Indexing:** Can OM Plus determine where there are page breaks within this document.

**Restart-able:** Can OM Plus restart this document from a page other than the first page. This also governs the ability to copy out a range of pages from this document. Even if this column is marked 'no', a printer restart may be possible. See 'Restarting a request' in the 'Working with status components' section.

**Line Feed to Carriage Return + Line Feed Conversions:** Will this document have Carriage Returns pre-pended to all of its Line Feed if specified by the system.

**Translation:** Will this document be filtered through the translation table logic if specified.

## DESTINATION DETAILS SCREEN

**Destination:** The name of the destination.

**Mode:** The connection mode for this destination. For more information, see Modes.

**Device:** Location of device.

**Filter:** The default filter used by this device.

**User Filter:** The user filter to be used by this device.

**Def Form:** The default form for this device.

**Form:** Form currently mounted to this device.

**Accept Time:** Time device was last set to “accept.”

**Accept Reason:** Note field for describing the reason for setting to “accept.”

**Enable Time:** Time of last enable.

**Enable Reason:** Note field for the enable.

**Metering:** The rate, in character per second, that jobs will be sent to the device.

**Model:** The model this destination will use for processing jobs.

**File Break:** Will the destination insert a page break after each file?

**Copy Break:** Will the destination insert a page break after each copy?

**Banner:** Will the destination attach a banner page by default?

**Line Feed Carriage Feed:** Will the destination convert line feeds to carriage return line feeds?

**Close Delay:** The amount of time to keep the connection active between jobs in streaming mode.

**Write Timer:** The amount of time, in seconds, OM Plus will attempt to write a job to this device.

**Open Timer:** The amount of time, in seconds, OM Plus will attempt to open a connection to this device.

**Purge Time:** The amount of time, in seconds, jobs will be kept after being marked eligible for purge and before being purged.

**Term Info:** The terminfo file associated with this device.

**Pcap File:** The PCAP file associated with this destination.

**Comments:** Notes about this device.

**Support:** Name or contact information.

**Two Way Protocol:** The method of communication used by this device.

**Alt Dest:** The alternate destination for this device.

**SW Dest:** The switch destination for this device.

**Page Limit:** The maximum number of pages.

**Pend Form:** When initiating a form change, this is the form that will be loaded when the device is re-enabled.

## REQUEST DETAILS SCREEN

|                     |                                      |
|---------------------|--------------------------------------|
| <b>Status:</b>      | Interrupted                          |
| <b>Title:</b>       | testPage                             |
| <b>Source:</b>      | skarllap                             |
| <b>Destination:</b> | Dell_S5840                           |
| <b>User:</b>        | skarl                                |
| <b>Date:</b>        | 8/20/20, 4:06:09 PM                  |
| <b>Pages:</b>       | 0 / 1                                |
| <b>Copies:</b>      | 0 / 1                                |
| <b>Form:</b>        | stock                                |
| <b>Options:</b>     | nob<br>purge<br>restart=00001        |
| <b>Priority:</b>    | 2                                    |
| <b>Data Type:</b>   | simple                               |
| <b>Tracking No</b>  | skarllap15979539695762_skarllap00102 |

**Note:** This first tab shows the most relevant data in an easy to read format. To find the full queue file contents with all options and settings (or to find an easier format for copying and pasting into emails), click the second tab.

**Request ID (title bar):** The RID for this request.

**Status:** The status of this request.

**Title:** The title of the job. This will be a file name if coming from the command line or the title assigned by the Windows print spooler if coming through a linked printer.

**Source:** Name of the server that spooled the job. In Windows this is often the workstation.

**Destination:** The destination to which this job will despool.

**User:** The user name of the user who spooled this job.

**Date:** The date and time the job was spooled.

**Pages:** The number of pages printed out of the number of pages in this print job. If OM Plus is unable to count the number of pages due to the data type, it will display the size in bytes with "SB" added to the end.

**Priority:** The priority of this job. 0 is lowest, 40 is highest. 20 is default.

**Copies:** Number of copies printed and requested.

**Data Type:** The format in which OM Plus believes this job to be.

**Form:** The form required for this job.

**Options:** Any options that have been assigned using the -o option string.