# PASO DE LENGUAJE DE ALTO NIVEL A BAJO NIVEL

# 1. LENGUAJE ALTO NIVEL

Int main (){

Int P = 3014;

Int C = 19223;

D [150];

D[22] = 32 + P;

D [15] = 18332;

Return P + C + D[22];

Para realizar el paso a ensamblador realizamos asignación de registros:

P = %L0

C = %L1

D = %L2

Ahora procedemos a realizar el paso del programa anterior a lenguaje ensamblador.

### 2. LENGUAJE ENSAMBLADOR

MOV 3014, %L0

SETHI 18, %L1

OR %L1, 791, %L1

ADD %LO, 32, %LO

ST %L0, [%L2 + (22 \* 4)]

SETHI 17, %L3

OR %L3, 924, %L3

ADD %L0, %L1, %L0

LD [%L2 + (22 \* 4)], %L4

ADD %L0, %L4, %O0

#### 3. LENGUAJE MAQUINA

Para este proceso se requiere utilizar los formatos 1 y 2 de SPARC V8 de la siguiente manera:

		1. MOV							
ОР	RD	OP3		RS1 IN		М	INM 13		
10	10000		0010	00000			0101111000110		
2. SETHI									
OP	RD	RD OP2		22INM					
00	1001	0	100	000000000000000010010					
3.OR									
OP	RD		OP3	RS	RS1		INM 13		
10	10001	С	000010	10001		1	0001100010111		
4. ADD									
ОР	RD		OP3	RS	RS1		INM 1	3	
10	10001	0	00000	100	10001		000000100000		
5. ST									
OP	RD		OP3	RS <sup>2</sup>	RS1 II		INM 13		
11	10000	0	00100	1000	10001 1 00000010110		11000		
6. SETHI									
OP	RD		OP2	OP2 22INM					
00	1000	1							
7.OR									
OP	RD	OP3		RS1		INM	INM 1	3	
10	10011	0	00010	1001	10011		00011100	11100	
8. ADD									
OP	RD	0	DP3	RS1	ı	NM	UNSIGNED	RS2	
10	10000	00	00000	1000	0	0	00000000	10000	
9. LD									
OP	RD	RD OP3		RS1	RS1 INM		INM 13		
10	10100	0	000100 10000 1 000000		000000101	11000			
10. ADD									
ОР	RD	(	OP3	RS1	I	NM	UNSIGNED	RS2	
10	01000	00	00000	1000	o T	1	00000000	10100	

### 4. CÓDIGO HEXADECIMAL

se procede a pasar el lenguaje de maquina a código hexadecimal

1	0X A0102BC6
2	0X 25000012
3	0X A2146317
4	0X A2046020
5	0X E0246058
6	0X 2300039C
7	0X A614E39C
8	0X A0020010
9	0X A8242058
10	0X 90042014