

CompTIA Server+

Installing and Configuring Server Roles and Features

- Introduction
 - Lab Topology
 - Exercise 1 - Identify Server Roles
 - Exercise 2 - Install and Configure a Server Role
 - Exercise 3 - Implement and Configure a DHCP Client
 - Review
-

Introduction

Server+

Server Roles

DHCP

DNS

Active Directory Domain Services Role

Welcome to the **Installing and Configuring Server Roles and Features** Practice Lab. In this module, you will be provided with the instructions and devices needed to develop your hands-on skills.

In this module, the learner will identify the roles that are available in Windows Server operating systems. The learner will also install a role to provide the services for networked clients, as well as identify and install the associated features for the server role.

In today's modern networks, organizations implement client/server networks. The server's functionality in networking is to provide services for client operating systems that request these services. The services that servers provide are known as roles, and it is up to server administrators to be able to identify the services the clients require and install the roles accordingly. Along with the roles that servers perform are features that are used by the server to augment a role functionality, and these features might be added as a part of installing server roles within the server operating system.

Learning Outcomes

In this module, you will complete the following exercises:

- Exercise 1 - Identify Server Roles
- Exercise 2 - Install and Configure a Server Role
- Exercise 3 - Implement and Configure a DHCP Client

After completing this module, you should be able to:

- Examine the Active Directory Domain Services Role on a Windows Server Operating System
- Examine the DNS Server Role in a Windows Server Operating System
- Install the DHCP Role on a Windows Server Operating System
- Configure the DHCP Server Role on a Windows Server Operating System
- Configure the Windows 10 DHCP Client

Exam Objectives

The following exam objectives are covered in this module:

2.3 Given a scenario, configure and maintain server functions and features

- Server roles requirements

Lab Duration

It will take approximately **1 hour** to complete this lab.

Help and Support

For more information on using Practice Labs, please see our **Help and Support** page. You can also raise a technical support ticket from this page.

Click **Next** to view the Lab topology used in this module.

Lab Topology

During your session, you will have access to the following lab configuration.

Depending on the exercises, you may or may not use all of the devices, but they are shown here in the layout to get an overall understanding of the topology of the lab.

- **PLABDC01** - (Windows Server 2019 - Domain Controller)
- **PLABDM01** - (Windows Server 2022 - Domain Member Server)
- **PLABWIN10** - (Windows 10 - Domain Member Workstation)
- **PLABALMA** - (Alma Linux 8.7 - Standalone Linux Workstation)
- **PLABUBUNTU** - (Linux Ubuntu - Standalone Linux Server)

Click **Next** to proceed to the first exercise.

Exercise 1 - Identify Server Roles

Microsoft Active Directory is one of the most popular directory services implemented in enterprise networks today. Active Directory Domain Services or AD DS role is the backbone service of Microsoft's Active Directory functionality providing centralized administration of all objects within a Windows domain. Microsoft's Active Directory relies heavily on the Domain Name System or DNS service for name resolution and is installed side-by-side with Active Directory.

In this exercise, you will examine a directory services role used in a Windows Active Directory domain as well as examine the DNS server roles installed on a Windows Server operating system.

Learning Outcomes

After completing this exercise, you should be able to:

- Examine the Active Directory Domain Services Role on a Windows Server Operating System
- Examine the DNS Server Role in a Windows Server Operating System

Your Devices

You will be using the following device in this lab. Please power this on now.

- **PLABDC01** - (Windows Server 2019 - Domain Controller)

Task 1 - Examine the Active Directory Domain Services Role on a Windows Server Operating System

Windows Active Directory is a common server role found in organizations used for centralized management of users, groups, servers, workstations, and much more.

In this task, you will identify the directory services role that is being performed by the Windows Server operating system.

Step 1

Connect to **PLABDC01**.

In the **Server Manager** window, select **AD DS** on the left pane.




Figure 1.1 Screenshot of PLABDC01: Displaying selecting AD DS in the Server Manager window.

Note: The server PLABDC01 is performing the role of a Domain Controller for Microsoft Active Directory. The role is called Active Directory Domain Services and provides a

directory service for centralized account and service management within a Windows Domain environment. When a user logs into a Windows workstation that is a domain member, the authentication request is sent to the AD DS server for verification. The directory services role contains a centralized database of all objects inside a Windows Active Directory enterprise network.

Step 2

In the context pane, scroll down to the **EVENTS** section.

Select any event containing **Microsoft-Windows-ActiveDirectory_DomainService** as the source of the event.




Figure 1.2 Screenshot of PLABDC01: Displaying the Server Manager > AD DS window and selecting Microsoft-Windows-ActiveDirectory_DomainService in the EVENTS section.

Step 3

Review the **Event** details directly below the **EVENTS** section of the context pane.




Figure 1.3 Screenshot of PLABDC01: Displaying the Server Manager > AD DS window and viewing details of the Microsoft-Windows-ActiveDirectory_DomainService Event.

Note: Server Manager in Windows Server provides a quick way to view the roles that are installed on the server. In this example, when you select an event for AD DS, you can examine the details associated with that event.

Step 4

In the **Server Manager** window, access the **Tools** menu.

Select **Active Directory Users and Computers** from the drop-down menu.




Figure 1.4 Screenshot of PLABDC01: Displaying the Server Manager window and selecting Active Directory Users and Computers from the Tools drop-down menu.

Note: The tools menu gives you a view of the current roles and features installed on the server. When a role is installed, the role's management interface can be selected to configure the role's services. You can see from the Tools list that PLABDC01 is running the Active Directory Domain Services role and the Domain Name System or DNS role. Active Directory relies on DNS, and this server role will be installed as a part of installing AD DS.

Step 5

In the **Active Directory Users and Computers** management interface window, expand the **practicelabs.com** node on the left pane.




Figure 1.5 Screenshot of PLABDC01: Displaying the Active Directory Users and Computers window and expanding the practicelabs.com node.

Note: The Active Directory Users and Computers Microsoft Management Console is the primary interface to manage accounts within an Active Directory domain environment.

Step 6

Close the **Active Directory Users and Computers** window.




Figure 1.6 Screenshot of PLABDC01: Displaying closing the Active Directory Users and Computers window.

Keep the **Server Manager** window open.

Task 2 - Examine the DNS Server Role in a Windows Server Operating System

The Domain Name System or DNS is one of the most important services used in modern networks today. Microsoft's Active Directory relies heavily on DNS to locate computers and services inside a Windows domain and is installed by default when installing the Active Directory Domain Services role.

In this task, you will identify the DNS server role as well as review the properties of the DNS domain.

Step 1

In **PLABDC01**, the **Server Manager** window is open.

Access the **Tools** menu and select **DNS** from the drop-down list.




Figure 1.7 Screenshot of PLABDC01: Displaying the Server Manager window and selecting DNS from the Tools drop-down menu.

Step 2

On the **DNS Manager** console, select **PLABDC01** on the left pane.




Figure 1.8 Screenshot of PLABDC01: Displaying selecting PLABDC01 in the DNS Manager console.

Note: The server **PLABDC01** is configured with the Domain Name System server role to provide the name resolution service with Active Directory.

Step 3

On the **DNS Manager** console, navigate to the following:

PLABDC01 > Forward Lookup Zones > practicelabs.com

Select **practicelabs.com**.

On the right details pane, select and right-click on the **plabdc01 - Host(A)** record and select **Properties**.




Figure 1.9 Screenshot of PLABDC01: Displaying right-clicking on plabdc01 and selecting Properties in the DNS Manager console.

Step 4

In the **plabdc01 Properties - Host (A)** tab, review the following sections of the DNS A record:

- **Host**
- **IP address**




Figure 1.10 Screenshot of PLABDC01: Displaying the plabdc01 Properties dialog box.

Note: This DNS record is used to map the PLABDC01's name to an IP address in a process called name resolution. The Domain Name System is one of the most important network services provided by the DNS server role.

Step 5

Click **Cancel** on the **plabdc01 Properties** dialog box.




Figure 1.11 Screenshot of PLABDC01: Displaying clicking Cancel on the plabdc01 Properties dialog box.

Step 6

Close the **DNS Manager** window.




Figure 1.11 Screenshot of PLABDC01: Displaying closing the DNS Manager window.

Exercise 2 - Install and Configure a Server Role

A common part of server administration is the ability to install and configure server roles. In this exercise, you will install and configure the DHCP role on a Windows Server Operating System.

Learning Outcomes

After completing this exercise, you should be able to:

- Install the DHCP Role on a Windows Server Operating System
- Configure the DHCP Server Role on a Windows Server Operating System

Your Devices

You will be using the following devices in this lab. Please power these on now.

- **PLABDC01** - (Windows Server 2019 - Domain Controller)
- **PLABDM01** - (Windows Server 2022 - Domain Member Server)

Task 1 - Install the DHCP Role on a Windows Server Operating System

In this task, you will use Server Manager to install the DHCP role on a Windows Server.

Step 1

Connect to **PLABDM01**.

In the **Server Manager** window, access the **Manage** menu and select the **Add Roles and Features** option from the drop-down menu.




Figure 2.1 Screenshot of PLABDM01: Displaying accessing the Manage menu and selecting Add Roles and Features in the Server Manager window.

Step 2

From the **Add Roles and Features Wizard - Before you begin** page, click **Next**.




Figure 2.2 Screenshot of PLABDM01: Displaying clicking Next in the Add Roles and Features Wizard - Before you begin page.

Step 3

In the **Select installation type** page, ensure that the **Role-based or feature-based installation** radio button is selected.

Click **Next**.




Figure 2.3 Screenshot of PLABDM01: Displaying clicking Next in the Select installation type page.

Step 4

In the **Select destination server** page, ensure that the **Select a server from the server pool** radio button is selected.

PLABDM01.practicelabs.com is highlighted.

Click **Next**.





Figure 2.4 Screenshot of PLABDM01: Displaying clicking Next in the Select destination server page.

Step 5

In the **Select server roles** page, enable the **DHCP Server** checkbox.



Step 6

In the **Add Roles and Features Wizard - Add features that are required for DHCP Server?** pop-up box, click **Add Features**.




Figure 2.6 Screenshot of PLABDM01: Displaying selecting Add Features in the Add Roles and Features Wizard - Add features that are required for DHCP Server? pop-up box.

Note: The Add Roles and Features Wizard recognize the feature dependencies that are required to run the DHCP server role and will prompt the administrator to install them.

Step 7

Back on the **Select server roles** page, click **Next**.




Figure 2.7 Screenshot of PLABDM01: Displaying selecting Next in the Select server roles page.

Step 8

From the **Select features** page, click **Next**.




Figure 2.8 Screenshot of PLABDM01: Displaying selecting Next in the Select features page.

Step 9

On the **DHCP Server** page, click **Next**.




Figure 2.9 Screenshot of PLABDM01: Displaying selecting Next on the DHCP Server page.

Step 10

In the **Confirm installation selections** page, review the role and associated features that will be installed and click **Install**.




Figure 2.10 Screenshot of PLABDM01: Displaying selecting Install on the Confirm installation selections page.

Step 11

Once the installation is complete, click **Close** on the **Installation progress** page.




Figure 2.11 Screenshot of PLABDM01: Displaying selecting Close on the Installation progress page.

Note: This completes the installation of the DHCP server role on PLABDM01. However, the server role requires additional configuration to provide the DHCP service.

Keep the **Server Manager** window open.

Task 2 - Configure the DHCP Server Role on a Windows Server Operating System

Once the DHCP role is installed, the role is not operational until it is configured.

In this task, you will authorize the DHCP server with Active Directory to provide IP address leases, configure IP address exclusions, and DHCP scope options.

Step 1

Ensure you are connected to **PLABDM01**, where the **Server Manager** window is open.

Select the **Notifications (Flag)** icon with the caution notification symbol next to it.




Figure 2.12 Screenshot of PLABDM01: Displaying the Server Manager window and selecting the Notifications icon.

Step 2

Under the **Post-deployment Configuration** task box, select **Complete DHCP configuration**.




Figure 2.13 Screenshot of PLABDM01: Displaying selecting Complete DHCP configuration under the Post-deployment Configuration task box.

Step 3

In the **DHCP Post-Install configuration wizard - Description** page, click **Next**.




Figure 2.14 Screenshot of PLABDM01: Displaying selecting Next on the DHCP Post-Install configuration wizard - Description page.

Step 4

On the **Authorization** page, ensure that the **Use the following user's credentials** radio button is selected and the **PRACTICELABS\Administrator** username is present.

Click **Commit**.




Figure 2.15 Screenshot of PLABDM01: Displaying the Authorization page with the Commit button highlighted.

Note: This step is required only in an Active Directory domain and not required for a standalone DHCP server. This feature requires only authorized DHCP servers to provide IP addresses in the Windows domain.

Step 5

Click **OK** on the **DHCP Post-Install configuration error** Alert box.




Figure 2.16 Screenshot of PLABDM01: Displaying clicking OK on the DHCP Post-Install configuration error Alert box.

Step 6

From the **Summary** page, click **Close**.

The screenshot shows a web browser window titled "PLABDM01 - Work - Microsoft Edge" with the URL <https://stg.practice-labs.com/device-advanced.aspx?client=html&device=1&width=1024&height=768&login=true&token=Mc1jsdN54LFPHUtS0CKnc...>. The page is titled "DHCP Post-Install configuration wizard" and displays the "Summary" tab. On the left, a sidebar lists "Description", "Authorization", and "Summary", with "Summary" selected. The main content area shows the status of post-install configuration steps:

The status of the post install configuration steps are indicated below:

Creating security groups		Done
Please restart the DHCP server service on the target computer for the security groups to be effective.		
Authorizing DHCP server		Done

At the bottom of the wizard, there are navigation buttons: "< Previous", "Next >", "Close", and "Cancel". The Windows taskbar is visible at the bottom of the screen.

Step 7

On the **Server Manager** window, access the **Tools** menu and select **DHCP**.




Figure 2.18 Screenshot of PLABDM01: Displaying accessing the Tools menu and selecting DHCP in the Server Manager window.

Step 8

In the **DHCP** management console, navigate to **plabdm01.practicelabs.com** > **IPv4** on the left pane.

Select and right-click on the **IPv4** node and select **New Scope** from the context menu.




Figure 2.19 Screenshot of PLABDM01: Displaying the DHCP window and right-clicking on the IPv4 node and selecting New Scope.

Step 9

In the **New Scope Wizard**, click **Next**.




Figure 2.20 Screenshot of PLABDM01: Displaying selecting Next in the New Scope Wizard.

Step 10

In the **Scope Name** page, type the following:

Name: Production Scope
Description: Production Computers

Click **Next**.




Figure 2.21 Screenshot of PLABDM01: Displaying the Scope Name page with the required Name and Description typed in and the Next button selected.

Step 11

In the **IP Address Range** page, type the following:

Configuration settings for DHCP Server

Start IP address: 192.168.0.1
End IP address: 192.168.0.50

The **Configuration settings that propagate to the DHCP Client** will be as follows:

Length: 24

Subnet mask: 255.255.255.0

Click **Next**.




Figure 2.22 Screenshot of PLABDM01: Displaying the IP Address Range page with the required settings performed and the Next button selected.

Note: The IP address range defines how many IP addresses are available to clients within this scope.

Step 12

From the **Add Exclusions and Delay** page, type the following

Start IP Address: 192.168.0.1
End IP Address: 192.168.0.5




Figure 2.23 Screenshot of PLABDM01: Displaying the Add Exclusions and Delay page with the required settings performed.

Note: The exclusion range that has been configured here is to prevent the IP addresses used by other servers in this lab environment from being leased out to DHCP clients requesting IP addresses. This type of situation will cause an IP address conflict on the network as multiple computers would be trying to use the same IP address on this network.

Step 13

In the **Add Exclusions and Delay** page, click **Add**.




Figure 2.24 Screenshot of PLABDM01: Displaying the Add Exclusions and Delay page with the excluded address range added.

Step 14

In the **Add Exclusions and Delay** page, click **Next**.




Figure 2.25 Screenshot of PLABDM01: Displaying the Add Exclusions and Delay page with the Next button highlighted.

Step 15

In the **Lease Duration** page, click **Next**.




Figure 2.26 Screenshot of PLABDM01: Displaying the Lease Duration page with the Next button highlighted.

Step 16

In the **Configure DHCP Options** page, ensure the **Yes, I want to configure these options now** radio button is selected.

Click **Next**.




Figure 2.27 Screenshot of PLABDM01: Displaying the Configure DHCP Options page with the required option selected and the Next button highlighted.

Step 17

In the **Router (Default Gateway)** page, type the following for the **IP address** field:

192.168.0.250

Click **Add**.




Figure 2.28 Screenshot of PLABDM01: Displaying the Router (Default Gateway) page with the required IP address added.

Note: This DHCP scope option will be the IP address of the connected router configured on the DHCP client.

Step 18

In the **Router (Default Gateway)** page, click **Next**.




Figure 2.29 Screenshot of PLABDM01: Displaying the Router (Default Gateway) page with the Next button highlighted.

Step 19

In the **Domain Name and DNS Servers** page, click **Next**.




Figure 2.30 Screenshot of PLABDM01: Displaying the Domain Name and DNS Servers page with the Next button highlighted.

Note: This DHCP scope option will be the IP address of the DNS server for the DHCP client.

Step 20

On the **WINS Servers** page, click **Next**.




Figure 2.31 Screenshot of PLABDM01: Displaying the WINS Servers page with the Next button highlighted.

Step 21

In the **Activate Scope** page, click **Next**.




Figure 2.32 Screenshot of PLABDM01: Displaying the Activate Scope page with the Next button highlighted.

Step 22

In the **Completing the New Scope Wizard** page, click **Finish**.




Figure 2.33 Screenshot of PLABDM01: Displaying the Completing the New Scope Wizard page with the Finish button highlighted.

Step 23

Back on the **DHCP** console, expand the **Scope [192.168.0.0] Production Scope** node.

Select **Address Pool**.




Figure 2.34 Screenshot of PLABDM01: Displaying the DHCP console window with Address Pool selected on the left pane.

Note: This is where you can identify the IP address range for the select scope as well as any IP addresses that are excluded from being issued to DHCP clients by this DHCP server.

Step 24

Select **Scope Options**.




Figure 2.35 Screenshot of PLABDM01: Displaying the DHCP console window with Scope Options selected on the left pane.

Note: These are the most common options to configure when setting up the DHCP server role:

003 Router

006 DNS Servers

015 DNS Domain Name

Close the **DHCP** window.

Minimize the **Server Manager** window.

Exercise 3 - Implement and Configure a DHCP Client

When implementing a server role, it is critical to confirm that DHCP clients can receive an IP address lease from the DHCP server on the local network.

In this exercise, you will identify and determine if PLABWIN10 is able to obtain an IP address lease from PLABDM01.

Learning Outcomes

After completing this exercise, you should be able to:

- Configure the Windows 10 DHCP Client

Your Devices

You will be using the following devices in this lab. Please power these on now.

- **PLABDM01** - (Windows Server 2022 - Domain Member Server)
- **PLABWIN10** - (Windows 10 - Domain Member Workstation)

Task 1 - Configure the Windows 10 DHCP Client

In this task, you will verify whether a DHCP client can obtain an IP address lease and examine the IP address lease on the DHCP server.

Step 1

Connect to **PLABWIN10**.

On the **Taskbar** in the **Notification** area on the right, right-click on the **Network** icon and select **Open Network & Internet settings**.




Figure 3.1 Screenshot of PLABWIN10: Displaying right-clicking on the Network icon and selecting Open Network & Internet settings.

Step 2

In the **Settings - Status** pane, click on the **Properties** button for **Ethernet 2**.




Figure 3.2 Screenshot of PLABWIN10: Displaying the Settings - Status pane and selecting the Properties for Ethernet 2.

Step 3

In the **Settings - practicelabs.com** window, click **Edit** under **IP settings**.




Figure 3.3 Screenshot of PLABWIN10: Displaying clicking Edit in the Settings - practicelabs.com window.

Step 4

In the **Edit IP settings** pop-up window, confirm that Ethernet 2 has **Automatic (DHCP)** configured.

Click **Cancel**.




Figure 3.4 Screenshot of PLABWIN10: Displaying clicking Cancel in the Edit IP settings pop-up window.

Step 5

Close the **Settings** window.




Figure 3.5 Screenshot of PLABWIN10: Displaying closing the Settings window.

Step 6

Click the **Start** charm and type the following:

```
cmd
```

Select **Command Prompt** from the **Best match** pop-up menu.





Figure 3.6 Screenshot of PLABWIN10: Displaying selecting Command Prompt from the Best match pop-up menu.

Step 7

In the **Command Prompt** window, type the following and press **Enter**:

```
ipconfig
```

Observe the properties of the **Ethernet adapter Ethernet 2**.



```
PLABWIN10 - Work - Microsoft Edge
https://stg.practice-labs.com/device-advanced.aspx?client=html&device=2&width=1024&height=768&login=true&token=Mc1jsdN54LFPHUt50CKnc...

Select Administrator: Command Prompt
C:\Users\Administrator>ipconfig

Windows IP Configuration

Ethernet adapter vEthernet (Default Switch):

    Connection-specific DNS Suffix  . : 
    Link-local IPv6 Address . . . . . : fe80::5197:db24:9ae0:6cf%18
    IPv4 Address. . . . . : 172.17.96.1
    Subnet Mask . . . . . : 255.255.240.0
    Default Gateway . . . . . : 

Ethernet adapter Ethernet:

    Connection-specific DNS Suffix  . : 
    IPv4 Address. . . . . : 192.168.0.3
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.0.250

Ethernet adapter Ethernet 2:

    Connection-specific DNS Suffix  . : practicelabs.com
    Link-local IPv6 Address . . . . . : fe80::7521:8dc7:4e7f:f9bf%11
    IPv4 Address. . . . . : 192.168.0.6
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.0.250

C:\Users\Administrator>
```

Figure 3.7 Screenshot of PLABWIN10: Displaying the output of the ip config command in the Command Prompt window.

Note: The IP address that was obtained by PLABWIN10 was the first available IP address in the Production Scope configured in the previous exercise on PLABDM01.

Step 8

Connect to **PLABDM01**.

Restore the **Server Manager** window from the **Taskbar**.




Figure 3.8 Screenshot of PLABDM01: Displaying restoring the Server Manager window from the Taskbar.

Step 9

In the **Server Manager** window, access the **Tools** menu and select **DHCP**.




Figure 3.9 Screenshot of PLABDM01: Displaying the Server Manager window and selecting DHCP from the Tools menu.

Step 10

In the **DHCP** console, expand **plabdm01.practicelabs.com > IPv4 > Scope [192.168.0.0] Production Scope**.

Select **Address Leases**.




Figure 3.10 Screenshot of PLABDM01: Displaying the DHCP window and selecting Address Leases on the left pane.

Step 11

In the **DHCP** console, under **Client IP Address**, confirm that PLABWIN10 has obtained an IP address lease from PLABDM01.




Figure 3.11 Screenshot of PLABDM01: Displaying the DHCP window and confirming that PLABWIN10 has obtained an IP address lease from PLABDM01.

Step 12

Close the **DHCP** window.




Figure 3.12 Screenshot of PLABDM01: Displaying closing the DHCP window.

Keep all devices that you have powered on in their current state and proceed to the review section.

Review

Well done, you have completed the **Installing and Configuring Server Roles and Features** Practice Lab.

Summary

You completed the following exercises:

- Exercise 1 - Identify Server Roles
- Exercise 2 - Install and Configure a Server Role
- Exercise 3 - Implement and Configure a DHCP Client

You should now be able to:

- Examine the Active Directory Domain Services Role on a Windows Server Operating System
- Examine the DNS Server Role in a Windows Server Operating System
- Install the DHCP Role on a Windows Server Operating System
- Configure the DHCP Server Role on a Windows Server Operating System
- Configure the Windows 10 DHCP Client

Feedback

Shutdown all virtual machines used in this lab. Alternatively, you can log out of the lab platform.