# documentation dns dynamique

```
apt install bind9 bind9utils bind9-doc ssh -y apt install isc-dhcp-server ssh -y apt update && apt upgrade -y
```

## partie dns:

```
GNU nano 7.2 /etc/hosts
127.0.0.1 dns.mondomaine.local dns localhost
127.0.1.1 dns
```

#### /etc/default/named

```
# run resolvconf?

RESOLVCONF=no

# startup options for the server

OPTIONS="-u bind -4"
```

```
pour le ddns on utilise la cle de bases de bind "rndc.key"
    root@dns:/etc/bind# ls
    bind.keys db.127 db.empty named.conf named.conf.local rndc.key
    db.0 db.255 db.local named.conf.default-zones named.conf.options zones.rfc1918

    rndc.key
    exemple du ficher:
    root@dns:/etc/bind# cat rndc.key
    key "rndc-key" {
        algorithm hmac-sha256;
        secret "wRz1h4HekMmsrZNDsRSjL48R4lYU9dMCviMEigc8B8M=";
};
```

dans named.conf.local( pas grand choses a par si besoin)

```
GNU nano 7.2
                                      named.conf.options
options {
      directory "/var/cache/bind";
      // If there is a firewall between you and nameservers you want
      // to talk to, you may need to fix the firewall to allow multiple
      // ports to talk. See http://www.kb.cert.org/vuls/id/800113
      // If your ISP provided one or more IP addresses for stable
      // nameservers, you probably want to use them as forwarders.
      // Uncomment the following block, and insert the addresses replacing
      // the all-0's placeholder.
      // forwarders {
      //
             0.0.0.0;
      // };
      //-----
      // If BIND logs error messages about the root key being expired,
      // you will need to update your keys. See https://www.isc.org/bind-keys
      //-----
      dnssec-validation no;
      // listen-on-v6 { any; };
};
```

```
GNU nano 7.2
                                               named.conf.local
//
// Do any local configuration here
//
// Consider adding the 1918 zones here, if they are not used in your
// organization
//include "/etc/bind/zones.rfc1918";
include "/etc/bind/rndc.key";
zone "mondomaine.local" {
        type master;
        file "/var/lib/bind/zones/db.mondomaine.local";
        update-policy {
                grant rndc-key zonesub A TXT DHCID;
        };
};
zone "0.16.172.in-addr.arpa" {
        type master;
        file "/var/lib/bind/zones/db.172.16.0";
        update-policy {
                grant rndc-key zonesub PTR TXT DHCID;
        };
};
```

```
les droit sur le fichier zones à créer

root@dns:/etc/bind# cd /var/lib/bind/
root@dns:/var/lib/bind# ls -l
total 4
drwxrwxr-x 2 root bind 4096 26 déc. 14:51 zones
root@dns:/var/lib/bind#

puis créer
db.mondomaine.local db.172.16.0
```

#### exemple de db.mondomaine.local

```
GNU nano 7.2
                                             db.mondomaine.local
; BIND reverse data file for empty rfc1918 zone
; DO NOT EDIT THIS FILE - it is used for multiple zones.
; Instead, copy it, edit named.conf, and use that copy.
$TTL
        86400
                        dns.mondomaine.local. root.mondomaine.local. (
        ΙN
                SOA
                              1
                                        ; Serial
                                        ; Refresh
                         604800
                          86400
                                        ; Retry
                        2419200
                                        ; Expire
                                        ; Negative Cache TTL
                          86400 )
                        dns.mondomaine.local.
        ΙN
                NS
dns
        ΙN
                        172.16.0.1
                Α
                        172.16.0.2
dhcp
        ΙN
                Α
```

```
GNU nano 7.2
                                                  db.172.16.0
BIND reverse data file for empty rfc1918 zone
; DO NOT EDIT THIS FILE - it is used for multiple zones.
; Instead, copy it, edit named.conf, and use that copy.
$TTL
        86400
                        dns.mondomaine.local. root.mondomaine.local. (
        ΙN
                SOA
                                         ; Serial
                                        ; Refresh
                         604800
                                         ; Retry
                          86400
                                         ; Expire
                        2419200
                                         ; Negative Cache TTL
                          86400 )
;
                        dns.mondomaine.local.
                NS
@
        ΙN
                        dns.mondomaine.local.
1
        ΙN
                PTR
                        dhcp.mondomaine.local.
2
        ΙN
                PTR
```

#### dans resolv.conf

```
# Generated by NetworkManager
nameserver 127.0.0.1
search mondomaine.local
```

et scp -r rndc.key root@addresse\_dhcp:/etc/dhcp

### partie dhcp:

```
GNU nano 7.2 /etc/hosts
127.0.0.1 dhcp.mondomaine.local dhcp localhost
127.0.1.1 dhcp
```

#### dans /etc/default/isc-dhcp-server

```
/etc/default/isc-dhcp-server
  GNU nano 7.2
# Defaults for isc-dhcp-server (sourced by /etc/init.d/isc-dhcp-server)
# Path to dhcpd's config file (default: /etc/dhcp/dhcpd.conf).
#DHCPDv4_CONF=/etc/dhcp/dhcpd.conf
#DHCPDv6_CONF=/etc/dhcp/dhcpd6.conf
# Path to dhcpd's PID file (default: /var/run/dhcpd.pid).
#DHCPDv4_PID=/var/run/dhcpd.pid
#DHCPDv6_PID=/var/run/dhcpd6.pid
# Additional options to start dhcpd with.
        Don't use options -cf or -pf here; use DHCPD_CONF/ DHCPD_PID instead
#OPTIONS=""
# On what interfaces should the DHCP server (dhcpd) serve DHCP requests?
        Separate multiple interfaces with spaces, e.g. "eth0 eth1".
INTERFACESv4="ens33"
INTERFACESv6=""
```

les droit des fichiers(normalement la cle va se retrouver dans le ddns-key a revoir)

```
root@dhcp:/etc/dhcp# ls -1
total 28
drwxr-x--- 2 root root 4096 26 déc. 13:34 ddns-keys
-rw-r--r-- 1 root root 1426 23 févr. 2022 debug
-rw-r--r-- 1 root root 1735 23 févr. 2022 dhclient.conf
drwxr-xr-x 2 root root 4096 3 déc. 18:23 dhclient-enter-hooks.d
drwxr-xr-x 2 root root 4096 3 déc. 18:31 dhclient-exit-hooks.d
-rw-r--r-- 1 root root 3331 17 avril 2023 dhcpd6.conf
-rw-r--r-- 1 root root 3824 26 déc. 13:57 dhcpd.conf
root@dhcp:/etc/dhcp# ls -1 ddns-keys/
total 4
-rw------ 1 root root 100 26 déc. 12:27 rndc.key
root@dhcp:/etc/dhcp#
```

### dans dhcpd.conf

```
# option definitions common to all suppo:
option domain-name "mondomaine.local";
option domain-name-servers 172.16.0.1;
default-lease-time 600;
max-lease-time 7200;
```

```
ddns-update-style standard;
ddns-domainname "mondomaine.local.";
ddns-rev-domainname "in-addr.arpa.";
allow client-updates;
update-optization;
update-conflict-detection off;
include "/etc/dhcp/ddns-keys/rndc.key";
zone mondomaine.local. {
        primary 172.16.0.1;
        key rndc-key;
zone 0.16.172.in-addr.arpa. {
        primary 172.16.0.1;
        key rndc-key;
```

```
subnet 172.16.0.0 netmask 255.255.255.0 {
   range 172.16.0.10 172.16.0.30;
# option domain-name-servers ns1.internal.
# option domain-name "internal.example.org
# option routers 10.5.5.1;
# option broadcast-address 10.5.5.31;
# default-lease-time 600;
# max-lease-time 7200;
}
```

relancer les deux et vérifier les log