第 0019 讲 5 内存管理 2 个调优参数

The Linux

内存管理--2 个调优参数分析

根据 Linux 内核内存管理模块所提供的常用调优参数,所支持内存管理调优

参数在/proc/sys/vm 目录《具体如下:

```
M.LinuxH.
vico@ubuntu:/proc/sys/vm$ ls
admin_reserve_kbytes
block_dump
                                                                                                             mmap_rnd_bits
mmap_rnd_compat_bits
nr_hugepages
nr_hugepages_mempolicy
nr_overcommit_hugepages
block_dump
compact_memory
compact_unevictable_allowed
dirty_background_bytes
dirty_bytes
dirty_exptice_centisecs
                                                                                                            nr_overcommit_hugepages
numa_stat
numa_stat
numa_zonelist_order
oom_dump_tasks
oom_kill_allocating_task
overcommit_kbytes
overcommit_remory
overcommit_ratio
page-cluster
panic_on_oom
percpu_pagelist_fraction
stat_interval
swappiness
           ty_ratio
tytime_expire_seconds
ty_writeback_centisecs
     rop_caches
ktfrag_threshold
ugetlb_shm_group
   aptop_mode
egacy_va_layout
owmem_reserve_ratio
      x_map_count
mory_failure_early_kill
mory_failure_recovery
                                                                                                             swappiness
unprivileged_userfaultfd
user_reserve_kbytes
vfs_cache_pressure
watermark_boost_factor
watermark_scale_factor
zone_reclaim_mode
memory_fature_recovery
min_free_kbytes
min_slab_ratio
min_unmapped_ratio
mmap_min_addr
vico@ubuntu:/proc/sys/vm$
```

一、内存管理区水位调优参数 min_free_kbytes

每个 min_free_kbytes 的数值会影响内存管理区的水位操作,具体操作对

应内核源码函数设计如下

```
static void __setup_per_zone_wmarks(void)
          unsigned long pages_min = min_free_kbytes >> (PAGE_SHIFT - 10);
          unsigned long lowmem_pages = 0;
          struct zone *zone;
          unsigned long flags;
7479
          /* Calculate total number of !ZONE_HIGHMEM pages */
          for_each_zone(zone) {
              if (!is_highmem(zone))
                 lowmem_pages += zone_managed_pages(zone);
7484
```

二、页面分配参数 lowmem_reserve_ratio

我们通过终端查看/proc/zoneinfo 节点来获得每个内存管理区中的核心参

THE REAL PROPERTY OF THE PARTY OF THE PARTY

数(高水位、低水位等)。//

具体操作对应内核源码函数设计如下:

```
root@ubuntu:/
File Edit View Search Terminal Help

root@ubuntu:/# cat /proc/zoneinfo
Node 0, zone DMA

per-node stats
    nr_inactive_anon 1612
    nr_active_anon 206498
    nr_inactive_file 95382
    nr_active_file 86260

root@ubuntu:/

File Edit View Search Terminal Help
Node 0, zone DMA32
    pages free 765443
    min 3128
    low 3910
    high 4692
    spanned 1044480
    present 782288
    managed 765904
    protection: (0, 0, 12964, 12964, 12964)
    nr_free_pages 765443
    nr_zone_inactive_anon 0
```

```
root@ubuntu:/

File Edit View Search Terminal Help

Node 0, zone Normal

pages free 2804770
min 13750
low 17187
high 20624
spanned 3407872
present 3407872
managed 3320750
```

spanned 3407872
present 3407872
managed 3320750
protection: (0, 0, 0, 0, 0)

```
Node 0, zone Movable

pages free 0

nin 0

low 0

high 0

spanned 0

protection: (0, 0, 0, 0, 0)

Node 0, zone Device

pages free 0

nin 0

low 0

high 0

spanned 0

present 0

managed 0

protection: (0, 0, 0, 0, 0)
```

通过对 lowmem_reserve[]数组的单位为页面,通过对它的设备来防止页面

分配器过度从低端内存管理区域分配内存。

影响页面回收参数:

- swappiness: 主要用于控制 kswapd 内核线程把页面写入交换区的活跃程序,此参数值的设置为 0--100 ,此参数默认设置为 60。
- zone_reclaim_mode: 当页面分配器在一个内存管理区分配失败, zone_reclaim_mode 为 0,表示可以从下一个内存管理区或者下一个内存节点分配内存; 否则表示可以在这个内存管理区中进行回收内存。
- watermark_boost_factor: 主要用于优化内存外碎片化。它临时提高内存管理区的水位,即 zone->watermark_boost。提高内存管理区的水平,kswapd 可以回收更多的内存。
- watermark_scale_factor: 除刚才讲的 min_free_kbytes 以外,watermark_scale_factor 此参数也会影响每个内存管理区的低水位和高水位。通过__setup_per_zone_wmarks 函数将 watermark_scale_factor 参数值默认设置为 10,分母为 10000。watermark_scale_factor 参数最大值为 1000。

有时间大家可以查看一下官方文档(影响脏页回写的参数: dirty_background_ratio、dirty_bytes 等等)。

1、Linux内核在系统初始化是通过函数来计算min_free_kbytes值的大小,然后计算每个内存管理区的水位, 具体计算公式如下:

```
min_free_kbytes=4_lowmem_kbytes
```

lowmem_keytes此变量是系统中所有内存管理区的管理页面数量减少高水位页面数量的总和。最后计算出来的min free kbytes有范围孤帆,最小值为128KB,最大值为64MB。

内存管理区的3个水位计算与min_free_kbytes有关。当系统只有一个内存管理区时,最低警戒水位等于min_free_kbytes,低水位、高水位与watermark_scale_factor参数、内存管理区管理的内存大小managed_pages有关。waterwark_boost表示临时提高的水位。