Chapter 5:: The 2nd law of thermodynamics

Jerry Wu

March 15, 2023

Entropy

Abstract

Entropy is a measure of the degree of disorder/randomness in an arbitrary system. We can use this concept to discuss matters such as spontaneous and non spontaneous processes.

Spontaneous & non spontaneous processes

A spontaneous change is one that occurs without a continuous input of energy from an outside system. A good example would be gravitational potential. We can increase the rate of a spontaneous process by introducing a catalyst to the system. A spontaneous process is not always fast.

Non spontaneous processes aren't impossible, but they require input of external energy or a **more spontaneous** reaction to proceed.

Example

A good example of an impossible spontaneous process is a ball starting to bounce on a surface spontaneously. This would require all particles under it (approx 6.02E23 particles) to start vibrating in the same direction at the same time. The chance of this being possible is basically 0.

Estimating spontaneity

The first law of thermodynamics accounts for energy in a system, but it does not predict the spontaneity of the energy transfer involved. We will use entropy to do this. A process is spontaneous if and only if $\Delta S > 0$.

Entropy as a state function

Entropy is a measure of how dispersed the energy of a system is (in units of $\frac{J}{K}$). We can start with this property::

$$\Delta S_{\Omega} = \Delta S_{\sigma} + \Delta S_{\bar{\sigma}}$$

Where Ω is the universe, σ is an arbitrary system, and $\bar{\sigma}$ is the surroundings. To calculate the absolute entropy of a system, the following formula is used::

$$S = k_b \ln(W) \implies \Delta S = k_b (\ln(W_0) - \ln(W_1))$$

Where $k_b = 1.38E - 23\frac{J}{K}$ is the boltzman constant, and $W = 2^n$ is the number of possible arrangements of position and energy of all molecules in the system (microstates) for $n \in \mathbb{N}$ particles. The macrostate with the **highest entropy** also has the **greatest dispersal of energy**.

Multiplicity of energy

Assume we have a hypothetical solid system with four atoms and a total energy of E. How many ways can we distribute that energy among the 4 atoms? Clearly there are 4 ways to distribute 1 unit of energy among 4 atoms because the system is small. However, if there are N atoms, and total energy is qE, then the number of microstates is modelled by the following formula::

$$W(N,q) = \frac{(q+N-1)!}{q!(N-1)!}$$

Bringing it all together

A hot and a cold bar, each made up of 4 atoms, are pushed together. What will happen? If the cold bar has 1 quantum of energy and the hot bar has 5 quanta of energy in the initial state, show that heat transfer is spontaneous by calculating ΔS_{Ω} for the process.

We can start by calculating the combinations of microstates for each process.

Entropy at the molecular level

In any system, when T increases, S will also increase proportionally with it. This makes sense because the faster the particles move, the more disorder there is in the system overall.

Statistical definition of entropy

We can model the change in entropy of a system between two states with the following formula::

$$\Delta S = S_2 - S_1 = k_b \ln(\frac{W_2}{W_1})$$

This is possible since entropy is a state function.

Entropy change due to mixing of ideal gases

Assume that mixing two ideal gases will sum up their entropies::

$$\Delta S_{mix} = \Delta S_A + \Delta S_B = n_A R \ln \left(\frac{V_A + V_B}{V_A} \right) + n_B R \ln \left(\frac{V_A + V_B}{V_B} \right)$$

By Avogadro's law, $T \equiv const \wedge P \equiv const \implies V \propto n$, so,

$$\Delta S_{mix} = n_A R \ln \left(\frac{n_A + n_B}{n_A} \right) + n_B R \ln \left(\frac{n_A + n_B}{n_B} \right)$$

Using the laws of logarithms, we have that::

$$\Delta S_{mix} = -n_A R \ln \left(\frac{n_A}{n_A + n_B} \right) - n_B R \ln \left(\frac{n_B}{n_A + n_B} \right)$$

Further simplifying the expression, we get::

$$\Delta S_{mix} = -R(n_A \ln(\chi_A) + n_B \ln(\chi_B))$$

Recall that $\chi_{\xi} < 1 \forall \xi \in U$

Isothermal expansion of an ideal gas

To calculate change in entropy for a process like this, we use::

$$\Delta S = nR \ln(\frac{V_2}{V_1})$$

Heat absorbed by the expansion is given by::

$$q_{rev} = nRT \ln \left(\frac{V_2}{V_1}\right)$$

So we have that::

$$\frac{q_{rev}}{T} = nR \ln \left(\frac{V_2}{V_1}\right) \implies \Delta S = \frac{q_{rev}}{T}$$

Example

One mole of N_2 at $20.5^{\circ}C$ and 6.00bar undergoes a transformation to the state described by $145^{\circ}C$ and 2.75bar. Calculate ΔS if

$$C_{P,m}(T) = 30.81 - (11.87E - 3)T + (2.3968E - 5)T^2 - (1.0176E - 8)T^3$$

We can invoke the formula::

$$\Delta S = -nR \ln(\frac{P_2}{P_1}) + n \int_{T_1}^{T_2} \frac{C_{P,m}(T)}{T} dT$$

$$= \int_{293.65}^{418.15} \frac{30.81}{T} - (11.87E - 3) + (2.3968E - 5)T - (1.0176E - 8)T^{2}$$

After integrating each term and some calculations, we have that::

$$6.48 + \left[30.81\ln(T) - (11.87E - 3)T + \frac{2.3969E - 5}{2}T^2 - \frac{1.0176E - 8}{3}T^3\right]_{293.65}^{418.15} \approx 16.8JK^{-1}$$

The 2nd law of thermodynamics

Any system σ is significantly smaller than the surroundings. We can consider the surroundings σ^{-1} is an infinitely large reservoir. Thus, we can say::

$$dq_{surr,rev} = dq_{surr,irrev} = dq_{surr}$$

Since entropy is a state function, we can express change in entropy in the surroundings as the ratio::

$$\Delta S_{surr} = \frac{q_{surr}}{T_{surr}}$$

Consider the isothermal expansion of an ideal gas. Heat absorbed by the system is just $q_{sys} = nRT \ln \left(\frac{V_2}{V_1} \right) \implies q_{surr} = -nRT \ln \left(\frac{V_2}{V_1} \right)$. So for a **reversible** process,

$$\Delta S_{\Omega} = nR \ln \left(\frac{V_2}{V_1} \right) + \left[-nR \ln \left(\frac{V_2}{V_1} \right) \right] = 0$$

For an irreversible process (i.e. a gas expanding into a vacuum),

$$\Delta S_{sys} = nR \ln \left(\frac{V_2}{V_1} \right)$$

Cases (IMPORTANT)

- For a reversible process, $\Delta S_{\Omega} = 0$
- For an irreversible process, $\Delta S_{\Omega} > 0$
- Overall, $\Delta S_{\Omega} \geq 0$

Example

One mole of an ideal gas at 25°C is allowed to expand adiabatically and irreversibly from 1L to 10L with no work done. What is the final temperature of the gas? Calculate the values of ΔS_{sys} , ΔS_{surr} and ΔS_{univ} .

We know that $q=0 \wedge w=0 \implies \Delta U=0$ in this system. So we can use the formula to calculate.

$$\Delta S_{sys} = nR \ln \left(\frac{V_2}{V_1} \right)$$

$$\Delta S_{sys} = (8.3145) \ln \left(\frac{10}{1} \right) = 19.1 J K^{-1} mol^{-1}$$

$$q = 0 \implies \Delta S_{surr} = 0 \implies \Delta S_{\Omega} = 19.1 J K^{-1} mol^{-1} \implies R \equiv spont.$$

Entropy change due to phase transitions

- In general, $\Delta_{vap}S^{\circ} > \Delta_{fus}S^{\circ}$ for the same substance.
- Solid to liquid transitions result in relatively small increase in entropy.
- Arrangements of molecules in gaseous state is completely random, implying larger increase in entropy from liquid to gas.

The molar entropy for oxygen gas (O_2) is shown on **slide 52**. We can see that phase changes have a large vertical jump on the entropy axis.

We can model the entropy change of the system during a phase change as the following equation::

$$\Delta S_{sys} = \frac{\Delta H_{trans}}{T_{trans}} \implies \Delta S_{surr} = -\frac{\Delta H_{trans}}{T_{trans}}$$

So at a phase transition, $\Delta S_{\Omega} = 0$

For temperature dependence, we can model entropy change as::

$$\Delta S = n\bar{C}_P \ln \left(\frac{T_2}{T_1}\right)$$

To find total entropy change of water over an interval of temperature with 1 phase change (liquid to gas), we can say::

$$\Delta S_{\Omega} = \sum_{S \in \Omega} \Delta S_i = C_P(H_2O(l)) \ln \left(\frac{T_2}{T_1}\right) + \frac{\Delta H_{trans}}{T_2} + C_P(H_2O(g)) \ln \left(\frac{T_3}{T_2}\right)$$

The 3rd law of thermodynamics

In essence, the entropy of a perfect crystal at 0K is 0. This law gives us the basis in calculating absolute entropies.

Proof

 \exists exactly one microstate at T=0K, so $W=1^{6.02E23}=1$. So $S=k_b\ln(W)=k_b\ln(1)=0$

We can also express heat capacities and entropy of a perfect crystal as the following limits::

$$\lim_{T \to 0} S = 0, \lim_{T \to 0} C_P = 0, \lim_{T \to 0} C_V = 0$$

We have never reached 0K. The world record for lowest temperature is 100pK.

Absolute entropy

Assume that the following holds::

$$q_{rev,P} = C_P dT$$

Therefore at 298K,

$$S_{gas}(T) = S(0K) + \int_{0}^{T_{fus}} \frac{C_{P,sol}}{T} dT + \frac{\Delta H_{fus}}{T_{fus}} + \int_{T_{fus}}^{T_{boil}} \frac{C_{P,liq}}{T} dT + \frac{\Delta H_{vap}}{T_{boil}} + \int_{T_{boil}}^{T_{f}} \frac{C_{P,gas}}{T} dT$$

If not at 298K,

$$\Delta S^{T} = \Delta S_{298.15K} + \int_{298.15}^{T} \frac{n\Delta C_{p}}{T} dT = \Delta S_{298.15K} + nC_{P} \ln \left(\frac{T}{298.15} \right)$$

Entropy changes for chemical reactions

Simply invoke Hess' law for entropy.

$$\Delta S_r = \sum v_p S_p - \sum v_r S_r$$

Example

If a spark is applied to a mixture of $H_2(g)$ and $O_2(g)$, an explosion occurs and water is formed. The gaseous water is cooled to $100^{\circ}C$. Calculate the entropy change when 2mol of gaseous H_2O is formed at $100^{\circ}C$ and 1atm from $H_2(g)$ and $O_2(g)$ at the same temperature and each at a particular pressure of 1atm.

$$R: 2H_2(q) + O_2(q) \to 2H_2O(q)$$

$$\Delta S(25^{\circ}C) = 2\bar{S}_{H_2O(g)} - \bar{S}_{O_2(g)} - 2\bar{S}_{H_2(g)}$$

$$= 2(188.72) - 205.04 - 2(130.57) = -88.74 \frac{J}{K}$$

In order to find ΔS at $100^{\circ}C, 1atm$, we need to know the heat capacities of the reactants and products from the table.

$$\Delta C_P(25^{\circ}C) = 2\bar{C}_P(H_2O(g))\bar{C}_P(O_2(g)) - 2\bar{C}_P(H_2(g))$$

$$= 2(33.6) - 29.4 - 2(28.8) = -19.8 \frac{J}{K}$$

$$\Delta S(100^{\circ}C) = \Delta S(25^{\circ}C) + \int_{298}^{373} \frac{\Delta C_P}{T} dT$$

$$-88.74 \frac{J}{K} - 19.8 \ln\left(\frac{373}{298}\right) = -93.18 \frac{J}{K}$$

The Carnot heat engine

An idealized model of a heat engine which converts heat to mechanical work (car engines, steam engines, etc.). Naturally, it is easier to turn work into heat, rather than heat into work. The reversible Carnot cycle dictates that::

- Isothermal expansion
- Adiabatic expansion
- Isothermal compression
- Adiabatic compression

What is the cause of this asymmetry? Well, we have to consider the following phenomena occurring in this system::

- Entropy increases causing irreversible changes
- Some energy is lost as waste heat

• Amount of work the system can do is limited as a result

We can deduce that, from a PV diagram with 4 points::

- $\Delta U = 0$ since it is a cyclic path
- $q(\psi) = \sum_{q \in \sigma} q_i = q_1 + q_2$

•
$$w(\psi) = -RT_2 \ln \left(\frac{V_2}{V_1}\right) - RT_1 \ln \left(\frac{V_4}{V_3}\right) = -R(T_2 - T_1) \ln \left(\frac{V_2}{V_1}\right)$$

•
$$q_2 = RT_2 \ln \left(\frac{V_2}{V_1}\right), q_1 = RT_1 \ln \left(\frac{V_4}{V_3}\right) = -RT_1 \ln \left(\frac{V_2}{V_1}\right)$$

Efficiency of a heat engine

Efficiency can be expressed by the formula::

$$\epsilon = \frac{\sum_{w \in \sigma} w_i}{q_2} = \frac{R(T_2 - T_1) \ln\left(\frac{V_2}{V_1}\right)}{RT_2 \ln\left(\frac{V_2}{V_1}\right)} = \frac{T_2 - T_1}{T_2} = 1 - \frac{T_{cold}}{T_{hot}}$$

So it would follow that $w_{\psi,irrev} < w_{\psi,rev} \implies \epsilon_{irrev} < \epsilon_{rev} < 1$. This makes sense because actual efficiency is less than ideal carnot efficiency.

Deriving S from efficiency

$$\epsilon = \frac{q_1 + q_2}{q_2} = \frac{T_2 - T_1}{T_2} = \frac{|w|}{q_{in}}$$

$$1 + \frac{q_1}{q_2} - 1 + \frac{T_1}{T_2} = 0$$

$$\frac{q_2}{T_2} + \frac{q_1}{T_1} = 0$$

$$\oint \frac{dq_{rev}}{T}dT = 0 \implies \Delta S = \int \frac{dq_{rev}}{T}dT$$

Note that ΔS must be calculated along a **reversible** path!