


Create a New Publisher


Create a Publisher to deploy on your network and use with a private app. The token generated in this procedure is used to deploy the Publisher, so be sure to make a copy. Auto-Update profiles have been add to the Publisher settings. If you have not yet created an Auto-Update profile, you can choose to use the default profile, or go to [Configure Publisher Auto-Updates](#) to create one.

1. Go to **Settings > Security Cloud Platform > Publishers**.
2. Click **New Publisher**.
3. Enter a Publisher name (like `AWS US-WestWing publisher`), and then select an Auto-Update profile.



The screenshot shows a web form titled "New Publisher". At the top right, there are two buttons: "Save" (blue) and "Save & Generate Token" (light blue), followed by a close icon (X). Below the title, there is a "Name" label and a text input field containing "AWS US-WestWing publisher". Underneath, there is an "Update Profile" label and a dropdown menu with "upgrade" selected. The "Save & Generate Token" button is highlighted with an orange border.

4. Click **Save & Generate Token**.



This screenshot is identical to the previous one, showing the "New Publisher" form. The "Save & Generate Token" button is highlighted with an orange border, indicating the next step in the process.

5. Click **Copy** to get the registration token.

Generate Token

Registration Token

Deploy the publisher in your environment, then copy and paste the token below to your publisher prompt within 24 hours. [View More](#)

(Expires: 05/30/2024, 5:48 PM)

Copy

eyJhbGciOiJSUzI1NiJ9.eyJpc3MiOiJucy02Mjg0LnVzLXN2NS5ucGEuZ29za29wZS5jb20iLCJzdWliOiJiMjc3YTU3YmZiMTQ1Mjc2liwiZXhwIjoxNzE3MTE2NTE0LCJqdGkiOiJiNTA5ZmE4NS00MTk3LTQxNGQ0OTY1Ni1kM2FhMzA1Mjk1NGUifQ.oU
U9xIDyVw2VD3oQDcGeI9ZFe_1IZTQG6dlv9Q6J7KDFIAMB_oj6HitESKvrvinOuM
tMF8DmgT0CdqwN5KjP3wjKTPmT1ACtFLrYqahRXOpnJvTlb2ZyOv4N4iAev3sF
vdFvOkOErewD9b_ykENL8wCKLL5YVgUHT29bwR5Vk8bxzdkDcrBgvFIQUd1Lc5
W97Rf0IQwrFZFajJtiaEXNIOGmpmaiZSWFW-
Sqs3MbGwi5DryMUsO6c8lpCwRGjIDZLbdfw7oBVRFltvyIYbsFhJOdFYFB-
Z0pyunWylkDTzV3vqkWcVMw5ooishjj2VGulRNywVh5pqwIS_tndeUA

Close


6. Click **Done**.

After deploying the Publisher, return to the Publisher page to verify the status is *Connected*.

New Publisher Auto-Update Setting ▾ Export Actions ▾ 159 Publishers Found				
	Publisher ↕	Status	Version ⓘ	CN
☐	TP-test	Not Registered		b275
☐	ty-azure-7170	Disconnected	115.0.0.8634	8ef3l
☐	AWS US-WestWing publisher	Connected	115.0.0.8634	d810t

The Publishers page shows how many Publishers have been created, each Publisher's name, status, version, CN, and number of connected apps. To customize the columns shown on the page, click the gear icon in the table header and check the columns you want to see. To edit the name, delete, or update a Publisher, click the menu icon in the row a Publisher is listed.

You can search for and filter Publishers listed on the page based on search criteria. If a filter has an arrow, you can select predefined search criteria, or search by entering specific criteria. Click **Add Filter** to view and select a predefined filter, or search for a Publisher, Update Profile, and Version.



Configure a Publisher in AWS

The Netskope Publisher allows for zero trust network access to applications and hosts in your public cloud or private data center. This includes the ability to leverage a Publisher in Amazon Web Services.

This section explains how to create a Publisher instance in Amazon Web Services. Knowledge of the Netskope UI and Amazon Web Services are required, along with:

- A Netskope Tenant.
- A copy of your Publisher registration token.
- An Amazon Web Services account.

To access the AMI file from the Publisher page in the Netskope UI, go to **Settings > Security Cloud Platform > Publishers** and click **Publisher AMI**. When deploying a Publisher in AWS China please deploy the AMI

through AWS marketplace in China: [Marketplace: Netskope Private Access Publisher](#)  instead of the link below.

Publishers

Publishers are Netskope software components that are deployed in your virtual network at your public cloud provider (e.g. AWS VPC) or internal network in your private datacenter. Publishers make your private applications available to authorized users and devices. View more instructions at [here](#).

AWS  **Publisher AMI**

VMware ESXi:  **PUBLISHER OVA**

Hyper-V:  **PUBLISHER VHDX**

Perform these steps in the AWS console.

Launch an EC2 Instance

1. Sign in to your Amazon Web Services (AWS) console.
2. Click **Services > Find services**. Search for *EC2* and then select **EC2**.
3. Click **Instances** in the left sidebar menu.
4. Click **Launch Instance**.

Choose an Amazon Machine Image (AMI)

1. Click **AWS Marketplace** in the left sidebar menu.
2. Enter **>Netskope** in the search bar.
3. *Netskope Private Access Publisher* should appear in the search results. Click **Select**.

Choose an Instance Type

1. Select **t3.medium** as the instance type.
2. Click **Next: Configure Instance Details**.

Configure Instance Details

The token you copied from the Netskope UI is needed to complete these steps.

1. Enter **1** in the **Number of instances** field.
2. Select the VPC where the application you want to publish via Netskope is deployed in the **Network** field.

3. Keep the default values for the remaining fields.

Optional (Only outside of China)

1. Click **Advanced Details** to expand this section.
2. In the User data section, select the **As text** option.
3. Enter the Netskope Publisher registration token into the *User Data* text field.

Add a Name Tag

Adding a name tag is optional, but doing so will make it easier to identify your Netskope Publisher EC2 instance.

1. Click the **Add Tags** tab, near the top of the page.
2. Click **Add Tag**.
3. Enter **Name** in the Key field.
4. Enter **AWS US-WestWing publisher** in the Value field.
5. Click **Review and Launch**.

Review Instance Launch

1. Review the information in the AMI Details Instance Type sections.
2. Click **Launch**.
3. Select or create a key pair. This key pair is used to ssh in to the Publisher VM. Password-based authentication is by default disabled on the AWS publishers.
4. Click **Launch Instances**.
5. Review the information on the Launch Status page.
6. Click **View Instances**.

View Instances

1. You should now see a new EC2 instance with the name **AWS US-WestWing publisher** (if you completed the *Add a Name Tag* steps).
2. AWS typically takes several minutes to launch EC2 instance and run status checks. Wait until your **Instance State** is Running and **Status Checks** have passed.

Register the Publisher

Note

Registering the Publisher is optional and only required if the Publisher token was not provided during the initial Publisher instance deployment, or when deploying a Publisher within AWS China.

SSH into the publisher (default username: `ubuntu`, default password: `ubuntu`). When prompted, change your password. After you change it, the system auto-disconnects your SSH session, so you will need to reconnect and log in with their new password before proceeding.

1. SSH into the Publisher (default username: `ubuntu`, default password: `ubuntu`).

Note

In the event of a password change, the new password must meet the following minimum requirements:

- Minimum password length must be 14 characters.
- Must contain one upper case letter.
- Must contain one lower case letter.
- Must contain one digit (number).
- Must contain one non-alphanumeric character. Cannot be a palindrome.

Note

For Publishers on AWS China: First proceed to the next [section](#) and do not register the publisher.

2. When prompted for a menu choice, select **Register**.
3. When requested, enter the Netskope registration token, and then click **Enter**. You can also enter the token with this command: `sudo ./npa_publisher_wizard -token <TOKEN>`.
4. Go to **Settings > Security Cloud Platform > Publishers** in your Netskope tenant and confirm your Publisher has a *Connected* status. If not, go to [Publisher Logs for Troubleshooting](#).

Additional Steps before Registration in AWS China

Perform the following steps on the Publisher VM in AWS China before registering the Publisher. These steps prepare the environment for registration and ensure downloads use China-accessible mirrors.

1. Exit the Publisher Wizard: When the wizard menu appears, select **7. Exit** to return to the shell prompt.
2. Install `curl` : Update package metadata and install `curl` :

```
sudo apt update && sudo apt install -y curl
```

3. Download the setup/upgrade helper script: Use `curl` to download the latest China setup script to your home directory:

```
curl https://npa-ova.oss-cn-shenzhen.aliyuncs.com/publisher.netskope.com/latest/generic/setup_and_upgrade_china_publisher.py > ~/setup_and_upgrade_china_publisher.py
```

4. Verify the script integrity (SHA-256): Calculate the SHA-256 checksum and confirm it matches the expected value:

```
shasum -a 256 setup_and_upgrade_china_publisher.py
```

Expected output (hash should match exactly):

```
2645a1d6c5bbb83fa8dc794d6bade10167d8b241463d62edc6c53eb8f3bb72f5  
setup_and_upgrade_china_publisher.py
```

 Note

If the checksum does not match, **do not run the script**. Redownload the file and verify again. Run the setup/upgrade script.

5. Execute the script to configure prerequisites and optimize mirrors for Mainland China.

```
sudo python3 setup_and_upgrade_china_publisher.py
```

 Note

The script may update packages and repositories. Allow it to complete without interruption.

6. Confirm Docker APT mirror is set to `Aliyun` : Validate that the Docker repository points to the `Aliyun` mirror instead of `download.docker.com` :

```
sudo cat /etc/apt/sources.list.d/archive_uri-  
https_download_docker_com_linux_ubuntu-jammy.list
```

Expected content:

```
deb [arch=amd64] http://mirrors.aliyun.com/docker-ce/linux/ubuntu jammy  
stable  
# deb-src [arch=amd64] http://mirrors.aliyun.com/docker-ce/linux/ubuntu  
jammy stable
```

If needed, update the file so that `https://download.docker.com/linux/ubuntu` is replaced with `http://mirrors.aliyun.com/docker-ce/linux/ubuntu` , and then run `sudo apt update` .

7. Validate required resource files: Ensure the following files are present (created by the setup/upgrade script):

```
ls -l /home/ubuntu/resources/npa-publisher-public.pem  
ls -l /home/ubuntu/resources/.prc_dp
```

 Note

If either file is missing, rerun the setup script from step 5.

8. Register the Publisher: Start the wizard and complete registration with your Publisher token:

```
sudo ./npa_publisher_wizard -token <TOKEN>
```


9. Upgrade the Publisher via the wizard: After registration has been completed, upgrade to the latest Publisher software version. Select **1. Upgrade** and follow the prompts.

Configure a Publisher in Azure

The Netskope Publisher allows for zero trust network access to applications and hosts in your public cloud or private data center. This includes the ability to leverage a Publisher in Azure.

This topic explains how to create a Publisher instance in Azure. Knowledge of the Netskope UI and Azure are required, along with:

- A Netskope Tenant
- A copy of your Publisher registration token
- An Azure account.

Note

Azure Publishers require 30GB HDD instead of the standard 8GB.

Perform these steps in the Azure console.

Create a Virtual Machine (VM)

1. Go to Azure Marketplace and search for **Netskope Private Access Publisher**.
2. Click **Create**.
3. Select **Netskope Private Access Publisher** from the drop-down menu.
4. Click **Basics**.
5. Select or edit the Resource group and virtual machine, if required.
6. While creating the VM, the Username field automatically adds `azureuser` by default. You must change the Username to `ubuntu`, and only use `ubuntu` to ensure a successful login to the virtual machine. Only the username `ubuntu` can be used to log in.

Size * ⓘ Standard_D2s_v3 - 2 vcpus, 8 GiB memory (\$76.65/month) ▼
[See all sizes](#)

Enable Hibernation ⓘ ☐
 ⓘ Hibernation is not supported by the image and size that you have selected. Choose an image and size that is compatible with Hibernation to enable this feature.
[Learn more](#) ⓘ

Administrator account

Authentication type ⓘ ☒ SSH public key ☐ Password

ⓘ Azure now automatically generates an SSH key pair for you and allows you to store it for future use. It is a fast, simple, and secure way to connect to your virtual machine.

Username * ⓘ ubuntu ✓

SSH public key source Generate new key pair ▼

SSH Key Type ☒ RSA SSH Format ☐ Ed25519 SSH Format
 ⓘ Ed25519 provides a fixed security level of no more than 128 bits for 256-bit key, while RSA could offer better security with keys longer than 3072 bits.

Key pair name * myVm_key ✓

Inbound port rules

Select which virtual machine network ports are accessible from the public internet. You can specify more limited or granular network access on the Networking tab.

Public inbound ports * ⓘ ☐ None ☒ Allow selected ports

Select inbound ports * SSH (22) ▼

7. Copy and paste your public SSH key under SSH public key. If you do not have a public SSH key, select **Generate new key pair**. This key pair is used to ssh in to the Publisher VM. Password-based authentication is by default disabled on the Azure publishers.
8. Select **SSH** from the **Select public inbound ports** dropdown menu.
9. Click **Next:Disks**.
10. Customize according to the desired disk settings or use the default settings.
11. Click **Next: Networking**.
12. Review your networking settings.
13. Select **SSH** from the **Select public inbound ports** dropdown menu.

14. Click **Review + Create** and analyze the virtual machine settings.
15. Click **Create**.
16. Wait until the deployment completes.

Open an SSH Session

1. Click **Virtual machines**.
2. Select the newly created VM.
3. Find a public IP address.
4. On your computer terminal execute: `ssh -i <your_private_ssh.key> ubuntu@<ipaddress>`.

Register the Publisher

Note

Registering the Publisher is optional and only required if the Publisher token was not provided during the initial Publisher instance deployment.

SSH into the publisher (default username: `ubuntu`, default password: `ubuntu`). When prompted, change your password. After you change it, the system auto-disconnects your SSH session, so you will need to reconnect and log in with their new password before proceeding.

1. SSH into the Publisher (default username: `ubuntu` , default password: `ubuntu`).

 Note

In the event of a password change, the new password must meet the following minimum requirements:

- Minimum password length must be 14 characters.
- Must contain one upper case letter.
- Must contain one lower case letter.
- Must contain one digit (number).
- Must contain one non-alphanumeric character.
- Cannot be a palindrome.

2. When prompted for a menu choice, select **Register**.

3. When requested, enter the Netskope registration token, and then click **Enter**. You can also enter the token with this command: `sudo ./npa_publisher_wizard -token <TOKEN> .`

4. Go to **Settings > Security Cloud Platform > Publishers** in your Netskope tenant and confirm your Publisher has a *Connected* status. If not, go to [Publisher Logs for Troubleshooting](#).

Configure a Publisher in GCP

The Netskope Publisher allows for zero trust network access to applications and hosts in your public cloud or private data center. This includes the ability to leverage a Publisher in Google Cloud Platform.

This topic explains how to create a Publisher instance in Google Cloud Platform Storage. Knowledge of the Netskope UI and Google Cloud Platform are required, along with:

- A Netskope Tenant
- A copy of your Publisher registration token

- A Google Cloud Platform account with a working VPC setup and API permissions.

! Important


Ensure your `/tmp` folder has a `777` permission for successful Publisher deployments and OS updates.

Perform these steps in the Google Cloud Platform console.

1. Log in to Google Cloud Platform at <https://console.cloud.google.com/>



2. Click the menu icon in the top left and select **Compute Engine** and then **VM instances**.



3. Click **Create Instance**.

M instances

CREATE INSTANCE

4. Enter a name for the instance, like `netskope-publisher`.

Name ?

Name is permanent

netskope-publisher

5. Select a Region and Zone. For testing purposes this can be anything. In a production environment, you want to enter the region and zone where the applications reside.

Region ?

Region is permanent

us-east1 (South Carolina)

Zone ?

Zone is permanent

us-east1-b

6. Configure the instance memory and CPU settings (2 core, 4 GB memory is the recommended setting, but for testing purposes a smaller machine will work).

Machine configuration

Machine family

General-purpose

Memory-optimized

Compute-optimized

Machine types for common workloads, optimized for cost and flexibility

Series

E2

CPU platform selection based on availability

Machine type

e2-medium (2 vCPU, 4 GB memory)

vCPU

1 shared core

Memory

4 GB

7. Click **Change** under Boot disk.

© Netskope Inc 2026

Page 14 of 43



8. Select **Ubuntu** as the Operating System and **Ubuntu 22.04 LTS** as the Version. Leave the Boot disk type and Size as the defaults.

Boot disk

Select an image or snapshot to create a boot disk; or attach an existing disk. Can't find what you're looking for? Explore hundreds of VM solutions in [Marketplace](#)

PUBLIC IMAGES CUSTOM IMAGES SNAPSHOTS EXISTING DISKS


Operating system
Ubuntu

Version *
Ubuntu 22.04 LTS
amd64 focal image built on 2022-04-04, supports Shielded VM features

Boot disk type *
Standard persistent disk

Size (GB) *
20

9. Click **Select**.



Note: Steps 10-13 are optional if no other route to the internet is available.

10. Click **Management, security, disks, networking, sole tenancy**

Firewall 

Add tags and firewall rules to allow specific network traffic from the Internet

☐ Allow HTTP traffic

☐ Allow HTTPS traffic

Management, security, disks, networking, sole tenancy

The following options have been customized:

Network interfaces

Your free trial credit will be used for this VM instance. [GCP Free Tier](#) 

Create Cancel

Equivalent [REST](#) or [command line](#)

11. Click **Networking**.

☐ Allow HTTPS traffic

Management Security Disks **Networking** Sole Tenancy

Description (Optional)

Deletion protection

☐ Enable deletion protection

When deletion protection is enabled, instance cannot be deleted. [Learn more](#)

12. Click the pencil icon to edit the network interface.

 npa-vpc 

13. Select your Network, Subnetwork, and specify an **Ephemeral** external IP.

16. In the SSH session, enter your home directory `/home/$USERNAME` through command `cd` .



Important

For deployments based on Ubuntu 22.04, GCP has an updated guest environment that might require manual DNS changes. Validate this for your environment before proceeding; refer to [Manually Configure Custom DNS on GCP](#).

17. Due to Google Cloud Platform's (GCP) network infrastructure, which uses a default MTU (Maximum Transmission Unit) of 1460, we advise customers to run the Netskope Publisher in a specific mode called *No NAT*.

In this mode, traffic is proxied directly from the egress network interface instead of applying Source NAT (SNAT). This approach avoids potential packet fragmentation problems that can occur from the interaction between Linux's *masquerade* and *conntrack* modules.

To enable No NAT mode on a new or existing Publisher installation, follow these steps:

- a. Ensure you are logged in with the normal user account that will be used to deploy or manage the Publisher (do not use the root user).
- b. Create the resources directory in your user's home directory, if it doesn't already exist:

```
mkdir -p ~/resources
```

- c. Create the empty `.nonat` file inside that directory. The presence of this file is what activates the mode.

```
touch ~/resources/.nonat
```

After creating the file, continue to step 18 or (re)start the Netskope Publisher service. It will automatically detect the `.nonat` file and enable the feature.

18. Run the following command under the home directory to download and install the necessary components for the Publisher. This may take about 10 minutes.

```
curl https://s3-us-west-2.amazonaws.com/publisher.netskope.com/latest/generic/bootstrap.sh | sudo bash; sudo su - $USER; exit
```

19. At the end of this process, you have a fully functional Netskope Publisher and can register it with Netskope.

Register the Publisher

SSH into the publisher (default username: `ubuntu`, default password: `ubuntu`). When prompted, change your password. After you change it, the system auto-disconnects your SSH session, so you will need to reconnect and log in with their new password before proceeding.

1. SSH into the Publisher (default username: `ubuntu`, default password: `ubuntu`).

Note

In the event of a password change, the new password must meet the following minimum requirements:

- Minimum password length must be 14 characters.
- Must contain one upper case letter.
- Must contain one lower case letter.
- Must contain one digit (number).
- Must contain one non-alphanumeric character.
- Cannot be a palindrome.

2. When prompted for a menu choice, select **Register**.
3. When requested, enter the Netskope registration token, and then click **Enter**. You can also enter the token with this command: `sudo ./npa_publisher_wizard -token <TOKEN>`.
4. Go to **Settings > Security Cloud Platform > Publishers** in your Netskope tenant and confirm your Publisher has a *Connected* status. If not, go to [Publisher Logs for Troubleshooting](#).

Configure a Publisher in VMWare ESXi

The Netskope Publisher allows for zero trust network access to applications and hosts in your public cloud or private data center. This includes the ability to leverage a Publisher in VMWare ESXi.

This topic explains how to create a Publisher instance in VMWare ESXi. Knowledge of the Netskope UI and VMWare ESXi are required, along with:

- A Netskope Tenant
- A copy of your Publisher registration token

- A VMWare ESXi account, Version 7 Update 2 or later.

To access the OVA from the Publisher page in the Netskope UI, go to **Settings > Security Cloud Platform > Publishers** and click **Publisher OVA** to download the Publisher OVA file. The OVA file is needed to create a ESXi-based Publisher.

Publishers

Publishers are Netskope software components that are deployed in your virtual network at your public cloud provider (e.g. AWS VPC) or internal network in your private datacenter. Publishers make your private applications available to authorized users and devices. View more instructions at [here](#).


AWS  [Publisher AMI](#) VMware ESXi:  [PUBLISHER OVA](#) Hyper-V:  [PUBLISHER VHDX](#)

Note

If you want to validate the integrity of the OVA, the SHA hash can be found in the [Publisher Release Notes](#).


Perform these steps in the VMWare ESXi console.

1. Log in to your ESXi instance and click **Virtual Machines**.




2. Click **Create/Register VM**.


3. For Select Creation Type, select **Deploy a virtual machine from an OVF or OVA file**, and then click **Next**.



4. For Select OVF and VMDK files, enter a name for the VM, drag and drop the OVA from Netskope, and then click **Next**.



5. For Select Storage, keep the default settings and click **Next**.




6. For Deployment Options, select your default network, and then click **Next**.

The screenshot shows the 'New virtual machine - MyPublisher' wizard in VMware Workstation. The left sidebar indicates the progress: 1 Select creation type, 2 Select OVF and VMDK files, 3 Select storage, 4 Deployment options (current step), and 5 Ready to complete. The main area is titled 'Deployment options' with the subtitle 'Select deployment options'. It contains three settings: 'Network mappings' set to 'bridged' with a dropdown menu showing 'VM Network 10'; 'Disk provisioning' with 'Thin' selected (radio button) and 'Thick' unselected; and 'Power on automatically' checked (checkbox). At the bottom right are buttons for 'Back', 'Next', 'Finish', and 'Cancel'. The VMware logo is visible in the bottom left corner of the window.

Setting	Value
Network mappings	bridged VM Network 10
Disk provisioning	Thin
Power on automatically	checked

7. For Ready to Complete, review the settings to confirm, and then click **Finish**.



If a Publisher needs additional interfaces, proceed to step 8.

8. To add another interface, click on the VM you just created and then click **Edit Settings**.

9. Click **Add Network Adapter**, and then click **Save**.

Register the Publisher

SSH into the publisher (default username: `ubuntu`, default password: `ubuntu`). When prompted, change your password. After you change it, the system auto-disconnects your SSH session, so you will need to reconnect and log in with their new password before proceeding.

1. SSH into the Publisher (default username: `ubuntu` , default password: `ubuntu`).

 Note

In the event of a password change, the new password must meet the following minimum requirements:

- Minimum password length must be 14 characters.
- Must contain one upper case letter.
- Must contain one lower case letter.
- Must contain one digit (number).
- Must contain one non-alphanumeric character.
- Cannot be a palindrome.

2. When prompted for a menu choice, select **Register**.

3. Execute the following command *only if* the Publisher is hosted inside China and needs to connect to a NewEdge DC inside China: `sudo touch resources/.prc_dp` .

4. When requested, enter the Netskope registration token, and then click **Enter**. You can also enter the token with this command: `sudo ./npa_publisher_wizard -token <TOKEN>` .

5. Go to **Settings > Security Cloud Platform > Publishers** in your Netskope tenant and confirm your Publisher has a *Connected* status. If not, go to [Publisher Logs for Troubleshooting](#).

Configure a Publisher in Hyper-V

The Netskope Publisher allows for zero trust network access to applications and hosts in your public cloud or private data center. This includes the ability to leverage a Publisher in Hyper-V.

This topic explains how to create a Publisher instance in Hyper-V. Knowledge of the Netskope UI and Hyper-V are required, along with:

- A Netskope Tenant
- A copy of your Publisher registration token
- A Hyper-V account.

To access the VHDX file from the Publisher page in the Netskope UI, go to **Settings > Security Cloud Platform > Publishers** and click **Publisher VHDX**.

Publishers

Publishers are Netskope software components that are deployed in your virtual network at your public cloud provider (e.g. AWS VPC) or internal network in your private datacenter. Publishers make your private applications available to authorized users and devices. View more instructions at [here](#).

AWS  **Publisher AMI**

VMware ESXi:  **PUBLISHER OVA**


Hyper-V:  **PUBLISHER VHDX**

Note

If you want to validate the integrity of the VHDX, the SHA hash can be found in the [Publisher Release Notes](#).

Perform these steps in the Hyper-V console.

1. Launch the Microsoft Hyper-V Manager and select the Action **New > Virtual Machine....**



2. Enter a VM Name (like NPA Publisher), optionally an installation location, and then click **Next**.




Tip

Name the Publisher to describe its location and/or application use.


The screenshot shows the 'New Virtual Machine Wizard' window, specifically the 'Specify Name and Location' step. The window has a title bar with the Microsoft logo and the text 'New Virtual Machine Wizard'. On the left is a navigation pane with the following steps: 'Before You Begin', 'Specify Name and Location' (which is highlighted with a blue bar), 'Specify Generation', 'Assign Memory', 'Configure Networking', 'Connect Virtual Hard Disk', 'Installation Options', and 'Summary'. The main area of the window contains the following text and controls:

- Section header: **Specify Name and Location**
- Instruction: 'Choose a name and location for this virtual machine.'
- Text: 'The name is displayed in Hyper-V Manager. We recommend that you use a name that helps you easily identify this virtual machine, such as the name of the guest operating system or workload.'
- Form: 'Name:' followed by a text box containing 'NPA Publisher'.
- Text: 'You can create a folder or use an existing folder to store the virtual machine. If you don't select a folder, the virtual machine is stored in the default folder configured for this server.'
- Form: A checkbox labeled 'Store the virtual machine in a different location' which is currently unchecked.
- Form: 'Location:' followed by a text box containing 'C:\ProgramData\Microsoft\Windows\Hyper-V\' and a 'Browse...' button.
- Warning: A yellow warning triangle icon followed by the text: 'If you plan to take checkpoints of this virtual machine, select a location that has enough free space. Checkpoints include virtual machine data and may require a large amount of space.'
- Navigation buttons at the bottom: '< Previous', 'Next >' (highlighted with a blue border), 'Finish', and 'Cancel'.


3. Leave **Generation 1** selected and click **Next**.




4. Specify the amount of memory for the NPA Publisher (4096 is recommended for most use cases) and click **Next**.




5. Select a network adapter to attach the NPA Publisher that has Internet access and click **Next**.




6. Select **Use an existing virtual hard disk** and then **Browse** to the downloaded VHDX file. When finished, click **Next**.




7. Confirm the Hyper-V Wizard configuration options and click **Finish**.



8. Now you can Start your NPA Publisher in Hyper-V.



9. Get the IP address provided by the Hyper-V Manager to SSH into a Publisher for Network Settings.



Register the Publisher

SSH into the publisher (default username: `ubuntu`, default password: `ubuntu`). When prompted, change your password. After you change it, the system auto-disconnects your SSH session, so you will need to reconnect and log in with their new password before proceeding.

1. SSH into the Publisher (default username: `ubuntu` , default password: `ubuntu`).

 Note

In the event of a password change, the new password must meet the following minimum requirements:

- Minimum password length must be 14 characters.
- Must contain one upper case letter.
- Must contain one lower case letter.
- Must contain one digit (number).
- Must contain one non-alphanumeric character.
- Cannot be a palindrome.

2. When prompted for a menu choice, select **Register**.

3. Execute the following command *only if* the Publisher is hosted inside China and needs to connect to a NewEdge DC inside China: `sudo touch resources/.prc_dp` .

4. When requested, enter the Netskope registration token, and then click **Enter**. You can also enter the token with this command: `sudo ./npa_publisher_wizard -token <TOKEN>` .

5. Go to **Settings > Security Cloud Platform > Publishers** in your Netskope tenant and confirm your Publisher has a *Connected* status. If not, go to [Publisher Logs for Troubleshooting](#).

Configure a Publisher on a KVM Host (QCOW2)

This document describes how to configure a Netskope NPA Publisher on a Linux host with a KVM (Kernel-based Virtual Machine) using the Publisher QCOW2 image. These instructions are based on Ubuntu 22.04 as the host OS, but apply to any Linux distribution that supports KVM and `libvirt` .

Prerequisites

To complete this configuration, you need:

- A Netskope tenant with NPA enabled.
- A Publisher registration token (generated from the Netskope tenant).
- A Linux host with KVM acceleration available (verify with `kvm-ok`).

- At least 4 GB RAM and 2 vCPUs free for the Publisher VM.
- 20 GB free disk space for the QCOW2 image.

Install KVM and Required Tools

```
sudo apt update
sudo apt install -y cpu-checker qemu-kvm libvirt-daemon-system libvirt-
clients virtinst bridge-utils

# Verify KVM is available
kvm-ok

# Should print: "KVM acceleration can be used"

# Add yourself to the kvm and libvirt groups (log out and back in
afterwards)
sudo usermod -aG kvm,libvirt $USER
```

Start the `libvirt` default network (created by the install above; it needs to be activated):

```
sudo virsh net-start default
sudo virsh net-autostart default
sudo virsh net-list # confirm "default" is active
```

Download the Publisher QCOW2 Image

```
wget https://s3-us-west-
2.amazonaws.com/publisher.netskope.com/latest/NetskopePrivateAccessPublisher
.qcow2
wget https://s3-us-west-
2.amazonaws.com/publisher.netskope.com/latest/NetskopePrivateAccessPublisher
.qcow2.SHA256.txt

# Verify the checksum
EXPECTED=$(cat NetskopePrivateAccessPublisher.qcow2.SHA256.txt)
ACTUAL=$(sha256sum NetskopePrivateAccessPublisher.qcow2 | awk '{print $1}')
[[ "$EXPECTED" == "$ACTUAL" ]] && echo "OK" || echo "MISMATCH"
```

```
# Move the image into libvirt storage
sudo mv NetskopePrivateAccessPublisher.qcow2 /var/lib/libvirt/images/npa-
publisher.qcow2
sudo chown libvirt-qemu:kvm /var/lib/libvirt/images/npa-publisher.qcow2
```

Create the Publisher VM

Launch the VM with the `libvirt` default NAT network. The VM gets an IP on the `libvirt` internal `192.168.122.0/24` network, and the host can reach the VM directly.

```
sudo virt-install \
  --name npa-publisher \
  --memory 4096 \
  --vcpus 2 \
  --disk path=/var/lib/libvirt/images/npa-
publisher.qcow2,format=qcow2,bus=virtio \
  --os-variant ubuntu22.04 \
  --network network=default,model=virtio \
  --graphics none \
  --console pty,target_type=serial \
  --import \
  --noautoconsole
```

Confirm the VM is running:

```
sudo virsh list --all
```

Register the Publisher

You can access the Publisher VM via the `libvirt` serial console or via SSH. Either method works for completing the wizard.

Option A: Connect via the serial console (recommended for KVM)

The serial console works regardless of network configuration and is the most reliable way to interact with a fresh Publisher VM.

```
sudo virsh console npa-publisher
# Press Enter at the blank screen to see the login prompt
```

```
# To exit the console later, press Ctrl + ]
```

Option B: Connect via SSH

Wait 30-60 seconds after the VM starts for DHCP to complete, then look up the VM's IP address:

```
sudo virsh domifaddr npa-publisher
# IP will be 192.168.122.x for default NAT

ssh ubuntu@<VM_IP>
```

First Login with Wizard

1. Log in with the default credentials: username `ubuntu`, password `ubuntu`.
2. You will be prompted to create a new password. Password rules:
 - Minimum 14 characters
 - At least one uppercase letter
 - At least one lowercase letter
 - At least one digit
 - At least one non-alphanumeric character
 - No palindromes
3. Run the Publisher wizard:

```
sudo ./npa_publisher_wizard
```

4. From the wizard menu, select **Register**, and paste your registration token when prompted.
5. Alternatively, register non-interactively with this command:

```
sudo ./npa_publisher_wizard -token <REGISTRATION_TOKEN>
```

6. Verify the Publisher status in the Netskope tenant; it should show as **Connected**.

Common VM Operations

```
# List VMs
sudo virsh list --all
```

```
# Stop / start the VM
sudo virsh shutdown npa-publisher
sudo virsh start npa-publisher

# Force off (if shutdown hangs)
sudo virsh destroy npa-publisher

# Connect to the console (Ctrl + ] to exit)
sudo virsh console npa-publisher

# Delete the VM and its disk
sudo virsh destroy npa-publisher
sudo virsh undefine npa-publisher --remove-all-storage
```

Advanced Network Options

The default NAT network works for most cases. If you need the Publisher VM to be reachable on your physical LAN, replace the `--network` argument in the `virt-install` command:

Bridge to a Physical NIC

The VM gets an IP on your LAN (same subnet as the host). Requires a pre-configured `br0` bridge on the host.

```
--network bridge=br0,model=virtio
```

macvtap direct

Quick LAN access without configuring a bridge. Note that the host itself cannot SSH to the VM in this mode (other LAN machines can). Replace `eth0` with the actual host interface name.

```
--network type=direct,source=eth0,source_mode=bridge,model=virtio
```

macvtap does not work on cloud instances (AWS EC2, GCP, Azure) because the cloud network filters non-ENI MAC addresses. Use it only on physical or on-premises virtualized hosts.

Troubleshooting

Network not found: no network with matching name 'default'

Start the default network:


```
sudo virsh net-start default
sudo virsh net-autostart default
```

If the default network was deleted (unusual), recreate it from the `libvirt` bundled XML:

```
sudo virsh net-define /usr/share/libvirt/networks/default.xml
sudo virsh net-start default
sudo virsh net-autostart default
```

virt-install: command not found

Install `virtinst` :

```
sudo apt install -y virtinst
```

VM has no IPv4 address (after `virsh domifaddr`)

Wait 30-60 seconds for DHCP to complete and check again. If the VM still has no IP (DHCP unavailable on your network, static IP required), connect via `virsh console` and use the Publisher wizard to configure networking interactively (static IP, DNS, gateway).

Permission denied (publickey,password) when SSHing

The Publisher requires password authentication. Use the default credentials (`ubuntu` / `ubuntu`) on first login; you'll be forced to change the password immediately.here

Configure a Publisher on a Standalone Linux System (Ubuntu/RHEL)

The Netskope Publisher allows for zero trust network access to applications and hosts in your public cloud or private data center. This includes the ability to leverage a Publisher on a standalone installation of Ubuntu 22.04 or Red Hat Enterprise Linux 9.6. Any x86 server running on Ubuntu 22.04 or RHEL 9.6, whether on-premises or in a public cloud, and whether physical or virtual, that satisfies the [requirements](#) is supported.

This topic explains how to create a Publisher instance on a Standalone Linux Installation. Knowledge of the Netskope UI is required, along with:

- A Netskope Tenant.
- A copy of your Publisher registration token.
- A Ubuntu 22.04 or Red Hat Enterprise Linux 9.6 installed system with following configuration:

- Meets [Publisher Requirements](#). Have a non-root user with sudo permission to install the Publisher with a script.

 Important

Ensure your `/tmp` folder has a `777` permission for successful Publisher deployments and OS updates.

Run the following command in the non-root SSH session on your Linux Operating System to download and install the necessary components for the Publisher. This may take about 10 minutes.

```
curl https://s3-us-west-2.amazonaws.com/publisher.netskope.com/latest/generic/bootstrap.sh | sudo bash; sudo su - $USER; exit
```

At the end of this process, you have a fully functional Netskope Publisher and can register it with Netskope.

 Note

During auto-update of this Publisher, Netskope will update the Publisher and make an attempt to update the operating system. Kernel updates should be carried out by the system administrator. For more information, go to [Publisher Auto-Update](#).

Register the Publisher

1. SSH into the Publisher.

 Note

In the event of a password change, the new password must meet the following minimum requirements:

- Minimum password length must be 14 characters. Must contain one upper case letter. Must contain one lower case letter. Must contain one digit (number). Must contain one non-alphanumeric character. Cannot be a palindrome.

2. Once logged in to the linux shell run: `sudo ./npa_publisher_wizard -token <TOKEN>`.

3. Go to **Settings > Security Cloud Platform > Publishers** in your Netskope tenant and confirm your Publisher has a *Connected* status. If not, go to [Publisher Logs for Troubleshooting](#).