mod19_ex03: Installing Ranger RMS

The purpose of this exercise to install and configure Ranger Resource Mapping Server (RMS).

Legacy CDH users set Hive policies which automatically linked Hive permissions to HDFS ACL's. This was especially convenient for external table data used by Spark or Hive. Previously, Ranger managed Hive and HDFS policies separately, you had to set both. Ranger RMS replicates the CDH capability, setting a Hive policy will make changes in HDFS.


Reference Information

TBD

- 1. Login into Cloudera Manager as the administrative user, allan_admin.
- 1.1 Login into Cloudera Manager as the administrative user, allan_admin, with password <password>.




- 2. Install Ranger RMS.
- 2.1 From Cloudera Manager Home select Action. Select Add Service.



2.2 Scroll down. Select Ranger RMS. Click Continue.




2.3 On Assign Roles click on Server.



2.4 Select the option for edge.example.com. Clear the checkmark for worker-3.example.com. Click OK.


1 Hosts Selected




2.5 Verify Server is set to edge.example.com. Click Continue.

Assign Roles You can customize the role assignments for your new service here, but note that if assignments are made incorrectly, such as assigning too many roles to a single host, performance will suffer. You can also view the role assignments by host. View By Host Server × 1 New edge.example.com •

2.6 On Setup Database configure the database. Click Test Connection. When succeful click Continue.





2.7 Scroll down to Heapsize. Set Ranger RMS Max Heapsize to 1 GiB.




2.8 Scroll down to Enable Mapping Hive Managed Tables. Select the option for Enable Mapping Hive Managed Tables. Click Continue.



This will be used by Ranger RMS to track managed tables. Kerberos and TLS will be automatically configured.


2.9 On Command Details monitor progress. When Finish click Continue.

Command Details




2.10 On Summary, click Finish.


Summary




- 3. Configure HDFS.
- 3.1 From Cloudera Manager Home select hdfs. Select Configurations.



3.2 Search for 'ranger-hdfs-security'. Add two properties to the ranger_security_safety_valve advanced configuration. Click Save Changes.



3.3 On HDFS select Actions. Select Restart. Click Restart. When Finished click Close.




4. Configure Hive.

4.1 From Cloudera Manager Home select Hive. Select Configuration.



4.2 Search for 'proxyuser.rangerrms'. Verify the property value is set to '*'.



- 4.3 Select Hive Actions. Select Restart. Click Restart. When Finished click Close.
- 5. Return to Cloudera Manager Home. Select Ranger RMS actions. Select Start. Click Start. When Finish click Close.



6. Return Cloudera Manager Home.