How To Create a Windows Deployment Server with Microsoft Deployment Tools


By Justin Mah


Requirements

- A Domain Controller (if you have not created one please refer to the tutorial "How to Create a Windows Server 2016 Domain Controller")
- A copy of a Windows Operating System ISO
- Windows 10 Automated Deployment Toolkit and WinPE add-on
- Microsoft Deployment Services


Steps

1) Create a virtual machine with the same specifications as you Domain Controller, install Windows Server 2016







3) Right click the network adapter icon > Network and Sharing Centre > Click "Change Adapter Settings"



4) Right click the network adapter "Ethernet0" > Properties




5) Select Internet Protocol Version 4 > Set the IP address, Subnet Mask, and Default Gateway to the network configuration outlined in step 2, set the Primary DNS Server to the IP Address of your Domain Controller




6) Download and install Windows 10 ADK and MDT, accept the defaults.

7) Add a second HDD, which will store the files necessary for deployment




note: Before formatting the drive as a new simple volume you need to bring it online


then initialize it as an MBR first




8) Push Windows + Pause | Break, under computer name click change settings




9) Click change




10) Select domain and enter your domain name (As created in How to create a domain controller)




11) Enter the Domain Administrator username and password




12) Login using the Domain Administrator account




13) Click Manage > Add Roles and Features




14) Accept defaults > Select Windows Deployment Services at the server roles page > Click add features when prompted




15) Click next 3 times > click install > click closed when completed




16) Click tools > Windows Deployment Services




17) Click servers > right-click server name > configure server




18) Click next > Select "Integrated with Active Directory"



19) Click browse > select the second drive created in step 7 and create a folder to store the remote installation folder




20) Select "Respond to all client computers (known and unknown)" . Leave Require administrator approval box unchecked




21) Click finish when prompted


22) Attach the installation ISO to your VM




23) Right click install images > Add install image > Name image group



24) Click browse > locate the install.wim file located in the sources folder



25) Click next 2 times > click finish




26) Open deployment workbench (under deployment toolkit in the start menu)


27) Right click deployment shares > New Deployment Share




28) Point the deployment share path to the second hard drive




29) Accept default UNC name




30) Give deployment share a descriptive name



31) Accept defaults




- 32) Click next 2 times
- 33) Click finish




34) Open deployment share


35) Right click operating systems > import operating system



36) Select Windows Deployment Services images




37) Enter deployment server name




- 38) click next 2 times > click finish
- 39) right click task sequences > new task sequence




40) Enter a task sequence id and name




41) Select "standard client task sequence"




42) Select install image imported in step 24




43) Accept defaults



44) Enter an organization name




45) Enter an Administrator password




46) Click next 2 times > finish


47) Right click *deployment share name* > update deployment share




48) Select "completely regenerate boot images" > click next




49) On WDS, right click boot images > Add Boot Image




50) Navigate to where the LiteTouchPE_x64.wim file is located, click next 3 times




51) Right click *server name* > properties



52) Select PXE response, ensure that "Respond to all client computers" is selected







with the PXE options you can force the client computer to perform a PXE boot by default or require the user to push F12 to boot


53) On your client machines push F12 to perform a PXE boot


```
Network boot from Intel E1000e
Copyright (C) 2003-2014 UMware, Inc.
Copyright (C) 1997-2000 Intel Corporation
CLIENT MAC ADDR: 00 0C 29 76 DD 45 GUID: 564D73CA-34F7-7DE7-C41B-7BC96D76DD45
CLIENT IP: 192.168.202.152 MASK: 255.255.255.0 DHCP IP: 192.168.202.254
GATEWAY IP: 192.168.202.2
Downloaded WDSNBP from 192.168.202.151 WDS.jmah22.local
Press F12 for network service boot
    Loading files...
    IP: 192.168.202.151, File: \Boot\x64\Images\LiteTouchPE_x64.wim
```


54) Follow the steps to complete the imaging

















click begin when ready

Note: the deployment can be automated so there is no user interaction during the imaging process (zero touch deployment)