DAYZ TOOLS · P3D MODELING

OBJECT BUILDER

Keyboard & mouse reference — page 1 of 2: modeling

`NUM` numeric keypad
`LMB` `RMB` mouse buttons
`drag` hold button & move
`⇧` Shift

VIEWPORTS & CAMERA

`Tab`	Cycle active viewport
`↑↓←→`	Scroll the view
`Ctrl` `↑↓←→`	Scroll faster
`Alt` `RMB drag`	Orbit camera (3D view)
`Alt` `LMB drag`	Pan view
`wheel` `NUM +` `NUM −`	Zoom in / out
`NUM *`	Center on selection
`Alt` `NUM *`	Center all views on selection
`F9`	Reset to 4-view layout
`Alt` `S`	Split window into 4 views
`F`	Show / hide back-facing faces

SELECTING

`F2` `O`	Object (whole piece) mode
`F3` `T`	Face mode
`F4` `V`	Vertex mode
`LMB drag`	Select / box-select
`Ctrl` `LMB`	Add to selection
`Ctrl` `⇧` `LMB`	Remove from selection
`Ctrl` `A`	Select all
`Ctrl` `D`	Deselect
`Ctrl` `I`	Invert selection
`Ctrl` `W`	Select front or back side only
`Ctrl` `H`	Hide selection · add ⇧ to unhide
`Ctrl` `L`	Lock selection · add ⇧ to unlock

TRANSFORM

`LMB drag`	Move selection
`⇧` `drag`	Duplicate & move
`Ctrl` `drag`	Rotate (around pin if on)
`Ctrl` `⇧` `drag`	Scale (from pin if on)
`X` `Y` `Z`	Lock movement to one axis
`P`	Flatten points to an axis or pin plane

PIN (PIVOT POINT)

`R`	Place pin (then click)
`C`	Center pin on selection
`⇧` `C`	Pin on / off for rotate, scale, insert
`Space`	Center view on pin
`⇧` `F11`	Measure pin → cursor

BUILD & DELETE

`Ins`	New vertex at cursor
`⇧` `Ins`	New vertex at pin
`F6`	Face from 3 or 4 selected verts
`F7` `F8`	Create box / cylinder
`Del`	Delete selection
`D`	Remove faces, keep vertices
`Ctrl` `Del`	Remove verts, merge faces, keep UVs
`⇧` `D`	Weld selected verts (also ⇧ M)
`⇧` `R`	Turn edge
`Q`	Uncross face
`NUM /`	Triangulate quads

NORMALS & SMOOTHING

`F5`	Recalculate normals — after any rotate
`W`	Reverse face (flip normals)
`U`	Make edges sharp
`I`	Make edges smooth

MAPPING & MATERIALS

`E`	Face properties: texture + .rvmat
`A`	Texture (background) mode
`B`	Apply background mapping
`Ctrl` `B`	Background from face
`M`	Map dialog
`G`	Gizmo mapping
`Ctrl` `U`	Unwrap dialog
`↑↓←→`	Move map rectangle · add ⇧ to resize

FILE & EDIT

`Ctrl` `N` `O` `S`	New / open / save
`Ctrl` `Z`	Undo (also Alt ⌫)
`Ctrl` `Y`	Redo
`Ctrl` `C` `X` `V`	Copy / cut / paste — works between LODs and OB windows

OBJECT BUILDER · WINDOWS, BULDOZER & DAYZ

WINDOWS & PROPERTIES

E	Face properties
⇧ E	Vertex properties
⇧ F5	Named selections
Alt L	LOD window
Alt P	Named properties (also Ctrl 1)
Alt M	Mass — Geometry LOD
Alt T	Texture / resource library
Alt H	History
⇧ W	Linear deform

FACE ORDER

Ctrl ⇧ Home	Move face first · End = last
Ctrl ⇧ PgUp	Move face up · PgDn = down

Order matters for alpha-textured faces (glass, foliage).

BULDOZER PREVIEW

S	Cycle selection masking (press in OB)
W E S ↑↓←→	Pan camera
A D	Rotate camera
NUM 2 4 6 8	Rotate object (or RMB drag)
Ctrl + move	Slower camera moves
NUM 5	Reset camera, center object
NUM + NUM −	Zoom
Enter ⌫	Next / previous model.cfg animation source
wheel	Step through that animation
[ ]	RTM playback slower / faster
⇧ [ ]	Set animation phase
RWin U I	Change weather
RWin T Y	Change time of day
RWin X	Toggle textures

MENU-ONLY ESSENTIALS

Structure › Topology › Find Components — names Geometry pieces

Structure › Topology › Find Non-Closed

Structure › Convexity — find non-convex, Component Convex Hull

Structure › Squarize — rejoin triangles after FBX import

Points › Merge Near — weld by distance

Points › Transform 3D — numeric move / rotate / scale, all LODs

KNOWN QUIRKS

Z is zoom mode in 2D views but Z-axis lock in the 3D view.

Lasso (~) and grid (Ctrl G) don't work — use Edit › Edit mode › Lasso.

Points only merge if their vertex properties match (⇧ E).

DAYZ FIELD NOTES

LOD checklist for a working P3D

`0.000, 1.000…`	Visual LODs, most detailed first. Roughly halve faces per step; keep selection names identical.
`Geometry`	Collision + mass. Closed, convex Component01…; assign mass with Alt M.
`Fire Geometry`	What bullets hit. Simple ComponentXX pieces with penetration .rvmats.
`View Geometry`	Sight blocking; without it (or Fire Geo) actions may not show.
`Memory`	Vertices only — named points and axes for config and model.cfg.
`LandContact`	Vertices touching the ground. Wrong height = floating or sinking.
`Roadway`	Surfaces players walk on (floors, stairs).
`ShadowVolume 0`	Closed, triangulated, all edges sharp, no textures, under 1000 tris.

Selections starting with **-** or **.** are work selections and aren't binarized.

Animated selection names: 32 characters max, present in every animated LOD.

From Blender: name objects like **Component01_LODGeometry**, tick LODs on FBX import, then Squarize.

Proxy models need **autocenter = 0** in their Geometry LOD.

Texture paths are P:-drive relative. Keep the P: drive mounted before you open a model.

Buldozer won't attach? Start Object Builder from the DayZ Tools launcher, not straight from Steam.