

Key Switches

Some parameters of SWAM instruments can also be triggered by the use of key switches. If there is an overlap in the instrument range after transposition, the key switches can be moved down one octave using the “KS Octave” parameter (see Advanced section). Key switches can be disabled by turning “KS Octave” To “OFF”.

Key switches are colored red on the instrument’s virtual keyboard.

Important note about Key Switches: “latch” Key Switches are sensitive to the KS velocity, even for two-state Key Switches. This way a sequence can be played correctly even if it is not started from the beginning; otherwise a “latch” status could work differently from how it should.

“KS Velocity Remap” adjusts the distribution of the KeySwitch values

The Key Switches provided are:

- C = Play Mode (at next Note On)
 - Low Velocity = Bow
 - Mid Velocity = Pizzicato
 - High Velocity = Col Legno
- C# = Manual Bowing
(see “Manual Bowing: KeySwitch” in Play Modes/Right Hand section)
 - Tremolo: Note-on / Note-off
 - Bow Change: Note-on only
- D = Gesture Mode (at next Note On)
 - Low Velocity = Expression
 - Mid Velocity = Bipolar
 - High Velocity = Bowing
- D# = Alternative Fingering (at next Note On)
 - Low Velocity = Mid Position
 - Mid Velocity = Near the Bridge

- High Velocity = Near the Nut + Open
- E = Bow Lift
 - Off String (default)
 - While this key is held = On String
- F = Bow Start
 - Down Bow
 - Up Bow
- F# = Harmonics
 - Off (default)
 - Low Velocity = 2nd harmonic
 - High Velocity = 3rd harmonic

Note: it's not possible to control the 4th harmonic through Key Switches

- G = Keep Bow Direction
 - OFF (default)
 - While this key is held = ON
- G# = Tremolo
 - OFF (default)
 - Low Velocity = Slow
 - High Velocity = Fast
- A = Tremolo Mode (at next Note On)
 - Low Velocity = Hz
 - Mid Velocity = Sync
 - High Velocity = Sync/Acc
- A# = Sordino (at next Note On)
 - Low Velocity = OFF



- High Velocity = ON
- B = 2nd page

2nd page of Key Switches (hold B Key Switch)

- B+C: Bow Real Mono
- B+C#: Bow Mono
- B+D: Bow Double
- B+D#: Bow Double/Hold
- B+E: Bow Auto
- B+F: Pizz/Col Legno Mono
- B+F#: Preferred strings 4-3 (for Double/Hold only)
- B+G: Pizz/Col Legno Poly
- B+G#: Preferred strings 3-2 (for Double/Hold only)
- B+A#: Preferred strings 2-1 (for Double/Hold only)

NOTE: All parameters controlled by the Key Switches can be controlled by MIDI Control Change, Aftertouch and NRPN messages as well, through the Controller Mapping section.

Instruments ranges

	Middle C = C3		Middle C = C4	
	Additional range	Regular range	Additional range	Regular range
SWAM Violin	D#2 - F#2	G2 - F6	D#3 - F#3	G3 - F7
SWAM Viola	G#1 - B1	C2 - C6	G#2 - B2	C3 - C7
SWAM Cello	F0 - B0	C1 - F5	F1 - B1	C2 - F6
SWAM Double Bass	B-1 - D#0	E0 - G#4	B0 - D#1	E1 - G#5

Notes:

- Ranges are provided in Concert (or Natural) pitch.
- Middle C can be switched from C3 to C4 in Main Menu -> Settings -> Options.
- To extend the lower range of the instrument act on the "String tuning" parameter in the "Advanced" page.
- SWAM Cello and SWAM Double Bass are transposed -12 semitones by default. Set the Transpose parameter to 0 to play with real pitch.