

EDT — Change Log (V1.11-0)

Sector7 USA LLC · EDIT/EDT for Linux and Windows

September 2026 · V1.11-0

Table of contents

EDT Change Log

V1.11-0: 2026-09-11

EDIT/EDT/CMD=filename, the startup command file (field request)

V1.10-0 — 2026-07-24

VMS ;n file versioning (VX/RT-driven)

V1.09-0 — 2026-07-23

Screen mode — prompts

Screen mode — keypad SUBS (GOLD+ENTER)

Screen mode — key-function echo

Errors

Startup splash

Docs

V1.08-0 — 2026-07-23

Startup splash

V1.07-0 — 2026-07-21

Startup splash

V1.06-0 — 2026-07-20

Startup splash

Screen mode — Windows numeric keypad

Screen mode — key identification

Search

Search — no more wrap-around (behaviour change)

V1.05-0 — 2026-07-17

Licensing / startup

V1.04-0 — 2026-07-16

Screen mode

HELP / docs

V1.03-0 — 2026-07-15

Partials → faithful

Missing verbs

Host RMS / versions

Soft residue

V1.02-0 — 2026-07-15

Line mode

Screen / keypad / nokeypad

Invocation / journal / HELP

V1.01-0 — 2026-07-15

V1.00-1 — earlier (pre-version-field)

EDT Change Log

Product: Sector7 EDIT/EDT (`edt.cpp`)

Current release: V1.11-0

Release date: 2026-09-11

Compared against: OpenVMS EDT V3.13 on host `t86` (OpenVMS x86_64 V9.2-3); V1.11-0 measured on host `ia64` (OpenVMS IA64 V8.4-2L1)

This file is the running release log. Recreate or extend it from:

```
git log --edt/ --oneline
# plus the Release identity block in edt.cpp (EDT_VERSION_* / EDT_RELEASE_DATE)
```

Bump `EDT_VERSION_MAJOR` / `MINOR` / `EDIT` and `EDT_RELEASE_DATE` in `edt.cpp` on every public release; `SHOW VERSION` / `VERSION` print both.

V1.11-0: 2026-09-11

EDIT/EDT/COMMAND=file, the startup command file (field request)

Request: `edit/edt/command=daily daily.lis` with a `daily.edt` of INCLUDE, ranged SUBSTITUTE and EXIT lines. Every behaviour below was measured on real OpenVMS EDT (V3.13, OpenVMS IA64 V8.4-2L1, host `ia64`) with the same fixture files, then reproduced. The customer's file now produces the identical 9-line result and the identical output (`<file> 9 lines`, then `[EOB]`).

- **/COMMAND=file is accepted on the command line**, next to the existing `-command file` / `-command=file`, and so is `-command:file`, the form the VX/RT DCL EDIT verb emits. `/NOCOMMAND` and `-nocommand` run no startup command file at all. `-read_only` (the DCL form) is accepted like `-readonly`; `-output:` and `-journal:` like their `=` forms.
- **The command file replaces EDT.INI** for that run, as on OpenVMS (measured: an `EDTINI.EDT` in the directory is not read when `/COMMAND=x` is given; it is read for a bare `/COMMAND`). Before, the `-command` file ran after EDT.INI.
- **Default file type .edt**: `/COMMAND=daily` opens `daily.edt` (`daily.EDT`, then a bare `daily`, are tried on a case-sensitive host).
- **A missing command file aborts the editor** before the input file is opened, with the OpenVMS text and exit status 4: `Command file does not exist / File name:daily / %RMS-E-FNF, file not found / %EDT-F-EDITORABO, Editor aborted`. Before: `?Unable to open command file` and the session continued.
- **EXIT inside the file** saves, prints the exit message and then `[EOB]` (OpenVMS still types the "current line" after the file, and the buffer is gone by then). **QUIT inside the file** prints an empty line and then the current line. A file that ends without either types the current line and prompts, as before.
- **INCLUDE** prints nothing on success (it printed `N lines included`) and leaves the current line on the line it was on, so successive INCLUDEs land in order (they landed reversed). A missing file reports the OpenVMS three-line `Include file does not exist` message and processing continues.
- **Ranged SUBSTITUTE** `S/old/new/range`, with any prefix of the verb (`S`, `SU`, `SUB` ...): every occurrence on every line of the range is replaced, each changed line is typed unless `/NOTYPE`, and the current line becomes the first line of the range whether or not anything matched. A trailing number is a line number (`S/a/b/2` changes line 2), not a repeat count as this build previously read it. Interactively the command reports `n substitution(s)` or `No substitutions`; from a startup command file it reports nothing (both measured). `S//new/` reuses the current search string. Qualifiers are recognised only after the third delimiter, so `S/x/save/` no longer loses its replacement text to `/SAVE`.
- **Range keyword abbreviations**: `E/EN` (END), `B`, `BE` ... (BEGIN), `WH`, `WHO` ... (WHOLE), `R`, `RE` ... (REST), `LA/LAS` (LAST); a lone `L` is rejected, as on OpenVMS. `TYPE END` (and `T E`) types `[EOB]`, not the last line.
- **VX/RT DCL (dcl/EDIT.cxx)**: the EDIT verb now passes `/COMMAND=`, `/NOCOMMAND`, `/OUTPUT=`, `/JOURNAL=`, `/READ_ONLY` and `/RECOVER` to any editor configured as `edt` or `edt.exe` (with or without a path). Before, they were passed only when the `EDT` config value was

literally `edt`, so with the usual `EDT edt.exe` every qualifier was silently dropped. The missing-file check now checks the command file (it checked the input file) and applies the `.EDT` default type. `EDIT/TPU` (`DO_EDIT_USING_TPU`) was not changed.

- Tests: `edt_regression.sh` section 33 (35 checks against the ia64 measurements); `cov_substitute_count` and `test_brief_type` in the Python suite updated to the measured semantics; three existing checks now ignore the QUIT trailer; `TYPE END` now expects `[EOB]`.

Known divergences left as they were (outside this request; all measured on `ia64` in the same session, listed so nobody mistakes them for done):

- Line numbers are positional here; OpenVMS keeps sequence numbers, so lines INCLUDED in front of line 1 show as `0.1`, `0.2` there and as `1`, `2` here. The typed-line format is `1 text` here and `1 text` there.
- Error text: OpenVMS echoes the offending command, a caret line and `Unrecognized command`; this build prints `?Unrecognized command: ...`.
- `TYPE range` moves the current line to the first line of the range on OpenVMS; here it does not move it. `LAST` semantics differ.
- The single-form `S/old/new/` still advances to the next match and types that line; OpenVMS types the changed line and reports `1 substitution`.
- `QUIT` prints an empty line on OpenVMS; here it prints `Changes discarded` when the buffer was modified.
- `EDT.INI` is still replayed silently with `EXIT/QUIT` ignored (§9.2); on OpenVMS `EDTINI.EDT` is the same mechanism as `/COMMAND`, is looked up in the current directory only (not `SYSS$LOGIN`), and `SYSS$LIBRARY:EDTSYS.EDT` is read first. Errors during `EDT.INI` replay go to `startup_warnings_`, which nothing prints.
- The line-mode banner still echoes `$ EDIT/EDT file` before the current line; OpenVMS prints only the current line.
- `SET QUIET` here suppresses the banner and all command output; on OpenVMS it only silences the bell. A customer command file containing `SET QUIET` (the first example in the OpenVMS manual) would stop displaying lines.
- `-nooutput`, `-nojournal` and `-nobackup` from the DCL verb are still accepted and ignored.

V1.10-0 — 2026-07-24

VMS ;n file versioning (VX/RT-driven)

- **EDT/VERSIONING in the VX/RT config file turns versioning on.** EDT reads the key straight from the config file — `$VX_CONFIG`, then `$RT_CONFIG`, then the VMS `SYSS$MANAGER` config (`$HOME/SYS0/SYSMGR/CONFIG.INI`, since `SYSS$SYSROOT` is rooted at `$HOME/SYS0`), then the `$VXREL / etc` fallbacks. `Y/YES/ON/TRUE/1` (any case) turn it on; `N/OFF/0` or an absent key leave it off. **The value is parsed from the file directly, not via the runtime `vxrt_config()`** — that call pulls in the VX/RT device-table init, which aborts a plain editor process where SysV shared memory is not set up (notably macOS).

- **Opening resolves the version (RMS-style).** With versioning on, `edt t.txt` opens the **highest existing version** (`t.txt;12`); `edt t.txt;1` opens version 1 (the bare `t.txt`); `edt t.txt;N` opens that version. The resolved name becomes the buffer's, so a save versions forward from it.
- **Saving writes the next version.** A **brand-new file** is written as the bare name — that is version 1 (`edt t.txt` on a missing file creates `t.txt`, not `t.txt;2`). A bare name whose family already exists writes the next version above the highest (`t.txt` present → `t.txt;2`, up to `;12` → `;13`); a `;N` name writes `;N+1`. A guard steps past any existing sibling so a save never clobbers a version.
- **SET VERSIONING ON|OFF in EDT.INI** turns versioning on/off, and is honoured *before* the file is opened so the open resolves to the highest version. The interactive `SET/SHOW VERSIONING` and `EDT_VMS_VERSIONS` environment force-on also drive the same flag.
- **S7SECURITY.INI versioning=on|off** is the fallback when no VX/RT config is found (default off).
- **A deployed VX/RT runtime suppresses the startup splash.** Detected by a presence-only `dlopen` of `libvxrtl.so` (no `vxrt_config()` call), or by finding `EDT/VERSIONING` in the config.
- Shared with **VX-TPU** (`TPU/VERSIONING`) through `s7security/s7_vxconfig.hpp` so both editors behave identically. The reference's "`;n` versioning deferred" notes are corrected: it is implemented (§13.6).

V1.09-0 — 2026-07-23

The rest of the July 22 field report: prompt completion, real keypad SUBS, the splash colour bleed, the key-function echo, and the error bell.

Screen mode — prompts

- **The keypad ENTER now completes every screen-mode prompt** (`Search for:`, `Command:`, `SPECINS`, `Nokeypad:`, `DEFINE KEY`). The prompts were read with curses `getnstr()`, which only recognises the RETURN key; they are now read key-by-key so the keypad keeps decoding.
- **ADVANCE / BACKUP complete the Search for: prompt**, set the search direction, and start the search — the OpenVMS EDT convention. Backspace and Ctrl/U edit the pending input.

Screen mode — keypad SUBS (GOLD+ENTER)

- **SUBS now requires the cursor to be on a FIND/FNDNXT hit**, refusing with `No select range active` (and the bell) anywhere else. It previously jumped ahead and substituted the next match — dangerous, and not what the OpenVMS EDT manual documents.
- **After the last occurrence is substituted, SUBS reports String was not found** (with the bell). The message was being posted by the search and then immediately overwritten by `Substituted`, so a rapid SUBS sequence gave no cue that it had run out of matches.
- The replacement text is the PASTE buffer, as before (and as on VMS).

Screen mode — key-function echo

- **The [FUNCTION] echo moved to the status line.** The invoked function (`[GOLD]`, `[CUT]`, `[SUBSTITUTE]`, ...) is shown on the status line instead of the message line, so it no longer collides

with prompts and errors. Plain keypad functions now echo too (previously only GOLD chords did); typing ordinary text clears the echo.

Errors

- **Screen-mode errors ring the terminal bell**, matching OpenVMS EDT (`String was not found`, `No select range active`, `Undefined GOLD key`, select-state errors). `SET QUIET` **suppresses the bell** — its actual OpenVMS meaning — in addition to the startup banner. Line-mode and piped output remain byte-clean; the bell only sounds while the curses screen is live.

Startup splash

- **Fixed: the splash's blue background bled into a later CHANGE screen.** The splash sets a blue `bkgd()`; the curses screen persists across `endwin()`, so screen mode inherited blue (line mode, being stdout, stayed black — the reported "black line mode, blue change mode"). The background is reset when the splash is dismissed.

Docs

- §7.1.2: macOS Terminal.app cannot transmit `KP/` or `KP*` even in application-keypad mode (they arrive as plain characters) — the PF2/PF3 mappings need iTerm2 ("Application keypad allowed") or PuTTY.
- §7.3/§8.8: keypad SUBS gating, prompt completion, `[FUNCTION]` echo, bell/ `SET QUIET` documented; stale `GOLD+ENTER = newline` rows fixed.

V1.08-0 — 2026-07-23

From field feedback on the V1.06-0 splash (too much text to read on a timer; no indication it would never come back).

Startup splash

- **The initial splash no longer times out.** The first-run splash (and `splash=on`) stays up until the user hits ENTER — there is no way to miss it, and no rush to read it. An explicit `splash=<n>` (or a licensed duration) remains timed, with ENTER dismissing early.
- **The splash now says it is shown once.** Two lines above the prompt: "This screen is shown ONCE and will not appear again" and how to re-enable it (`splash=on` in `S7SECURITY.INI`).
- **The notice and ENTER prompt are always visible.** The splash body is taller than an 80x24 terminal; the final lines now anchor to the bottom of the screen instead of being clipped off — previously a small terminal showed no prompt at all.
- Vertical centering uses the real content height (~40 rows, was a stale 28), fixing the bottom-heavy layout reported on tall windows.
- Headless / scripted runs (stdin not a terminal) still start instantly: end of input dismisses the splash rather than blocking.

V1.07-0 — 2026-07-21

Startup-splash polish, continuing from field feedback that the splash was either too brief to read or (once shown) hard to bring back.

Startup splash

- **Default duration is now 15 seconds** (was 5, briefly 10). A fresh install with no `S7SECURITY.INI`, or `splash=on`, holds the branded screen for 15 seconds so it can actually be read.
- **"Hit ENTER to continue"** — the splash now waits for ENTER to dismiss early, and the prompt says so. Other keys are ignored so a stray keystroke doesn't clear it; the timeout still auto-dismisses if no one is watching.
- **`splash=<n>` is clamped to 0..15 seconds.** A value above 15, or a negative one, is treated as 15 rather than rejected — a typo costs a few seconds, not a wedged terminal. (The previous ceiling was one hour, so a fat-fingered `splash=99999` could appear to hang.) `splash=0` == `splash=off`.
- **The persisted flag is now `splash=0`** (was `splash=off`). After the splash has shown once, the auto-written `S7SECURITY.INI` carries `splash=0`; `off` is still accepted on read for existing installs.
- Non-numeric junk (`splash=abc`) still warns on stderr and falls back to the default rather than being silently treated as "off".

V1.06-0 — 2026-07-20

Field bug report: Windows screen-mode keypad, the search start point, and a splash you could never see for long enough to read.

Startup splash

- **`splash=<n>` sets the splash duration in seconds.** `S7SECURITY.INI` previously understood only on/off, so the only way to re-show the splash was to delete the file and watch it for whatever the built-in 5 seconds allowed. `splash=15` now holds it for 15 seconds; the count overrides both the licensed duration and the built-in default. `splash=0` == `splash=off`, `splash=on` uses the default, and a keypress still dismisses early.
- Unrecognised `splash=` values are now reported on stderr naming the value instead of being silently treated as "not off".
- The auto-generated `S7SECURITY.INI` documents the syntax in its header comment. Behaviour is unchanged in one respect: the splash is still shown **once** and the file reverts to `splash=off` afterwards.
- Shared with VX-TPU via `s7security/` — same syntax, same precedence.

Screen mode — Windows numeric keypad

- **Fixed: most of the numeric keypad did nothing under CMD / PowerShell / Windows Terminal.** The `EDT_KPx` key codes were registered only through ncurses `define_key()`, inside `#if defined(NCURSES_VERSION)`. The Windows build links PDCurses, which never compiled that

block and never sees the `ESC O x` application-keypad sequences, so only the five keys that happened to have `KEY_A1/KEY_A3/KEY_B2/KEY_C1/KEY_C3` fallbacks (KP7, KP9, KP5, KP1, KP3) worked. Every other pad key fell through to `Undefined GOLD key`: KP0, KP2, KP4, KP6, KP8, KP., KP-, KP Enter, and KP/ KP* KP+.

- New `edt_normalize_key()` folds every platform spelling of the pad — the ncurses `define_key()` codes, the X/Open `KEY_A1–KEY_C3` virtual keypad, and the PDCurses `PAD0 / PADSTOP / PADENTER / PADMINUS / PADSLASH / PADSTAR / PADPLUS` family — onto the single `EDT_KPx` set, applied once at each `getch()`. The screen-mode handlers are now written purely in `EDT_KPx` terms and the per-handler fallback cases are gone.
- Verified end-to-end on Windows, not just by unit test: real Win32 `INPUT_RECORD` key events injected into a console input buffer, read back through PDCurses `getch()` and normalized — 20/20, including the negative cases proving the real arrow cluster is untouched (KP2 and Down arrow are both `VK_DOWN`, distinguished only by the `ENHANCED_KEY` flag).
- `SET KEYPAD PC` now also works on Windows: `KP/` → PF2 (HELP), `KP*` → PF3 (FNDNXT), `KP-` → PF4 (DEL L), `KP+` → DEL W, matching the ncurses `define_key()` block.
- **Num Lock must be OFF on Windows.** With Num Lock on, the Win32 console hands PDCurses plain ASCII `'0'–'9' / '.'` for the pad, indistinguishable from the top-row digits, so they insert as text. Documented in the reference (§7.1.4); it is a PDCurses limitation, not something EDT can override. The function-key row still gives the PF row: F1 = GOLD, F2–F4 = PF2–PF4.
- **KP/, KP* and KP+ are now bound in the default `SET KEYPAD EDT`**, not just under `SET KEYPAD PC`. These three have no DEC counterpart, so they take over what a PC keyboard cannot otherwise reach: `/` → PF2 (HELP), `*` → PF3 (FNDNXT), and `+` → **DEL C**, the DEC pad's comma-key function — a PC pad has no comma key, so DEL C was previously unreachable from the keypad. `KP-` keeps its DEC meaning of DEL W. `SET KEYPAD PC` is unchanged: it moves the whole PF row onto `/ * -` and keeps DEL W on `+` (reference §7.1.3).

Screen mode — key identification

- `Undefined GOLD key` now names the key it could not bind, e.g. `Undefined GOLD key: KP/` (code 458 / 0x1CA), reusing the `-d` decoder. Previously the message was the same for every unbound key, which is what made the broken Windows map hard to pin down.
- (Reminder — this already existed: `-d / -k / /DEBUG` shows the decoded name and code of every key pressed on the status line.)

Search

- **Fixed: `TOP` did not reset the `FIND / FNDNXT` search point.** `find_next()` always started the forward scan at `cursor_col_ + 1`, so a match starting at the cursor was skipped. After `TOP`, `FIND "foo"` on a buffer whose line 1 began with `foo` reported line 3. The `+1` now applies only when the cursor is still parked on the previous hit (tracked by position *and* needle), so repeated `FNDNXT` still advances. `TOP` and `BOTTOM` additionally clear that state, so either reliably resets the search point.
- `BOTTOM` did **not** have the mirror-image bug — the backward scan was already exclusive of the cursor — but it now clears the same state for symmetry.

Search — no more wrap-around (behaviour change)

- **FIND / FNDNXT no longer wrap**, matching OpenVMS EDT's default `SET SEARCH UNBOUNDED :` the scan covers only the buffer between the cursor and the relevant end, then stops. Previously a forward miss restarted from `(0,0)` and a backward miss from the end of the buffer, so a search never reported a miss while any occurrence existed anywhere. Use `TOP / BOTTOM` to rescan from the other end.
- **A missed search now says so.** In line mode a failed `FIND / FNDNXT` previously printed the *current* line, exactly as a successful find does — the miss was invisible. Both now print `String was not found` (the OpenVMS wording) and leave the cursor where it was. `find_next()` returns a bool so callers can tell the two apart.
- Migration note: a forward `FIND` from `BOTTOM` that used to return the first match in the buffer now reports `String was not found`.
- Regression suite updated for the new semantics and extended: **210 tests, all passing** (was 207).

V1.05-0 — 2026-07-17

Licensing made optional + splash-once startup, from user field feedback.

Licensing / startup

- **S7SECURITY.INI is now OPTIONAL** — EDT runs whether or not a security file is present. The editor no longer refuses to start when the file is missing or unreadable; the old `edt: security file not found` hard-exit is gone.
- **Splash shown once, then suppressed** — on first launch (no `splash=off` flag present) the branded splash shows once for its usual duration, after which EDT writes a plain-text `S7SECURITY.INI` containing `splash=off` at the resolved path (`$S7SECURITY`, else `$HOME/S7SECURITY.INI`). Subsequent launches read that flag and skip the splash. Delete the file (or set `splash=on`) to see the splash again.
- **Legacy license blob still honoured** — an existing encrypted `S7SEC1` blob is read tolerantly to preserve the licensed name/email on the splash, but it is no longer required and is replaced by the plain `splash=off` flag once the splash has been shown. `s7security/mksecurity` and `s7licdb` still generate encrypted blobs (now effectively single-use).
- Unlicensed splash drops the "licensed to ..." line and shows the plain `(c) Sector7 USA LLC EDT` banner.

V1.04-0 — 2026-07-16

Screen-mode usability + documentation pass from user field feedback.

Screen mode

- **GOLD echo** — after a GOLD chord the status line now shows the resolved function (e.g. `PASTE`, `OPEN LINE`, `BOTTOM`) instead of leaving the literal `GOLD` prompt. (`gold_function_name()` / `handle_gold_key`)

- **Debug key display** — new `-d / -k` (also `/DEBUG`) switch shows the decoded name and raw code of the last key pressed on the status line (e.g. `KEY: PF1/F1 (code 265 / 0x109)`), for mapping foreign keyboards and Num Lock.
- **SET KEYPAD PC** — maps a PC numeric keypad's top row (`/ * -`) onto PF2/PF3/PF4 in screen mode (PuTTY application-keypad convention); DEL W moves to the PC `+` key. Default `SET KEYPAD EDT` keeps strict DEC mapping (keypad `-` = DEL W).

HELP / docs

- **HELP screen ASCII fix** — replaced Unicode em-dash / arrow glyphs that rendered as garbage ("@"-like) characters on non-UTF-8 terminals.
- **Reference §7.1 rewritten** — now shows both a **VT100/VT220** and a **PC** keypad layout, each key with KeyID / normal / GOLD function on separate lines, plus Num Lock → PF1 (GOLD) guidance.
- **PDF code blocks** — light background instead of dark navy, so fenced blocks (including the §7.1 keypad diagram) are legible in print / Adobe.

V1.03-0 — 2026-07-15

Fidelity close-out: former PARTIAL / MISSING / deferred RMS host stubs.

Partials → faithful

- Wildcards: VMS `%` matches like `?` (single char)
- `SET LINES n` clamps screen text window; `SET TRUNCATE` clips horizontally (no soft-wrap scroll)
- `SET PARAGRAPH WPS|NOWPS` changes FILL joining; `SET TEXT FORMFEED` used in TYPE
- `SET TERMINAL` updates `SHOW + TERM`; `SET KEYPAD WPS` reports WPS (EDT GOLD map)
- `RESEQUENCE /DUPLICATE` uses increment 0 (same sequence on all lines)
- `HELP / SET HELP file`; topics XLATE RETAIN RANGE FILES JOURNAL
- `-journal= / /JOURNAL=`; text journal host model documented

Missing verbs

- `XLATE, RETAIN / STORE TEXT, RANGE sticky, FILES, .+N/.-N, SUBSTITUTE/old/new/N`

Host RMS / versions

- `SET RMS FIXED n|VARIABLE / SHOW RMS` on WRITE/EXIT
- `SET VERSIONING / EDT_VMS_VERSIONS → ;n` sibling saves (POSIX approx)

Soft residue

- Text journal ≠ binary OVMS; RMS/`;n` not Files-11

V1.02-0 — 2026-07-15

Closing pass for identified OVMS fidelity gaps (**RMS** / **;n** **versioning deferred** at the time).

Line mode

- `WRITE file [range] [BUFFER name] range form`
- Multiline `INSERT` until Ctrl/Z, `^Z`, or `.`
- Line-mode `TAB` (spaces to next stop)
- Ctrl/C abort (`*Abort*`) on TYPE / FIND / SUBSTITUTE loops
- `/BRIEF[:n]` for TYPE / FIND
- `SET SEARCH WORD / BEGIN / END` wired into FIND
- `RESEQUENCE /SEQUENCE=start:incr` with 8-column `NNNNN.00` prefixes
- `BELL, DATE, TAB ADJUST, SUBSTITUTE/old/new/, XLATE stub` (from V1.01+)

Screen / keypad / nokeypad

- `SET CURSOR` soft scroll margins applied
- LK201: PgUp/PgDn, Insert→PASTE, Find→FNDNXT, Select, Command→prompt
- Ctrl/K interactive DEFINE KEY; GOLD+Ctrl/K → DEL EOL
- Ctrl/C clears GOLD / select in screen mode
- **NOKEYPAD** mode + inline `CHANGE ;cmds`
- Nokeypad alphabet: C/W/L/EOL/BOL/PAGE, ADV/BACK, DC/DW/DL, SEL/CUT/PASTE/APPEND, TOP/BOTTOM, FIND, INSERT...ESC, **CHGC/CHNGCASE, CLSS/RESET, EX/EXIT/EXT**

Invocation / journal / HELP

- `-output= / /OUTPUT=, -readonly / /READ_ONLY, -recover / /RECOVER, /STAY`
- Text `.jou` append; recover replay; **delete .jou on clean EXIT**
- `HELP` topics: SET, SHOW, CHANGE, KEYPAD, NOKEYPAD, VERSION
- Release banner: `V1.02-0 + Release date: 2026-07-15`

V1.01-0 — 2026-07-15

First numbered public release identity + SET/SHOW surface expansion.

- Release identity constants + `SHOW VERSION` / `VERSION` / `HELP` / usage banners
- SET/SHOW: AUTOREPEAT, CASE, COMMAND, CURSOR, FNF, HELP, KEYPAD, LINES, PARAGRAPH, REPEAT, SCREEN, SUMMARY, TERMINAL, TEXT, TRUNCATE, FILES, MODE
- `SUBSTITUTE/old/new/` delimiters; TAB ADJUST; BELL; DATE; RESEQUENCE soft-ack
- GOLD digit-repeat; SPECINS decimal ASCII; Ctrl/D direction toggle
- GOLD+PF2 BOTTOM; GOLD+Enter SUBS; KP0 LINE; Ctrl/J LINEFEED
- Minimal journal append + `-recover`
- CLI `-readonly`, `-output=`

V1.00-1 — earlier (pre-version-field)

Baseline Sector7 EDT in `edt.cpp`: line + CHANGE modes, named buffers, SELECT model, FIND wildcards (`%/*`), DEFINE KEY/MACRO, UNDO/REDO snapshots, core keypad map, `-command / EDT_INI`.

Sector7 USA LLC — EDIT/EDT for Linux and Windows