

EDT — Change Log (V1.11-0)

Sector7 USA LLC · EDIT/EDT for Linux and Windows

September 2026 · V1.11-0

Table of contents

EDT Change Log

V1.11-0: 2026-09-11

EDIT/EDT/CMD=filename, the startup command file (field request)

V1.10-0 — 2026-07-24

VMS ;n file versioning (VX/RT-driven)

V1.09-0 — 2026-07-23

Screen mode — prompts

Screen mode — keypad SUBS (GOLD+ENTER)

Screen mode — key-function echo

Errors

Startup splash

Docs

V1.08-0 — 2026-07-23

Startup splash

V1.07-0 — 2026-07-21

Startup splash

V1.06-0 — 2026-07-20

Startup splash

Screen mode — Windows numeric keypad

Screen mode — key identification

Search

Search — no more wrap-around (behaviour change)

V1.05-0 — 2026-07-17

Licensing / startup

V1.04-0 — 2026-07-16

Screen mode

HELP / docs

V1.03-0 — 2026-07-15

Partials → faithful

Missing verbs

Host RMS / versions

Soft residue

V1.02-0 — 2026-07-15

Line mode

Screen / keypad / nokeypad

Invocation / journal / HELP

V1.01-0 — 2026-07-15

V1.00-1 — earlier (pre-version-field)

EDT Change Log

Product: Sector7 EDIT/EDT (`edt.cpp`)

Current release: V1.11-0

Release date: 2026-09-11

Compared against: OpenVMS EDT V3.13 on host `t86` (OpenVMS x86_64 V9.2-3); V1.11-0 measured on host `ia64` (OpenVMS IA64 V8.4-2L1)

This file is the running release log. Recreate or extend it from:

```
git log --edt/ --oneline
# plus the Release identity block in edt.cpp (EDT_VERSION_* / EDT_RELEASE_DATE)
```

Bump `EDT_VERSION_MAJOR` / `MINOR` / `EDIT` and `EDT_RELEASE_DATE` in `edt.cpp` on every public release; `SHOW VERSION` / `VERSION` print both.

V1.11-0: 2026-09-11

EDIT/EDT/COMMAND=file, the startup command file (field request)

Request: `edit/edt/command=daily daily.lis` with a `daily.edt` of INCLUDE, ranged SUBSTITUTE and EXIT lines. Every behaviour below was measured on real OpenVMS EDT (V3.13, OpenVMS IA64 V8.4-2L1, host `ia64`) with the same fixture files, then reproduced. The customer's file now produces the identical 9-line result and the identical output (`<file> 9 lines`, then `[EOB]`).

- **/COMMAND=file is accepted on the command line**, next to the existing `-command file` / `-command=file`, and so is `-command:file`, the form the VX/RT DCL EDIT verb emits. `/NOCOMMAND` and `-nocommand` run no startup command file at all. `-read_only` (the DCL form) is accepted like `-readonly`; `-output:` and `-journal:` like their `=` forms.
- **The command file replaces EDT.INI** for that run, as on OpenVMS (measured: an `EDTINI.EDT` in the directory is not read when `/COMMAND=x` is given; it is read for a bare `/COMMAND`). Before, the `-command` file ran after EDT.INI.
- **Default file type .edt**: `/COMMAND=daily` opens `daily.edt` (`daily.EDT`, then a bare `daily`, are tried on a case-sensitive host).
- **A missing command file aborts the editor** before the input file is opened, with the OpenVMS text and exit status 4: `Command file does not exist / File name:daily / %RMS-E-FNF, file not found / %EDT-F-EDITORABO, Editor aborted`. Before: `?Unable to open command file` and the session continued.
- **EXIT inside the file** saves, prints the exit message and then `[EOB]` (OpenVMS still types the "current line" after the file, and the buffer is gone by then). **QUIT inside the file** prints an empty line and then the current line. A file that ends without either types the current line and prompts, as before.
- **INCLUDE** prints nothing on success (it printed `N lines included`) and leaves the current line on the line it was on, so successive INCLUDEs land in order (they landed reversed). A missing file reports the OpenVMS three-line `Include file does not exist` message and processing continues.
- **Ranged SUBSTITUTE** `S/old/new/range`, with any prefix of the verb (`S`, `SU`, `SUB` ...): every occurrence on every line of the range is replaced, each changed line is typed unless `/NOTYPE`, and the current line becomes the first line of the range whether or not anything matched. A trailing number is a line number (`S/a/b/2` changes line 2), not a repeat count as this build previously read it. Interactively the command reports `n substitution(s)` or `No substitutions`; from a startup command file it reports nothing (both measured). `S//new/` reuses the current search string. Qualifiers are recognised only after the third delimiter, so `S/x/save/` no longer loses its replacement text to `/SAVE`.
- **Range keyword abbreviations**: `E/EN` (END), `B`, `BE` ... (BEGIN), `WH`, `WHO` ... (WHOLE), `R`, `RE` ... (REST), `LA/LAS` (LAST); a lone `L` is rejected, as on OpenVMS. `TYPE END` (and `T E`) types `[EOB]`, not the last line.
- **VX/RT DCL (dcl/EDIT.cxx)**: the EDIT verb now passes `/COMMAND=`, `/NOCOMMAND`, `/OUTPUT=`, `/JOURNAL=`, `/READ_ONLY` and `/RECOVER` to any editor configured as `edt` or `edt.exe` (with or without a path). Before, they were passed only when the `EDT` config value was

literally `edt`, so with the usual `EDT edt.exe` every qualifier was silently dropped. The command file is resolved like the input file, through the runtime's actual-file lookup with the `.EDT` default type (DCL upper-cases the value to `DAILY`; the lookup still finds `daily.edt`); the old check tested the input file instead and, with `EDT edt`, aborted every `/COMMAND= edit` with `File name:DAILY`. A bare `/COMMAND` passes nothing, so the editor uses its own startup file. Verified end to end on `rh8x` (2026-09-14) with a `dcl` built from this tree and `EDT edt.exe: edit/edt/command=daily daily.lis` produces the same nine lines and the same two output lines as OpenVMS. The installed July runtime there has no text for the EDT facility, so the abort status prints as `%NONAME-F-NOMSG`, Message number `008580a4` rather than `%EDT-F-EDITORABO`, Editor aborted; `utl/messages.msg` defines the text, a current runtime build was not tried. `EDIT/TPU` (`DO_EDIT_USING_TPU`) was not changed.

- Tests: `edt_regression.sh` section 33 (35 checks against the ia64 measurements); `cov_substitute_count` and `test_brief_type` in the Python suite updated to the measured semantics; three existing checks now ignore the QUIT trailer; `TYPE END` now expects `[EOB]`.

Known divergences left as they were (outside this request; all measured on `ia64` in the same session, listed so nobody mistakes them for done):

- Line numbers are positional here; OpenVMS keeps sequence numbers, so lines INCLUDED in front of line 1 show as `0.1`, `0.2` there and as `1`, `2` here. The typed-line format is `1 text` here and `1 text` there.
- Error text: OpenVMS echoes the offending command, a caret line and `Unrecognized command`; this build prints `?Unrecognized command: ...`.
- `TYPE range` moves the current line to the first line of the range on OpenVMS; here it does not move it. `LAST` semantics differ.
- The single-form `S/old/new/` still advances to the next match and types that line; OpenVMS types the changed line and reports `1 substitution`.
- `QUIT` prints an empty line on OpenVMS; here it prints `Changes discarded` when the buffer was modified.
- EDT.INI is still replayed silently with EXIT/QUIT ignored (§9.2); on OpenVMS EDTINI.EDT is the same mechanism as `/COMMAND`, is looked up in the current directory only (not `SYSS$LOGIN`), and `SYSS$LIBRARY:EDTSYS.EDT` is read first. Errors during EDT.INI replay go to `startup_warnings_`, which nothing prints.
- The line-mode banner still echoes `$ EDIT/EDT file` before the current line; OpenVMS prints only the current line.
- `SET QUIET` here suppresses the banner and all command output; on OpenVMS it only silences the bell. A customer command file containing `SET QUIET` (the first example in the OpenVMS manual) would stop displaying lines.
- `-nooutput`, `-nojournal` and `-nobackup` from the DCL verb are still accepted and ignored.

V1.10-0 — 2026-07-24

VMS ;n file versioning (VX/RT-driven)

- **EDT/VERSIONING in the VX/RT config file turns versioning on.** EDT reads the key straight from the config file — `$VX_CONFIG`, then `$RT_CONFIG`, then the VMS `SYS$MANAGER` config (`$HOME/SYS0/SYSMGR/CONFIG.INI`, since `SYS$SYSROOT` is rooted at `$HOME/SYS0`), then the `$VXREL / /etc` fallbacks. `Y/YES/ON/TRUE/1` (any case) turn it on; `N/OFF/0` or an absent key leave it off. **The value is parsed from the file directly, not via the runtime `vxrt_config()`** — that call pulls in the VX/RT device-table init, which aborts a plain editor process where SysV shared memory is not set up (notably macOS).
- **Opening resolves the version (RMS-style).** With versioning on, `edt t.txt` opens the **highest existing version** (`t.txt;12`); `edt t.txt;1` opens version 1 (the bare `t.txt`); `edt t.txt;N` opens that version. The resolved name becomes the buffer's, so a save versions forward from it.
- **Saving writes the next version.** A **brand-new file** is written as the bare name — that is version 1 (`edt t.txt` on a missing file creates `t.txt`, not `t.txt;2`). A bare name whose family already exists writes the next version above the highest (`t.txt` present → `t.txt;2`, up to `;12` → `;13`); a `;N` name writes `;N+1`. A guard steps past any existing sibling so a save never clobbers a version.
- **SET VERSIONING ON|OFF in EDT.INI** turns versioning on/off, and is honoured *before* the file is opened so the open resolves to the highest version. The interactive `SET/SHOW VERSIONING` and `EDT_VMS_VERSIONS` environment force-on also drive the same flag.
- **S7SECURITY.INI versioning=on|off** is the fallback when no VX/RT config is found (default off).
- **A deployed VX/RT runtime suppresses the startup splash.** Detected by a presence-only `dlopen` of `libvxrtl.so` (no `vxrt_config()` call), or by finding `EDT/VERSIONING` in the config.
- Shared with **VX-TPU** (`TPU/VERSIONING`) through `s7security/s7_vxconfig.hpp` so both editors behave identically. The reference's "`;n` versioning deferred" notes are corrected: it is implemented (§13.6).

V1.09-0 — 2026-07-23

The rest of the July 22 field report: prompt completion, real keypad SUBS, the splash colour bleed, the key-function echo, and the error bell.

Screen mode — prompts

- **The keypad ENTER now completes every screen-mode prompt** (`Search for:`, `Command:`, `SPECINS`, `Nokeypad:`, `DEFINE KEY`). The prompts were read with curses `getnstr()`, which only recognises the RETURN key; they are now read key-by-key so the keypad keeps decoding.
- **ADVANCE / BACKUP complete the Search for: prompt**, set the search direction, and start the search — the OpenVMS EDT convention. Backspace and Ctrl/U edit the pending input.

Screen mode — keypad SUBS (GOLD+ENTER)

- **SUBS now requires the cursor to be on a FIND/FNDNXT hit**, refusing with `No select range active` (and the bell) anywhere else. It previously jumped ahead and substituted the next match — dangerous, and not what the OpenVMS EDT manual documents.
- **After the last occurrence is substituted, SUBS reports `String was not found`** (with the bell). The message was being posted by the search and then immediately overwritten by `Substituted`, so a rapid SUBS sequence gave no cue that it had run out of matches.
- The replacement text is the PASTE buffer, as before (and as on VMS).

Screen mode — key-function echo

- **The `[FUNCTION]` echo moved to the status line.** The invoked function (`[GOLD]` , `[CUT]` , `[SUBSTITUTE]` , ...) is shown on the status line instead of the message line, so it no longer collides with prompts and errors. Plain keypad functions now echo too (previously only GOLD chords did); typing ordinary text clears the echo.

Errors

- **Screen-mode errors ring the terminal bell**, matching OpenVMS EDT (`String was not found` , `No select range active` , `Undefined GOLD key` , select-state errors). **SET QUIET suppresses the bell** — its actual OpenVMS meaning — in addition to the startup banner. Line-mode and piped output remain byte-clean; the bell only sounds while the curses screen is live.

Startup splash

- **Fixed: the splash's blue background bled into a later CHANGE screen.** The splash sets a blue `bkgd()` ; the curses screen persists across `endwin()` , so screen mode inherited blue (line mode, being stdout, stayed black — the reported "black line mode, blue change mode"). The background is reset when the splash is dismissed.

Docs

- §7.1.2: macOS Terminal.app cannot transmit `KP/` or `KP*` even in application-keypad mode (they arrive as plain characters) — the PF2/PF3 mappings need iTerm2 ("Application keypad allowed") or PuTTY.
- §7.3/§8.8: keypad SUBS gating, prompt completion, `[FUNCTION]` echo, bell/ `SET QUIET` documented; stale `GOLD+ENTER = newline` rows fixed.

V1.08-0 — 2026-07-23

From field feedback on the V1.06-0 splash (too much text to read on a timer; no indication it would never come back).

Startup splash

- **The initial splash no longer times out.** The first-run splash (and `splash=on`) stays up until the user hits ENTER — there is no way to miss it, and no rush to read it. An explicit `splash=<n>` (or a licensed duration) remains timed, with ENTER dismissing early.
- **The splash now says it is shown once.** Two lines above the prompt: "This screen is shown ONCE and will not appear again" and how to re-enable it (`splash=on` in `S7SECURITY.INI`).
- **The notice and ENTER prompt are always visible.** The splash body is taller than an 80x24 terminal; the final lines now anchor to the bottom of the screen instead of being clipped off — previously a small terminal showed no prompt at all.
- Vertical centering uses the real content height (~40 rows, was a stale 28), fixing the bottom-heavy layout reported on tall windows.
- Headless / scripted runs (stdin not a terminal) still start instantly: end of input dismisses the splash rather than blocking.

V1.07-0 — 2026-07-21

Startup-splash polish, continuing from field feedback that the splash was either too brief to read or (once shown) hard to bring back.

Startup splash

- **Default duration is now 15 seconds** (was 5, briefly 10). A fresh install with no `S7SECURITY.INI`, or `splash=on`, holds the branded screen for 15 seconds so it can actually be read.
- **"Hit ENTER to continue"** — the splash now waits for ENTER to dismiss early, and the prompt says so. Other keys are ignored so a stray keystroke doesn't clear it; the timeout still auto-dismisses if no one is watching.
- **`splash=<n>` is clamped to 0..15 seconds.** A value above 15, or a negative one, is treated as 15 rather than rejected — a typo costs a few seconds, not a wedged terminal. (The previous ceiling was one hour, so a fat-fingered `splash=99999` could appear to hang.) `splash=0` == `splash=off`.
- **The persisted flag is now `splash=0`** (was `splash=off`). After the splash has shown once, the auto-written `S7SECURITY.INI` carries `splash=0`; `off` is still accepted on read for existing installs.
- Non-numeric junk (`splash=abc`) still warns on stderr and falls back to the default rather than being silently treated as "off".

V1.06-0 — 2026-07-20

Field bug report: Windows screen-mode keypad, the search start point, and a splash you could never see for long enough to read.

Startup splash

- **`splash=<n>` sets the splash duration in seconds.** `S7SECURITY.INI` previously understood only on/off, so the only way to re-show the splash was to delete the file and watch it for whatever the

built-in 5 seconds allowed. `splash=15` now holds it for 15 seconds; the count overrides both the licensed duration and the built-in default. `splash=0` == `splash=off`, `splash=on` uses the default, and a keypress still dismisses early.

- Unrecognised `splash=` values are now reported on stderr naming the value instead of being silently treated as "not off".
- The auto-generated `S7SECURITY.INI` documents the syntax in its header comment. Behaviour is unchanged in one respect: the splash is still shown **once** and the file reverts to `splash=off` afterwards.
- Shared with VX-TPU via `s7security/` — same syntax, same precedence.

Screen mode — Windows numeric keypad

- **Fixed: most of the numeric keypad did nothing under CMD / PowerShell / Windows Terminal.** The `EDT_KPx` key codes were registered only through ncurses `define_key()`, inside `#if defined(NCURSES_VERSION)`. The Windows build links PDCurses, which never compiled that block and never sees the `ESC O x` application-keypad sequences, so only the five keys that happened to have `KEY_A1`/`KEY_A3`/`KEY_B2`/`KEY_C1`/`KEY_C3` fallbacks (KP7, KP9, KP5, KP1, KP3) worked. Every other pad key fell through to `Undefined GOLD key`: KP0, KP2, KP4, KP6, KP8, KP., KP-, KP Enter, and KP/ KP* KP+.
- New `edt_normalize_key()` folds every platform spelling of the pad — the ncurses `define_key()` codes, the X/Open `KEY_A1`–`KEY_C3` virtual keypad, and the PDCurses `PAD0` / `PADSTOP` / `PADENTER` / `PADMINUS` / `PADSLASH` / `PADSTAR` / `PADPLUS` family — onto the single `EDT_KPx` set, applied once at each `getch()`. The screen-mode handlers are now written purely in `EDT_KPx` terms and the per-handler fallback cases are gone.
- Verified end-to-end on Windows, not just by unit test: real Win32 `INPUT_RECORD` key events injected into a console input buffer, read back through PDCurses `getch()` and normalized — 20/20, including the negative cases proving the real arrow cluster is untouched (`KP2` and Down arrow are both `VK_DOWN`, distinguished only by the `ENHANCED_KEY` flag).
- `SET KEYPAD PC` now also works on Windows: `KP/` → PF2 (HELP), `KP*` → PF3 (FNDNXT), `KP-` → PF4 (DEL L), `KP+` → DEL W, matching the ncurses `define_key()` block.
- **Num Lock must be OFF on Windows.** With Num Lock on, the Win32 console hands PDCurses plain ASCII `'0'`–`'9'` / `'.'` for the pad, indistinguishable from the top-row digits, so they insert as text. Documented in the reference (§7.1.4); it is a PDCurses limitation, not something EDT can override. The function-key row still gives the PF row: F1 = GOLD, F2–F4 = PF2–PF4.
- **`KP/`, `KP*` and `KP+` are now bound in the default `SET KEYPAD EDT`**, not just under `SET KEYPAD PC`. These three have no DEC counterpart, so they take over what a PC keyboard cannot otherwise reach: `/` → PF2 (HELP), `*` → PF3 (FNDNXT), and `+` → **DEL C**, the DEC pad's comma-key function — a PC pad has no comma key, so DEL C was previously unreachable from the keypad. `KP-` keeps its DEC meaning of DEL W. `SET KEYPAD PC` is unchanged: it moves the whole PF row onto `/ * -` and keeps DEL W on `+` (reference §7.1.3).

Screen mode — key identification

- `Undefined GOLD key` now names the key it could not bind, e.g. `Undefined GOLD key: KP/ (code 458 / 0x1CA)`, reusing the `-d` decoder. Previously the message was the same for every unbound key, which is what made the broken Windows map hard to pin down.
- (Reminder — this already existed: `-d / -k / /DEBUG` shows the decoded name and code of every key pressed on the status line.)

Search

- **Fixed: `TOP` did not reset the `FIND / FNDNXT` search point.** `find_next()` always started the forward scan at `cursor_col_ + 1`, so a match starting at the cursor was skipped. After `TOP`, `FIND "foo"` on a buffer whose line 1 began with `foo` reported line 3. The `+1` now applies only when the cursor is still parked on the previous hit (tracked by position *and* needle), so repeated `FNDNXT` still advances. `TOP` and `BOTTOM` additionally clear that state, so either reliably resets the search point.
- `BOTTOM` did **not** have the mirror-image bug — the backward scan was already exclusive of the cursor — but it now clears the same state for symmetry.

Search — no more wrap-around (behaviour change)

- **`FIND / FNDNXT` no longer wrap**, matching OpenVMS EDT's default `SET SEARCH UNBOUNDED`: the scan covers only the buffer between the cursor and the relevant end, then stops. Previously a forward miss restarted from `(0,0)` and a backward miss from the end of the buffer, so a search never reported a miss while any occurrence existed anywhere. Use `TOP / BOTTOM` to rescan from the other end.
- **A missed search now says so.** In line mode a failed `FIND / FNDNXT` previously printed the *current* line, exactly as a successful find does — the miss was invisible. Both now print `String was not found` (the OpenVMS wording) and leave the cursor where it was. `find_next()` returns a bool so callers can tell the two apart.
- Migration note: a forward `FIND` from `BOTTOM` that used to return the first match in the buffer now reports `String was not found`.
- Regression suite updated for the new semantics and extended: **210 tests, all passing** (was 207).

V1.05-0 — 2026-07-17

Licensing made optional + splash-once startup, from user field feedback.

Licensing / startup

- **`S7SECURITY.INI` is now `OPTIONAL`** — EDT runs whether or not a security file is present. The editor no longer refuses to start when the file is missing or unreadable; the old `edt: security file not found` hard-exit is gone.
- **Splash shown once, then suppressed** — on first launch (no `splash=off` flag present) the branded splash shows once for its usual duration, after which EDT writes a plain-text `S7SECURITY.INI` containing `splash=off` at the resolved path (`$S7SECURITY`, else `$HOME/S7SECURITY.INI`).

Subsequent launches read that flag and skip the splash. Delete the file (or set `splash=on`) to see the splash again.

- **Legacy license blob still honoured** — an existing encrypted `S7SEC1` blob is read tolerantly to preserve the licensed name/email on the splash, but it is no longer required and is replaced by the plain `splash=off` flag once the splash has been shown. `s7security/mksecurity` and `s7licdb` still generate encrypted blobs (now effectively single-use).
- Unlicensed splash drops the "licensed to ..." line and shows the plain `(c) Sector7 USA LLC EDT` banner.

V1.04-0 — 2026-07-16

Screen-mode usability + documentation pass from user field feedback.

Screen mode

- **GOLD echo** — after a GOLD chord the status line now shows the resolved function (e.g. `PASTE`, `OPEN LINE`, `BOTTOM`) instead of leaving the literal `GOLD` prompt. (`gold_function_name()` / `handle_gold_key`)
- **Debug key display** — new `-d` / `-k` (also `/DEBUG`) switch shows the decoded name and raw code of the last key pressed on the status line (e.g. `KEY: PF1/F1 (code 265 / 0x109)`), for mapping foreign keyboards and Num Lock.
- **SET KEYPAD PC** — maps a PC numeric keypad's top row (`/ * -`) onto PF2/PF3/PF4 in screen mode (PuTTY application-keypad convention); `DEL W` moves to the PC `+` key. Default `SET KEYPAD EDT` keeps strict DEC mapping (keypad `-` = `DEL W`).

HELP / docs

- **HELP screen ASCII fix** — replaced Unicode em-dash / arrow glyphs that rendered as garbage ("`@`"-like) characters on non-UTF-8 terminals.
- **Reference §7.1 rewritten** — now shows both a **VT100/VT220** and a **PC** keypad layout, each key with `KeyID` / `normal` / `GOLD` function on separate lines, plus Num Lock → PF1 (`GOLD`) guidance.
- **PDF code blocks** — light background instead of dark navy, so fenced blocks (including the §7.1 keypad diagram) are legible in print / Adobe.

V1.03-0 — 2026-07-15

Fidelity close-out: former **PARTIAL** / **MISSING** / deferred **RMS** host stubs.

Partials → faithful

- Wildcards: `VMS %` matches like `?` (single char)
- `SET LINES n` clamps screen text window; `SET TRUNCATE` clips horizontally (no soft-wrap scroll)
- `SET PARAGRAPH WPS|NOWPS` changes `FILL` joining; `SET TEXT FORMFEED` used in `TYPE`
- `SET TERMINAL` updates `SHOW + TERM`; `SET KEYPAD WPS` reports `WPS` (`EDT GOLD` map)
- `RESEQUENCE` / `DUPLICATE` uses increment 0 (same sequence on all lines)

- `HELP / SET HELP file`; topics XLATE RETAIN RANGE FILES JOURNAL
- `-journal= / /JOURNAL=`; text journal host model documented

Missing verbs

- `XLATE, RETAIN / STORE TEXT, RANGE sticky, FILES, .+N/ .-N, SUBSTITUTE/old/new/N`

Host RMS / versions

- `SET RMS FIXED n|VARIABLE / SHOW RMS` on WRITE/EXIT
- `SET VERSIONING / EDT_VMS_VERSIONS` → `;n` sibling saves (POSIX approx)

Soft residue

- Text journal ≠ binary OVMS; RMS/`;n` not Files-11

V1.02-0 — 2026-07-15

Closing pass for identified OVMS fidelity gaps (**RMS** / **;n** **versioning deferred** at the time).

Line mode

- `WRITE file [range] [BUFFER name] range form`
- Multiline `INSERT` until Ctrl/Z, `^Z`, or `.`
- Line-mode `TAB` (spaces to next stop)
- Ctrl/C abort (`*Abort*`) on TYPE / FIND / SUBSTITUTE loops
- `/BRIEF[:n]` for TYPE / FIND
- `SET SEARCH WORD / BEGIN / END` wired into FIND
- `RESEQUENCE /SEQUENCE=start:incr` with 8-column `NNNNN.00` prefixes
- `BELL, DATE, TAB ADJUST, SUBSTITUTE/old/new/, XLATE stub` (from V1.01+)

Screen / keypad / nokeypad

- `SET CURSOR` soft scroll margins applied
- LK201: PgUp/PgDn, Insert→PASTE, Find→FNDNXT, Select, Command→prompt
- Ctrl/K interactive DEFINE KEY; GOLD+Ctrl/K → DEL EOL
- Ctrl/C clears GOLD / select in screen mode
- **NOKEYPAD** mode + inline `CHANGE ;cmds`
- Nokeypad alphabet: C/W/L/EOL/BOL/PAGE, ADV/BACK, DC/DW/DL, SEL/CUT/PASTE/APPEND, TOP/BOTTOM, FIND, INSERT...ESC, **CHGC/CHNGCASE, CLSS/RESET, EX/EXIT/EXT**

Invocation / journal / HELP

- `-output= / /OUTPUT=, -readonly / /READ_ONLY, -recover / /RECOVER, /STAY`
- Text `.jou` append; recover replay; **delete .jou on clean EXIT**
- `HELP` topics: SET, SHOW, CHANGE, KEYPAD, NOKEYPAD, VERSION
- Release banner: `V1.02-0 + Release date: 2026-07-15`

V1.01-0 — 2026-07-15

First numbered public release identity + SET/SHOW surface expansion.

- Release identity constants + `SHOW VERSION` / `VERSION` / `HELP` / usage banners
- SET/SHOW: AUTOREPEAT, CASE, COMMAND, CURSOR, FNF, HELP, KEYPAD, LINES, PARAGRAPH, REPEAT, SCREEN, SUMMARY, TERMINAL, TEXT, TRUNCATE, FILES, MODE
- `SUBSTITUTE/old/new/` delimiters; TAB ADJUST; BELL; DATE; RESEQUENCE soft-ack
- GOLD digit-repeat; SPECINS decimal ASCII; Ctrl/D direction toggle
- GOLD+PF2 BOTTOM; GOLD+Enter SUBS; KP0 LINE; Ctrl/J LINEFEED
- Minimal journal append + `-recover`
- CLI `-readonly`, `-output=`

V1.00-1 — earlier (pre-version-field)

Baseline Sector7 EDT in `edt.cpp`: line + CHANGE modes, named buffers, SELECT model, FIND wildcards (`%/*`), DEFINE KEY/MACRO, UNDO/REDO snapshots, core keypad map, `-command / EDT_INI`.

Sector7 USA LLC — EDIT/EDT for Linux and Windows