PLAN-06 - Frontend UX and Cross-Module Behavior

POS-DGFY - Global Location Switching | Plan v1.0 | Revision 2026-09-27

Field	Value
Project	POS-DGFY - Global Location Switching
Plan version	1.0
Section	PLAN-06 - Frontend UX and Cross-Module Behavior
Revision date	2026-09-27
Plan status	NOT EXECUTION READY
Purpose	Define how the global entry point, transition flow, context refresh, and requested modules behave on desktop and mobile.
Dependencies	PLAN-03 through PLAN-05; existing TerminalPage and TerminalOperationsWorkspace.

Navigation decision

Place Current Location in the global header on desktop and in the mobile sidebar/menu. Clicking it opens the governed flow. Keep the detailed Change Active Shift Location form inside Shift as the canonical workflow, not as a second implementation.

Context display

UI element	Display	Safety behavior
Global header	Operating location, terminal, and shift status.	Never imply that viewing a branch changes the register.
Location selector	Authorized destinations and read-only viewing choices.	Hide unauthorized options; still enforce on server.
Shift transition modal	Destination, terminal, closing cash, opening float, reason, notes.	Require preflight completion before submit.
Read-only banner	Viewing location and reason it is read-only.	Disable mutation and queue actions.
Loading state	Context transition in progress.	Block duplicate actions and stale navigation.
Error state	Permission, conflict, offline, or validation reason.	Offer recovery action without auto-takeover.

Operating switch workflow

```
Open Current Location
-> Run cart, payment, offline, permission, and terminal preflight
-> Select authorized destination location and terminal
-> Enter counted closing cash, opening float, reason, and notes
-> Submit idempotent shift transition
-> Refresh context and all dependent modules
-> Confirm destination operating context
```

Module behavior

Module	Operating location	Viewing location
Items / Add Item	Load branch stock, availability, visibility, and permitted branch operations.	Allow only authorized read/edit behavior defined by module permissions.
Sales / checkout	Use active shift, terminal, stock, parked sales, and queue.	No checkout or payment mutation.
Reports	Default to operating branch where relevant.	Allow authorized branch or multi-branch read-only filters.
Shifts	Owns transition, cash drawer, and terminal state.	Read-only monitoring only.
Settings	Load branch and terminal settings while preserving tenant settings.	Allow only permitted configuration viewing/editing.

Module	Operating location	Viewing location
Vouchers	Apply location eligibility and redemption location.	View definitions only if authorized.
Price lists	Load location assignment or override.	View permitted price configuration.
Affiliates	Record attribution and eligibility location.	Filter reporting by authorized location.
Audit	Write current operating context.	Filter the tenant-wide trail by authorized location.

Refresh and race handling

- Increment a context version before transition and abort or ignore old requests.
- Clear location-dependent caches and carts only according to the approved workflow.
- Refresh items, stock, queue, reports, shift, settings, vouchers, pricing, affiliate context, and audit filters after authoritative success.
- Do not refresh a module into a new location until the backend confirms the transition.

Responsive and accessibility requirements

- Desktop header selector and mobile sidebar selector expose the same permission-aware flow.
- Labels explicitly say Operating Location or Viewing Location.
- Focus moves into the transition dialog and returns to the trigger after close.
- Warnings are readable without color alone and controls expose disabled reasons.