Overlay Studio

Slint desktop instruction manual

This manual documents the current Slint desktop build: Design, Live, Remote, Animate, media import, custom fields, and recovery. Screenshots were captured from the native app. QR codes shown for pairing are examples only—always scan the fresh code from your running session.


Run the app with `cargo run --release --manifest-path desktop/slint/Cargo.toml`. Validate with `cargo test` and the Slint package tests.

Contents

1. Design workspace
2. Layers and appearance
3. Game setup: teams and clocks
4. Live desk and outputs
5. Custom live fields
6. Remote controller and QR pairing
7. Animation timeline
8. Event rules
9. Image and video import
10. Recovery after a crash

Design workspace

Open a project and stay in Design to build scoreboard canvases. Use Blank or Copy design for new layouts, then place text, shapes, images, and video from the Create palette.




11 slint designer

1. Choose a design in the left list, or create a blank canvas.
2. Select a creation tool, then click or drag on the canvas to place layers.
3. Use the inspector for precise geometry, colors, fonts, and live-value bindings.
4. Save the project with Save or Save as. Export design writes a reusable .scoredesign file.

Layers and appearance

Click a color swatch in the inspector to open the visual picker. Draft fills support opacity; team and remote button colors stay opaque.




18 slint color picker

1. Select a layer, then edit Fill/Stroke or Text color.
2. Drag the hue strip and color area, or choose a preset chip.
3. Confirm to apply, or Cancel to keep the previous color.
4. Hidden and Locked checkboxes protect layers during live shows.

Game setup: teams and clocks

In Live, open Game setup to add teams, scoring steps, and independent clocks. Create scoreboard builds an adaptive multi-team layout on the canvas.




15 slint clocks

1. Press Game setup, then Add team or Add clock.
2. Edit names, team colors, and scoring steps such as -1, +1, +5.
3. Set each clock’s reset time and count up/down mode.
4. Press Finish setup when operators should only adjust live scores and clocks.

Live desk and outputs

Live Desk combines scores, clocks, and output senders. Each output has a name, Syphon or NDI protocol, frame rate, and selected design.




14 slint live

1. Adjust scores with the step buttons under each team.
2. Start or pause clocks from the clock cards.
3. Configure an output, press Start output, then Take design when the canvas is ready.
4. Hide sends transparent frames; Stop removes the sender.

Custom live fields

Game setup can add custom live text fields. Bind design text layers to those fields so the same show data drives multiple canvases.




24 slint custom fields

1. In Game setup, enter a field name and add it.
2. In Design, select a text layer and choose the field in the live-value binding list.
3. Update the value from Live; bound layers refresh automatically.
4. Removing a field repairs bindings, cues, and remote buttons in one Undoable action.

Remote controller and QR pairing

Remote layout designs phone and iPad controls. Start remote control, scan the QR code on the same local network, then operate scores and clocks from the browser.




16 slint remote

1. Choose a local network address and press Start remote control.
2. Scan the QR code with the phone or iPad camera.
3. Drag buttons in the grid; use Build team controls for a full scoring set.
4. Press Stop remote / revoke QR when the session ends. Always scan a fresh QR from your own app.

Animation timeline

Animate provides a canvas preview, scrubber, and layer timeline. Keyframes store X/Y, size, rotation, opacity, and easing.




19 slint timeline

1. Select a layer track and add a pose at the playhead.
2. Edit transform fields or drag frames along the timeline.
3. Enable Loop for repeating motion; presets remain available for simple entrances.
4. Play, Pause, Restart, and Exit preview control playback without changing the live program.

Event rules

Events automate show responses. Rules can react to score changes or clock milestones and then replay animation, take a design, or set a live value.




20 slint events

1. In Animate, switch to Events and add a rule.
2. Choose the trigger, target field or clock, and the resulting action.
3. Enable the rule for automatic firing, or use Run cue now for a manual take.
4. Undo/Redo pauses clocks so restored state does not replay elapsed time.

Image and video import

Design imports PNG/JPEG images and short video clips. Video conversion uses a local FFmpeg install; playback does not require FFmpeg afterward.




22 slint media

1. Press Image / logo… or Video clip… in the Create palette.
2. Wait for preparation to finish; Cancel import stops an active conversion.
3. Imported assets travel inside .overlay and .scoredesign files.
4. Motion layers are limited to about 15 seconds with a preview ceiling during development.

Recovery after a crash

Autosave recovery lives in Application Support. On launch, Recover opens the draft as unsaved, Discard removes it, and Later keeps it for the next launch.



20 slint recovery

1. Relaunch Overlay Studio if it closed unexpectedly.
2. Choose Recover to inspect the draft, then Save when it looks correct.
3. Outputs, clocks, and remote control stay stopped after recovery.
4. Check crash.log in the Application Support folder if a Rust error was recorded.

Shortcuts and limits

Design tools: V select, R rectangle, O ellipse, T text, L line, Escape cancels a creation tool. Command-S saves, Command-Z / Shift-Command-Z undo and redo, Command-D duplicates. Command-1…4 switch Design, Live, Remote, and Animate.

Current limits include 32 teams, 16 clocks, 8 outputs, 64 designs, 100 remote buttons, and 1000 layers per canvas. Rehearse on the actual receiver hardware before a live event.