GSM 网关配置 SSH 反向连接

作用: 使公司内网工作机透过公网服务器访问客户内网的 GSM 网关,以便调试

(一)服务器配置

```
Openvox-Wireless-Gateway
   IP: 172.16.8.186
   Port: SSH 12345, Web Port 80
   Username: Web admin, SSH super
公网服务器
   IP: 106.185.43.194
   SSH Port: 22
   SSH Username: root
丁作机.
   IP: 172.16.8.180
```

(二)配置步骤

- 1) 端口映射(在 GSM 网关上进行操作) 1. 将网关上的 80 端口映射到公网服务器的 10241 端口 A. ssh -f -N -R 10241:localhost:80 root@106.185.43.194 -p 22 B. 需要输入公网服务器密码 2. 将网关上的 12345 端口映射到公网服务器的 10242 端口
 - A. ssh -f -N -R 10242:localhost:12345 root@106.185.43.194 -p 22

 - B. 需要输入公网服务器密码

```
root@Openvox-Wireless-Gateway:~# ssh -f -N -R 10241:localhost:80 root@106.185.43.194 -p 22
root@Openvox-Wireless-Gateway:~#
root@Openvox-Wireless-Gateway:~# ssh -f -N -R 10242:localhost:12345 root@106.185.43.194 -p 22
root@106.185.43.194's password:
root@Openvox-Wireless-Gateway:~#
```

- 2) 配置公网服务器共享 SSH 隧道 (在公网服务器上进行操作)
 - 1. 编辑 /etc/ssh/sshd_conf: 设置 GatewayPorts yes
 - 2. service iptables start
 - 3. service sshd restart

```
Starting sshd:
                                                 Foreign Address
                                                                                           PID/Program name
                                                                                           2290/pptpd
                  0 0.0.0.0:10241
                                                                                           16561/sshd
```

(三)使用 SSH 隧道

2) 关闭 SSH 隧道(在 GSM 网关上进行操作) 使用 ps 命令查找ssh 相应的端口转发进程,使用 kill 命令将其杀掉

```
4107 root 420 S ssh -f -N -R 10241:localhost:80 root@106.185.43.194 - 4110 root 408 S ssh -f -N -R 10242:localhost:12345 root@106.185.43.19 4112 root 500 S dropbear -p 12345 4113 root 464 S -ash 4124 root 368 R ps -ef root@Openvox-Wireless-Gateway:~# kill 4107 4110 root@Openvox-Wireless-Gateway:~#
```

3) 关闭监听的端口(在公网服务器上进行操作) 使用 1sof 命令查找监听端口的进程,使用 kill 命令将其杀掉

```
[root@li754-194 ~]# lsof -i :10241

COMMAND PID USER FD TYPE DEVICE SIZE/OFF NODE NAME

sshd 973 root 7u IPv4 4394862 0t0 TCP *:10241 (LISTEN)

sshd 973 root 8u IPv6 4394863 0t0 TCP *:10241 (LISTEN)

[root@li754-194 ~]# kill 973

[root@li754-194 ~]# netstat -ntpl

Active Internet connections (only servers)

Proto Recv-Q Send-Q Local Address Foreign Address State PID/Program name

tcp 0 0 0.0.0.0:22 0.0.0.0:* LISTEN 16790/sshd

tcp 0 0 0.0.0.0:1723 0.0.0.0:* LISTEN 2290/pptpd

tcp 0 0 :::22 :::* LISTEN 16790/sshd

[root@li754-194 ~]#
```

(四) SSH 无密码登陆

- 1. 使用 ssh-keygen 生成公钥和私钥(一路回车,可以不输入任何信息)
- 2. 使用 ssh-copy-id 将公钥拷贝到公网服务器,需输入一次公网服务器密码
- 3. 以后便可无需密码连接公网服务器

```
[-]# xm -rf /root/.ssh/*
[-]# ssh-keygen]
Generating public/private rsa key pair.
Enter file in which to save the key (/root/.ssh/id_rsa):
Enter passphrase egain:
Your public file in which to save the key (/root/.ssh/id_rsa):
Enter passphrase again:
Your jedrification has been saved in /root/.ssh/id_rsa.
Your public key has been saved in /root/.ssh/id_rsa.
Your public hex has been saved in /root/.ssh/id_rsa.
Your public has been saved in /root/.ssh/id_
```

(五) SSH 反向连接自动重连

```
1. 使用 autossh autossh -M 20241 -f -N -R 10241:localhost:80 root@106.185.43.194 -p 22
-M port[:echo_port], port 为监听端口,默认的 echo_port=port+1 autossh 通过 port 和 echo_port 监听 ssh 状态,从 port 发送数据,echo_port 接收数据
注:在 CentOS 上测试,无数据流经过时,5-6 分钟连接失效,但进程仍在
```