

AccessMatrix.AI Deployment Guide - 6.0.1-GA (AI)

Table of Contents

1. Preface - AccessMatrix.AI Deployment Guide.....	3
2. System Requirements.....	4
3. Installation and Deployment.....	5
4. Deployment Configurations.....	7

1. Preface - AccessMatrix.AI Deployment Guide

This guide contains instructions on the deployment and configuration of the AccessMatrix.AI system.

Intended Reader

It is intended for the system administrators to set up and deploy the AccessMatrix.AI system.

Document Scope

This document provides instructions on the installation and deployment of a locally hosted Large Language Model (LLM) and AccessMatrix.AI. For in-depth details and instructions on deploying the AccessMatrix system, refer to the [AccessMatrix Common Deployment Guide](#).

For feedback or questions regarding this document, contact doc@i-sprint.com.

Related Documents

For more information, see the following documents in the AccessMatrix Product Suite:

- [AccessMatrix Release Notes](#)
- [AccessMatrix Common Deployment Guide](#)

2. System Requirements

There are certain system requirements in order to be able to utilize AccessMatrix.AI. The following section describes those.

Pre-Installation Preparation and Prerequisites

- **AccessMatrix Server**
 - The AccessMatrix Server must be running to generate the necessary data for various audit reports. For more details on how it can be deployed, refer to [AccessMatrix Common Deployment Guide](#).
- **Large Language Model (LLM) and Framework**
 - Framework: Ollama 0.3
 - LLM: Meta Llama 3.1
- **Server Environment**
 - AccessMatrix.AI must be deployed using the Node.js server environment.
 - Version: Node.js 20
- **System Requirements:**
 - AccessMatrix.AI is intended to be deployed on-premise using a local machine. It must be deployed separately from the AccessMatrix server with the following requirements:

Component	Requirement
GPU	Nvidia Geforce RTX 40 Series with minimum 8 GB VRAM
RAM	Minimum 16 GB
OS	Windows or Linux

3. Installation and Deployment

The following instructions provide detail on how to deploy and run AccessMatrix.AI.

Download and Install Large Language Model (LLM)

AccessMatrix.AI requires the use of the Ollama platform and the Meta Llama LLM. Ollama is an open-source platform that allows for small, lightweight LLMs (such as Meta Llama) to be hosted on a local machine.

To install, perform the following steps:

i Note: Before deploying AccessMatrix.AI, ensure that you have a dedicated GPU with at least 8GB of VRAM. For more details, refer to System Requirements .	
Windows	1. Click this link to download. 2. Open the downloaded OllamaSetup.exe file. 3. Follow the prompts provided by the installation wizard. Once the installation is complete, the installation wizard will be closed and Ollama will run automatically. 4. Execute the following command to verify that it has been installed correctly: <code>ollama -v</code> i Note: It should return the ollama version number.
Linux	1. Execute the following command to download Ollama: <code>curl -fsSL https://ollama.com/install.sh sh</code> 2. Execute the following command to install Ollama: <code>ollama pull llama3.1</code> 3. Execute the following command to verify that it has been installed correctly: <code>ollama -v</code> i Note: It should return the ollama version number.

Deploy AccessMatrix.AI

To access the AccessMatrix.AI portal, perform the following steps:

i Note: Ensure that the Ollama service is currently running. For more details on how to start the Ollama service, refer to Helpful Commands .	
Windows	1. Extract the AccessMatrixAI.zip file into a folder. i Note: This folder will be referred as the installation root or base directory, i.e. <code><ACMATRIX_AI_ROOT></code>. 2. Execute the following command to navigate to the directory: <code>cd /ACMATRIX_AI_ROOT</code> 3. Execute the following command to start up AccessMatrix.AI: <code>npm start</code> 4. Access your localhost using a web browser. For example: <code>http://localhost:5000</code>

Linux	1. Extract the AccessMatrixAI.zip file into a folder. <i>i</i> Note: This folder will be referred as the installation root or base directory, i.e. <ACMATRIX_AI_ROOT> 2. Execute the following command to navigate to the directory: <code>cd /ACMATRIX_AI_ROOT</code> 3. Execute the following command to start up AccessMatrix.AI: <code>npm start</code> 4. Access your localhost using a web browser. For example: <code>http://localhost:5000</code>
-------	--

Helpful Commands

The following table provides some commands that may be useful for using Ollama.

i **Note:** These commands are only applicable to Linux environments.

Function	Command
Remove Ollama model	<code>ollama rm llama3.1</code>
Display Ollama model list	<code>ollama list</code>
Start Ollama service	<code>ollama serve</code>

4. Deployment Configurations

This sections details the various configurations that can be made to AccessMatrix.AI.

Configure AccessMatrix.AI

AccessMatrix.AI allows for several optional configurations. For example, this can include changing the URL for the AccessMatrix server that AccessMatrix.AI will connect to, or the plugins that will be loaded into AccessMatrix.AI. For a list of configurations available, refer to [Optional Configurations](#).

To configure AccessMatrix.AI, perform the following:

1. Navigate to `<ACMATRIX_AI_ROOT>\config` and open the **config.json** file.
2. Edit the values as required. For example:

```
JSON

{
  "OLLAMA_HOST": "http://localhost:11434",
  "AM5_URL": "https://localhost:8443",
  "CONNECTOR" : "amaudit-general,amaudit",
  "ENABLE_LOG" : true,
  "ALLOW_SELF_SIGNED_CERTIFICATE" : true,
  "PORT" : 5000,
  "PORT_HTTPS" : 5443,
  "INTERVAL": 60
}
```

3. Save the changes.
4. Restart AccessMatrix.AI for the changes to take effect.

Optional Configurations

The optional configurations available for AccessMatrix.AI are described in the following table:

Configuration	Description
OLLAMA_HOST	Specifies the URL and port where the Ollama LLM is hosted.
AM5_URL	Specifies the URL for the AM5 audit API.
CONNECTOR	Specifies the plugin that will be loaded into the audit assistant. Multiple plugins can be included by using a comma.

Configuration	Description
	Values: "amaudit-general" Provides a summary of audit events based on historical data. "amaudit" Provides audit event details in tables and charts based on real-time data.
ENABLE_LOG	Specifies if logging will be enabled. The log includes details such as the plugin that was initialized, the prompts that were queried, and the functions called to generate the response. Values: "true" "false"
ALLOW_SELF_SIGNED_CERTIFICATE	Specifies if SSL certificates are allowed. This configuration is used when the AM server and AccessMatrix.AI have an encrypted connection between them. Values: "true" "false"
PORT	Specifies the port for which AccessMatrix.AI will be running on.
PORT HTTPS	Specifies the secure port for which AccessMatrix.AI will be running on.
INTERVAL	Specifies how often the backend is updated, in minutes.
