Informatica® Intelligent Data Management Cloud

October 2026

User Administration

Informatica Intelligent Data Management Cloud User Administration
October 2026

© Copyright Informatica LLC 2021, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices and AI assistant acknowledgements are included with the product.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-10-16

Table of Contents

Preface 6

Informatica Resources 6

- Informatica Documentation 6
- IDMC web site 6
- IDMC Communities 6
- IDMC Marketplace 6
- Data Integration connector documentation 7
- Informatica Knowledge Base 7
- IDMC Trust Center 7
- IDMC Pulse Dashboard 7
- Informatica Global Customer Support 7

Chapter 1: User administration 8

Chapter 2: User authentication 9

Multi-factor authentication 9

- Setting up multi-factor authentication 10

Ecosystem single sign-on 10

Authentication properties 12

Fingerprint authentication 13

Chapter 3: SAML single sign-on 15

SAML single sign-on requirements 16

Single sign-on restrictions 16

User management with SAML authentication 17

- Switching from SAML authentication and authorization 18

User management with SAML authentication and authorization 18

- Switching from SAML authentication only 20
- Pushing user and group information using SCIM 2.0 20

Configuring SAML single sign-on for IDMC 22

SAML configuration 25

- SSO configuration properties 25
- Identity provider configuration properties 26
- Service provider settings 27
- SAML attribute mapping properties 28
- SAML role and group mapping properties 30

OAuth using JSON web tokens 30

Chapter 4: Users 32

Application Integration anonymous user 33

User statistics. . . . 33
User details. . . . 34
Creating a user. . . . 37
Assigning and unassigning services 38
Disabling a user. . . . 39
Resetting a user. . . . 39
Reassigning a user's scheduled jobs. . . . 40
Deleting a user. . . . 40

Chapter 5: User groups. . . . 42

User group details. . . . 43
Creating a user group. . . . 44
Renaming a user group. . . . 45
Deleting a user group. . . . 45

Chapter 6: User roles. . . . 46

Role details. . . . 47
System-defined roles. . . . 48
- Cross-service roles. . . . 49
- Administrator roles. . . . 51
- AI Agent Engineering roles. . . . 51
- API Center roles. . . . 52
- Application Integration and Application Integration Console roles. . . . 53
- B2B Gateway roles. . . . 54
- B2B Partners Portal roles. . . . 54
- Business 360 Console roles. . . . 55
- CLAIRE GPT roles. . . . 55
- Cloud Data Integration for PowerCenter (CDI-PC) roles. . . . 56
- Customer 360 SaaS roles. . . . 56
- Data Governance and Catalog roles. . . . 57
- Data Ingestion and Replication roles. . . . 57
- Data Integration roles. . . . 58
- Data Marketplace roles. . . . 59
- Data Profiling roles. . . . 61
- Data Quality roles. . . . 62
- Integration Hub roles. . . . 62
- Metadata Command Center roles. . . . 63
- Monitor roles. . . . 63
- Operational Insights roles. . . . 64
- Product 360 SaaS roles. . . . 64
- Reference 360 roles. . . . 64
- Supplier 360 SaaS roles. . . . 65

Custom roles. . . . 66

Creating a custom role. . . . 66
Renaming a role. . . . 67
Deleting a role. . . . 67
Role asset and feature privileges. . . . 68
Administrator asset and feature privileges. . . . 69
AI Agent Engineering asset and feature privileges. . . . 72
Application Integration feature privileges. . . . 72
Data Governance and Catalog feature privileges. . . . 74
Data Ingestion and Replication minimum asset and feature privileges. . . . 75
Data Integration asset and feature privileges. . . . 76
Data Marketplace feature privileges. . . . 78
Data Profiling feature privileges 78
Data Quality feature privileges. . . . 79
Domain Management Service asset and feature privileges. . . . 80
Human Task asset and feature privileges. . . . 81
Metadata Command Center feature privileges. . . . 82
Monitor feature privileges. . . . 83
Operational Insights feature privilges. . . . 83
Workbench Service asset and feature privileges. . . . 84

Chapter 7: Notifications. . . . 86
Configuring email notifications for your organization. . . . 86
Configuring email notifications for yourself. . . . 87
Notification categories and subcategories. . . . 88

Chapter 8: User configuration examples. . . . 91

Chapter 9: Editing your user profile. . . . 93

Chapter 10: Editing your user settings. . . . 94

Chapter 11: Inviting users to join your organization. . . . 95

Index. . . . 96

Preface

Use *User Administration* to learn how to configure IDMC℠ user accounts manually or using SAML single-sign on. Learn how to create user groups, assign roles to users, and edit your user profile.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security, compliance, and privacy practices.

You can access the trust center at https://trust.informatica.com/.

IDMC Pulse Dashboard

The IDMC Pulse Dashboard provides system status and upgrade information for all PODs and services across IDMC.

Follow the services you use and subscribe to alerts to receive notifications about upgrades, maintenance, production incidents, and upcoming releases. The IDMC Pulse Dashboard displays the production status of all the IDMC products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single service or all IDMC services. Subscribing to all services is the best way to be certain you never miss an update.

For more information, see the Service Status and Communications guide.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

User administration

Configure users and user groups to allow access to your organization and assets. A user is an individual account in Intelligent Data Management Cloud (IDMC) that allows secure access to an organization.

To configure users, you can set up single sign-on through Microsoft Azure or through a SAML third party identity provider. You can also create users directly in Administrator. For more information about SAML configuration with Microsoft Azure, see "Ecosystem single sign-on" on page 10. For more information about SAML configuration with a third-party identity provider, see Chapter 3, "SAML single sign-on" on page 15. For more information about configuring user accounts directly, see Chapter 4, "Users" on page 32.

A user group is a group of user accounts in which all members of the group can perform the same tasks and have the same access rights for different types of assets. For more information about user groups, see Chapter 5, "User groups" on page 42.

Users and groups can perform tasks and access assets based on the roles that you assign to them. For more information about user roles, see Chapter 6, "User roles" on page 46.

Each user can configure personal information, including their email, password, and time zone, in their user profile. Users can configure notification preferences and source control credentials in their user settings. For more information, see Chapter 9, "Editing your user profile" on page 93 and Chapter 10, "Editing your user settings" on page 94 .

CHAPTER 2

User authentication

IDMC uses different types of user authentication. Native users are authenticated through IDMC. Salesforce, Microsoft Azure, and SAML users are authenticated through their identity providers.

IDMC can use the following types of user authentication:

Native

Native users are authenticated through IDMC and log in using a user name and password that's unique to their organization. Native human users can log in to the user interface while non-human users are restricted to using APIs.

Native human users must provide an access code to log in to the user interface unless the organization administrator disables multi-factor authentication.

Salesforce

Salesforce users sign in to IDMC through Salesforce or a Salesforce app. They are authenticated through Salesforce.

For more information about Salesforce authentication, see the help for the Salesforce connector in the Data Integration help.

Microsoft Azure

Microsoft Azure users sign in to IDMC through Microsoft Azure. They are authenticated through Microsoft Azure.

For more information about Microsoft Azure authentication, see "Ecosystem single sign-on" on page 10.

SAML

SAML users sign in to IDMC through their identity provider. They are authenticated through their identity provider.

For more information about configuring SAML single sign-on, see Chapter 3, "SAML single sign-on" on page 15.

Multi-factor authentication

Native human users can use multi-factor authentication to receive a verification code through email each time they log in to the user interface. By default, multi-factor authentication is enabled for organizations when they're provisioned.

To set up multi-factor authentication, categorize users into the following identity types:

Human user

A real person who logs in to the user interface to interact with services. When multi-factor authentication is enabled, human users receive a verification code through email. You need to verify that the email address for each human user is valid.

Non-human user


A user account for software, integrations, automated processes, and APIs that access services without human interaction.

You can categorize users who don't use the user interface as non-human users. Non-human users can't log in to the user interface, and they don't need to enter a verification code to run APIs.

Setting up multi-factor authentication

Set up multi-factor authentication so that native human users receive a verification code each time they log in to IDMC.

1. On the **Organization** page, enable multi-factor authentication.
2. On the **Users** page, categorize users as human or non-human users.
   - To categorize an individual user, drill down on a user and set the **Identity Category** to human or non-human.
   - To categorize multiple users at the same time, select each user. Then, select **<number> Selected** > **Update Identity Category** > **Human** or **Non-Human**.
     The following image shows the menu options to categorize multiple users:



On the **Logs** page, review the security logs to verify that a user is using multi-factor authentication to log in to their account.


Ecosystem single sign-on

IDMC enables single sign-on capability for Microsoft Azure users. This allows Microsoft Azure users to sign in to IDMC without having to enter their login information again.

When you create your organization through Microsoft Azure, you can configure some single sign-on properties for Microsoft Azure users on the **Ecosystem SSO** page.

Note: The ecosystem single sign-on properties that you configure for Microsoft Azure are different than the SAML single sign-on properties that you configure to enable single-sign on from a third-party identity provider. To configure SAML single sign-on for your organization, see Chapter 3, "SAML single sign-on" on page 15.

The following image shows the **Ecosystem SSO** page:



You can configure the following properties for Microsoft Azure users:

Assign users default role

When a Microsoft Azure user signs in to your organization for the first time, IDMC adds the user to your organization and assigns the user a default role. By default, IDMC assigns the user the Admin role.

You can change the default role to a different role such as the Designer role. To change the default user role, select a different role in the **Assign users default role** list.

Note: If you want Microsoft Azure users to be able to download, install, and register a Secure Agent, assign them the Admin or Designer role. You can also assign users a custom role that has privileges to create, read, and update Secure Agents.

Disable auto-provisioning of users

By default, the first time a Microsoft Azure user signs in to your organization, IDMC adds the user to your organization. This process is called auto-provisioning.

You can enable or disable the auto-provisioning of Microsoft Azure users. To do this, enable or disable the **Disable auto provisioning of users** option.

Note: If you disable auto-provisioning, you must create each user on the **Users** page. If you want the user to be able to use single sign-on from Microsoft Azure, you must also set the **Authentication** field on the user details page to **Azure SSO**.

Authentication properties

You can configure authentication properties for your organization and sub-organizations. Authentication properties control password restrictions and IP address filtering.

Password restrictions are enforced when users create or change their passwords. If you change the password expiration date from "never" to a number of days, then users with passwords that are older than the number of days will be required to change their passwords the next time that they log in to IDMC.

The following table describes the authentication properties:

Property	Description
Minimum Password Length	Minimum password length required for a valid password. Must be a number between 8 and 25 characters. If the organization uses multi-factor authentication, the minimum password length is 8 characters. Otherwise, the minimum password length is 15 characters.
Minimum Character Mix	Minimum number of character types required for a valid password. Passwords can contain a mix of the following character sets: - Lowercase alphabetic characters - Uppercase alphabetic characters - Numeric characters - Special characters For example, if you set **Minimum Character Mix** to 1, then passwords must contain at least one of the character sets. If you set **Minimum Character Mix** to 2, then passwords must contain at least two of the character sets.
Password Reuse	Controls whether users can reuse passwords.
Password Expires	Determines how often users must reset their passwords.
Enable Multi-Factor Authentication	Enables multi-factor authentication for native human users. By default, multi-factor authentication is enabled when organizations are provisioned. With multi-factor authentication, native human users receive a verification code through email when they log in to the user interface. The email address for each human user must be valid. Categorize users as human or non-human users on the **Users** page. For more information, see *User Administration*.
Session Idle Timeout	Amount of time before a user's session times out due to inactivity. IDMC displays a warning message to the user 60 seconds before the user is logged out. Default is 30 minutes, which is the recommended value.
Authentication Type	Authentication type used after a user logs in. Default is **Session ID**. For JWT authentication, select a duration for tokens to expire. Default is 30 minutes. When you change the authentication type, the new type takes effect at the next login. The change doesn't affect sessions that are in progress. Before you use the JWT authentication type, modify custom scripts to refresh the tokens before they expire. For more information, see the JWT Support Knowledge article. **Note:** Don't use the JWT authentication type if your organization uses REST V2 Connector to call IDMC APIs.

Property	Description
Use Trusted IP Ranges	Enables IP address filtering. IP address filtering uses trusted IP address ranges in addition to account passwords to prevent unauthorized users from accessing your organization. When you enable IP address filtering, a user with a valid login must also have an IP address within the range of trusted IP addresses, or the user can't log in to your organization. This option applies to all Informatica clients that connect to IDMC, including human and non-human users, REST API users, Secure Agents, and Secure Agent services. When you enable this option, you must also enter one or more trusted IP address ranges. Use the following guidelines: - If you create a serverless runtime environment when trusted IP ranges are enabled, you must add the IP addresses of the DMZ NAT gateway to the list of trusted IP addresses. For a list of the DMZ NAT gateway addresses, see *Runtime Environments*. - If you enable trusted IPs and use Cloud Integration Hub, ensure that you've also allowed the outbound IP addresses under Core Services for your POD. For more information, see POD Availability and Networking.
Allowed Trusted IP Ranges	The trusted ranges of IP addresses from which users can log in to access the organization. IDMC supports IP address formats in IP version 4 (IPv4) and version 6 (IPv6). Fields for the trusted IP address range appear when you enable IP address filtering. To enter additional address ranges, click **+**. To ensure seamless communication between resources across both IPv4 and IPv6 networks, enable a dual stack configuration. For example, if your virtual machine uses one network type, IPv4 or IPv6, and the servers that host the connectors use another network type, enable dual stack on your virtual machine to ensure seamless communication regardless of their network type. **Note:** If you enter an invalid IP address range, users cannot access your organization. Contact your network administrator for valid IP address ranges.

Fingerprint authentication

Fingerprint authentication verifies that a Secure Agent starts up on the same machine it was set up on. You can configure settings to customize how your organization handles fingerprint mismatches.

The first time an agent starts up, IDMC uses anonymized device attributes to create a unqiue fingerprint of the Secure Agent machine. Every subsequent time that the agent starts up, IDMC checks the fingerprint and, if there's a mismatch, sends an alert to the notifications tray for administrators.

Note: If you uninstall and reinstall the Secure Agent on the same machine, the fingerprint remains the same.

Configure settings for fingerprint authentication in the Authentication section of the **Settings** page. The following table describes the fingerprint authentication properties:

Property	Description
Fingerprint Enforcement	Prevents the Secure Agent from starting up and logs an error when there's a fingerprint mismatch. IDMC logs the following error in the agentcore.log file: Internal error. Agent <Secure Agent ID> fingerprint is not matching with the previous stored value for request <request ID>. When you disable this property and there's a fingerprint mismatch, the Secure Agent starts up normally. Default is off.
Fingerprint Mismatch Email Notifications	To receive mismatch alerts by email, enter an email address. IDMC checks the email format, but doesn't verify the email address. Be sure to allow emails from the address "admin@informaticacloud.com". IDMC sends an email with the following message: There was a fingerprint mismatch while logging in agent with name <Secure Agent name> for Organization <organization ID>. The agent was last active on <date in UTC>.

CHAPTER 3

SAML single sign-on

You can enable single sign-on (SSO) capability so that users can access their organization without the need to enter login information. You can use SSO for user authentication or for both authentication and authorization in an organization. You configure SSO capability for an organization on the **SAML Setup** page.

Single sign-on to IDMC is based on the Security Assertion Markup Language (SAML) 2.0 web browser single sign-on profile. The SAML web browser single sign-on profile consists of the following entities:

Identity provider

An entity that manages authentication information and provides authentication services by using security tokens.

Service provider

An entity that provides web services to principals, for example, an entity that hosts web applications. IDMC is a service provider.

Principal

An end user who interacts through an HTTP user agent.

SAML 2.0 is an XML-based protocol that uses security tokens that contain assertions to pass information about a principal between an identity provider and a service provider. An assertion is a package of information that supplies statements made by a SAML authority. You can find more information about SAML on the Oasis web site: https://www.oasis-open.org

The process that occurs when a user enters the IDMC URL in a browser or launches IDMC through a chiclet differs based on whether the organization uses SAML SSO for authentication only or for both authentication and authorization.

SAML single sign-on for authentication only

When a user signs on to IDMC and the organization uses SAML SSO for user authentication only, the following process occurs:

1. IDMC sends a SAML authentication request to the organization's identity provider.
2. The identity provider confirms the user's identity and sends a SAML authentication response to IDMC. The authentication response includes a SAML token.
3. When IDMC receives the SAML authentication response from the identity provider, it completes the following tasks:
   - If the user exists, IDMC establishes the user session and logs the user in.
   - If the user does not exist and auto-provisioning of users is enabled, IDMC gets the user attributes from the SAML token, creates the user, and assigns the user the default role and the default group, if it is configured. IDMC establishes the user session and logs the user in.

- If the user does not exist and auto-provisioning of users is disabled, IDMC fails the login.

4. When a user logs out of IDMC or the session times out, IDMC sends a SAML logout request to the identity provider.
5. The identity provider terminates the user session on the identity provider side.

SAML single sign-on for authentication and authorization

When a user signs on to IDMC and the organization uses SAML SSO for authentication and authorization, the following process occurs:

1. IDMC sends a SAML authentication request to the organization's identity provider.
2. The identity provider confirms the user's identity and sends a SAML authentication response to IDMC. The authentication response includes a SAML token.
3. When IDMC receives the SAML authentication response from the identity provider, it completes the following tasks:
   - If the user exists, IDMC gets the user roles, groups, and attributes from the SAML token. It finds the corresponding IDMC user roles and groups, and updates the user roles, if necessary. IDMC establishes the user session and logs the user in.
   - If the user does not exist and auto-provisioning of users is enabled, IDMC gets the user roles, groups, and attributes from the SAML token and creates the user. IDMC establishes the user session and logs the user in. If the token contains no SAML role or group information, IDMC fails the login.
   - If the user does not exist and auto-provisioning of users is disabled, IDMC fails the login.
4. When a user logs out of IDMC or the session times out, IDMC sends a SAML logout request to the identity provider.
5. The identity provider terminates the user session on the identity provider side.

SAML single sign-on requirements

SAML single sign-on for an IDMC organization requires an appropriate identity provider.

To set up SAML single sign-on for an organization, ensure that the following requirements are met:

- The system uses a SAML 2.0-based identity provider.

  Common identity providers include Microsoft Active Directory Federation Services (AD FS), Okta, SSOCircle, OpenLDAP, and Shibboleth. The identity provider should be configured to use either the DSA-SHA256 or RSA-SHA256 algorithm to generate the signature.
- The IDMC organization has the SAML based Single Sign-On license.
- You have access to the organization as an organization administrator to set up single sign-on.

Single sign-on restrictions

There are some restrictions for SAML single sign-on access to IDMC.

The following restrictions apply to SAML single sign-on access:


- Your license with the identity provider must remain valid to access IDMC through single sign-on.

- If the identity provider is down or IDMC servers can't reach it, users can't log in to IDMC through single sign-on.
- If the identity provider certificate used for SAML single sign-on to IDMC expires, users can't access IDMC through single sign-on.
- If your organization uses trusted IP address ranges, users can't log in to IDMC from an IP address that is not within the trusted IP address ranges.

User management with SAML authentication

When you use SAML SSO to authenticate users only, IDMC verifies the user credentials each time a user signs in to IDMC. In this scenario, you manage a user's authorization using the group and role assignments within IDMC.

To use SAML SSO for authentication only, disable the **Map SAML Groups and Roles** option on the **SAML Setup** page. The following image shows the **SAML Setup** page with this option disabled:



The **Map SAML Groups and Roles** option is disabled by default and you'll need to configure a default user role and optionally a default user group. For more information, see "SAML role and group mapping properties" on page 30.

When you use SAML for authentication only, you manage users in the following ways:

New users with auto-provisioning

When a new user signs on to IDMC for the first time and auto-provisioning is enabled, IDMC gets the user attributes such as first name, last name, and email address from the SAML token and stores them in the repository. It creates the user and assigns the user the default role and the default group, if one has been configured.

If you want to refine the user's level of access to assets, update the user's group and role assignments on the user details page. For more information, see"User details" on page 34.

New users without auto-provisioning

If auto-provisioning is disabled, users are not automatically added to the organization when they attempt to sign on to IDMC for the first time. You need to create the user in Administrator.

Existing users

When an existing user signs on, IDMC authenticates the user but does not get the SAML roles, groups, or user attributes from the SAML token. If this information changes, you can update the user's groups and roles on the user details page.

You can also create a native user account with credentials in Administrator, and the user credentials are saved in the IDMC repository. If you do this, the user logs in to IDMC directly instead of using SAML single sign-on.


If you delete a user from IDMC, the user is deleted from the IDMC repository but not from the identity provider.

For all SAML users, the information in the user profile is read-only except for the time zone. The password and security question do not appear in the user profile.

Switching from SAML authentication and authorization

If your organization uses SAML for both authentication and authorization, you can change it to use SAML for authentication only.

To use SAML for authentication only, disable the **Map SAML Groups and Roles** option on the **SAML Setup** page. The following image shows the **SAML Setup** page with this option disabled:




If you disable this option after it was previously enabled, the group and role mapping information on the **SAML Setup** page becomes read-only but is not deleted. All SAML groups become regular IDMC groups. You can edit the groups, delete them, and add and remove group members.

When you disable this option, users' IDMC roles do not change, so scheduled jobs are unaffected.

User management with SAML authentication and authorization


When you use SAML SSO for user authentication and authorization, IDMC verifies the user credentials each time a user attempts to sign on. It also gets the user's SAML groups and roles and assigns the user the corresponding IDMC roles.

To use SAML SSO for authentication and authorization, enable the **Map SAML Groups and Roles** option on the **SAML Setup** page. The following image shows the **SAML Setup** page with this option enabled:



For some identity providers, you can also choose to push user and group information to IDMC using SCIM 2.0.

When you enable the **Map SAML Groups and Roles** option, map IDMC roles to SAML roles and groups on the **SAML Role Mapping** and **SAML Group Mapping** tabs. The following image shows the **SAML Role Mapping** and **SAML Group Mapping** tabs:



Mapping roles and groups ensures that users have the appropriate levels of access to IDMC assets. You can't configure user roles or groups for these users individually in Administrator.

If the SAML groups that you map on the **SAML Setup** page don't exist yet, IDMC creates these groups for you.

Note: You can view these groups on the **User Groups** page, but you can't edit the group information or change the group members.

IDMC ignores any SAML groups and roles that are returned in the SAML token but are not mapped on the **SAML Setup** page.

When you use SAML for authentication and authorization, you manage users in the following ways:

New users with auto-provisioning

When a new user signs on to IDMC for the first time and auto-provisioning is enabled, IDMC gets the SAML roles, groups, and user attributes from the SAML token and stores them in the repository. It creates and authenticates the user and assigns the user the IDMC roles that are mapped on the **SAML Setup** page.

If there are no roles or groups in the SAML token, IDMC fails the login.

New users without auto-provisioning

If auto-provisioning is disabled, users are not automatically added to the organization when they attempt to sign on to IDMC for the first time. You need to create the user in Administrator.

Existing users

When an existing user signs on, IDMC authenticates the user and gets the SAML roles, groups, and user attributes from the SAML token. If this information has changed since the last login, IDMC updates the user attributes and roles.


You can also create a native user account with credentials in Administrator, and the user credentials are saved in the IDMC repository. If you do this, the user logs in to IDMC directly instead of using single sign-on. You can delete these user accounts in Administrator.

For all SAML users, the information in the user profile is read-only except for the time zone. The password and security question do not appear in the user profile.

Switching from SAML authentication only

If your organization currently uses SAML for authentication only, you can change it to using SAML for both authentication and authorization.

To switch from SAML authentication to SAML authentication and authorization, enable the **Map SAML Groups and Roles** option on the **SAML Setup** page. The following image shows the **SAML Setup** page with this option enabled:




If you enable this option after it was previously disabled, the role and group mapping tabs on the **SAML Setup** page becomes editable. If any group or role mapping was configured previously, it is retained.

When you enable this option, users' authorization information is updated when they are authenticated in IDMC with a new SAML token. Updating authorization information can affect a user's scheduled jobs if the user's privileges change.

Pushing user and group information using SCIM 2.0

When you use SAML SSO for authentication and authorization and the identity provider is Okta or Azure Active Directory, you can choose to push user and group information to IDMC using SCIM 2.0.

To push information using SCIM 2.0, enable the **Enable IdP to push users/groups using SCIM 2.0** option on the **SAML Setup** page. The following image shows the **SAML Setup** page with this option enabled:



Enabling this option allows the identity provider to push user and group information at regular intervals to provision new users, delete users, and keep each user's SAML groups and roles in sync with their IDMC user roles. In this case, auto-provisioning of users is disabled because users are provisioned through SCIM. You can also create users manually in Administrator.

IDMC hosts SCIM endpoints that the identity provider can use to perform certain operations in IDMC. These operations include creating and deactivating users, creating and deleting user groups, adding and removing users from groups, and updating user attributes.

To access the SCIM endpoints, you must create a provisioning app as a SCIM client on Azure Active Directory or Okta. No special privileges are needed to access the SCIM endpoints. When you create the app, you must provide a SCIM token which you generate on the **SAML Setup** page using the **Manage Token** button.

For information about setting up SCIM 2.0 and creating the provisioning app, see the following articles on Informatica Network:

- Setting up SCIM with Azure Active Directory
- Setting up SCIM with Okta

When you enable SCIM provisioning, additional user attributes such as Display Name, Employee Number, Organization, Division, and Department are also pushed to IDMC. You must map these attributes on the **SAML Setup** page. You can view these attributes for each user on the user details page.

User and group information for individual users is also passed in the SAML token during single sign-on. As a result, if a user's SAML roles, groups, or attributes change, IDMC updates the user information when the user signs on.

Note: If you change group membership through SCIM, you must also update the SAML group-mapping configuration in Administrator to match the identity provider's SAML assertion. The SAML single sign-on overrides group membership on login, removing any updates performed through SCIM.

Managing SCIM tokens


Each user can create and use up to two SCIM tokens simultaneously. Each token is valid for 180 days from the time of generation. When a token expires, you need to generate a new one, even for an existing connection.

As a best practice, create tokens on different days so that they don't expire on the same day. For example, you might want to generate a token on one day and a second token 90 days later. IDMC notifies you when a token is about to expire.

Note: You can generate up to two SCIM tokens, including expired tokens. To generate another token, first delete one of the existing tokens.


You can also manage SCIM tokens using the scimTokens REST API resource. For more information, see *REST API Reference*.

1. On the **SAML Setup** page in Administrator, click **Manage Token**. The following image shows the **Manage Token** button:



   The **SCIM Tokens** dialog box displays the SCIM tokens that you created along with the expiration date and status of each token. If two tokens are listed, delete one before generating a new token.

2. To generate a token, click **Generate Token**. The following image shows the **Generate Token** button:



   You need this token when you enable SCIM in the provisioning app.
3. Click **Copy** to copy the token to the clipboard.
4. To delete a token, click the **Delete** icon for the token you want to delete.

Configuring SAML single sign-on for IDMC

Configure SAML single sign-on (SSO) in IDMC to exchange authentication and authorization information with your identity provider.

Tip: To watch a video that describes the SAML configuration procedure, see https://youtu.be/4DewSNbvJBc?si=VAeGj5-5Oq0HbXtF.

SAML single sign-on requires an identity provider and service provider. Examples of identity providers include: Okta, Microsoft Azure AD, and PingFederate. In this scenario, the service provider is IDMC.


Before you can configure SAML SSO in IDMC, it must already be set up in your identity provider. For information about configuring two common identity providers, see the following articles on the Informatica network:

- HOW TO: Configure SAML SSO in Informatica Cloud using Microsoft Azure AD
- HOW TO: Configure SAML SSO using OKTA in IICS


To configure SAML single sign-on for IDMC:

1. Contact your identity provider team for the following information:
   - Issuer
   - Single Sign-on Service URL
   - Signing Certificate
2. Enter the information into the corresponding fields in **Identity Provider Configuration** section of the **SAML Setup** page:
   - **Issuer**
   - **Single Sign-on Service URL**
   - **Signing Certificate**

The following images shows these fields on the **SAML Setup** page:




3. Enter the **Name Identifier Format** if possible, otherwise this can be added later. The following image shows the **Name Identifier Format** field:




4. Click **Save**.
   IDMC generates the service provider metadata file and a unique token for your organization.
5. Click **Download Service Provider Metadata**. This downloads the file `iics_saml_sp_metadata.xml` to your machine. It contains information that your service provider needs to complete the configuration.
6. In the **Information** dialog box, note the URL for single sign-on access to your IDMC organization. For example:
   `https://dm-us.informaticacloud.com/ma/sso/<organization token>`

7. Send the `iics_saml_sp_metadata.xml` file to the identity provider administrator, along with the URL for single sign-on access.
8. Complete the **SAML Attribute Mapping** section. For more information, see "SAML attribute mapping properties" on page 28.
9. If you want to map SAML roles to specific roles in IDMC, perform the following steps:
   a. Enable **Map SAML Groups and Roles**. The following image shows the **SAML Setup** page with this option enabled:



   b. In the **User Roles** field, enter the SAML attribute used to pass the assigned user roles. The following image shows the **User Roles** field:




   For example, if "idp_roles" is the name of the attribute from the identity provider used to pass user role information, then enter **idp_roles**.
   c. Map the corresponding IDMC roles in the **SAML Role Mapping** tab. For more information, see "SAML role and group mapping properties" on page 30.
10. If you don't want to map specific roles and instead just use a default role, perform the following steps:
   a. Ensure that **Map SAML Groups and Roles** is not selected.
   b. In the **SAML Role Mapping** tab, scroll to the bottom of the list and select a **Default Role**. The following image shows the **Default Role** field:



   The Administrator can change the roles later.
11. If you want to map SAML groups to specific groups in IDMC, perform the following steps:
   a. Select **Map SAML Groups and Roles**.

b. In the **User Groups** field, enter the SAML attribute used to pass the assigned user groups. The following image shows the **Default Groups** field:



For example, if "idp_groups" is the name of the attribute from the identity provider used to pass user group information, then enter **idp_groups**.

c. Map the corresponding IDMC groups in the **SAML Group Mapping** tab. For more information, see "SAML role and group mapping properties" on page 30.
If there isn't a matching IDMC group, enter a new group name and IDMC will create this group and map it to the SAML group. Groups created this way are read-only in IDMC.

12. If you don't want to map specific groups and instead just use a default group, perform the following steps:
    a. Ensure that **Map SAML Groups and Roles** is not selected.
    b. In the **SAML Group Mapping** tab, scroll to the bottom of the list and select a **Default Group**.
    The Administrator can change the groups later.
13. Complete the remaining fields on the **SAML Setup** page as necessary.

SAML configuration

Configure SAML single sign-on (SSO) settings and map SAML attributes on the **SAML Setup** page.

The SAML Setup page groups the properties into the following sections:

- "SSO configuration properties" on page 25
- "Identity provider configuration properties" on page 26
- "Service provider settings" on page 27
- "SAML attribute mapping properties" on page 28
- "SAML role and group mapping properties" on page 30

For more information on how to configure SAML single sign-on for your organization, see "Configuring SAML single sign-on for IDMC" on page 22.

SSO configuration properties

Define single sign-on configuration properties on the **SAML Setup** page.

If you have an identity provider XML file, you can upload the file to populate some of the properties. IDMC can parse and extract most of the data from the XML file. However, you might need to enter certain fields manually such as the name identifier format.

The following table describes the SSO configuration properties:

Property	Description
Use Identity Provider File	The identity provider XML file that populates many of the properties on the **SAML Setup** page. To use an identity provider XML file to define identity provider properties, click **Browse**, and navigate to the identity provider XML file.
Disable auto provisioning of users	Disables auto-provisioning of SAML users. Select this option to disable auto-provisioning. When auto-provisioning is disabled, users are not automatically added to the organization when they attempt to sign on to IDMC for the first time. If you disable auto-provisioning and you don't use SCIM 2.0 to push user and group information from the identity provider, you need to create the users manually in Administrator. If you use SCIM 2.0, this option is disabled because users are provisioned by the SCIM client. Default is disabled.
Map SAML Groups and Roles	Maps groups and roles from the SAML token each time a user signs on to IDMC. Enable this option to use SAML SSO for both authentication and authorization. Disable this option to use SAML SSO for authentication only. Default is disabled.
Enable IdP to push users/groups using SCIM 2.0	This option is available when you enable **Map SAML Groups and Roles**. Allows your identity provider to push user and group information to IDMC using SCIM 2.0 in addition to passing these attributes in the SAML token. When you enable this option, you generate a bearer token for the identity provider (SCIM client). To generate a token, click **Manage Token**. For more information about generating and managing bearer tokens, see "Managing SCIM tokens" on page 21. **Warning:** If you provide the identity provider with a token and then generate a new token, the previous token is overwritten, and you must provide the identity provider with the new token. When you enable this option, auto-provisioning of users is disabled because users are provisioned through the SCIM client. Default is disabled.

Identity provider configuration properties

Define identity provider configuration properties on the **SAML Setup** page.

The following table describes the identity provider configuration properties:

Property	Description
Issuer	The entity ID of the identity provider, which is the unique identifier of the identity provider. The Issuer value in all messages from the identity provider to IDMC must match this value. For example: `<saml:Issuer>http://idp.example.com</saml:Issuer>`
Single Sign-On Service URL	The identity provider's HTTP-POST SAML binding URL for the SingleSignOnService, which is the SingleSignOnService element's location attribute. IDMC sends login requests to this URL.
Single Logout Service URL	The identity provider's HTTP-POST SAML binding URL for the SingleLogoutService, which is the SingleLogoutService element's location attribute. IDMC sends logout requests to this URL.

Property	Description
Signing Certificate	Base64-encoded PEM format identity provider certificate that IDMC uses to validate signed SAML messages from the identity provider. **Note:** The identity provider signing algorithm must be either DSA-SHA256 or RSA-SHA256.
Use signing certificate for encryption	Uses the public key in your signing certificate to encrypt logout requests sent to your identity provider when a user logs out from IDMC.
Encryption Certificate	Base64-encoded PEM format identity provider certificate that IDMC uses to encrypt SAML messages sent to the identity provider. Applicable if you do not enable use of the signing certificate for encryption.
Name Identifier Format	The format of the name identifier in the authentication request that the identity provider returns to IDMC. IDMC uses the name identifier value as the IDMC user name. The name identifier cannot be a transient value that can be different for each login. For a particular user, each single sign-on login to IDMC must contain the same name identifier value. To specify that the name identifier is an email address, the Name Identifier Format is as follows: `urn:oasis:names:tc:SAML:1.1:nameidformat:emailAddress`
Logout Service URL (SOAP Binding)	The identity provider's SAML SOAP binding URL for the single logout service. IDMC sends logout requests to this URL.
Logout Page URL	The landing page to which a user is redirected after the user logs out of IDMC. IDMC redirects the logged out user to the landing page in the following ways: - If you specify a logout page URL, IDMC redirects the user to this URL after logout. - If you do not specify a logout page URL, IDMC redirects the user to a default logout page.

Service provider settings

Define the IDMC service provider settings on the **SAML Setup** page.

The following table describes service provider settings:

Property	Description
Informatica Cloud Platform SSO	Displays the single sign-on URL for your organization. IDMC generates this URL.
Clock Skew	Specifies the maximum permitted time, in seconds, between the time stamps in the SAML response from the identity provider and the IDMC clock. Default is 180 seconds (3 minutes).
Name Identifier value represents user's email address	If enabled, IDMC uses the name identifier as the email address. Default is enabled.
Sign authentication requests	If enabled, IDMC signs authentication requests to the identity provider. Default is enabled.

Property	Description
Sign logout requests sent using SOAP binding	If enabled, IDMC signs logout requests sent to the identity provider. Default is enabled.
Encrypt name identifier in logout requests	If enabled, IDMC encrypts the name identifier in logout requests. **Note:** Verify that the identity provider supports decryption of name identifiers before you enable this option. Default is disabled.

SAML attribute mapping properties

The authentication response from the identity provider to IDMC includes user login attributes such as name, email address, and user role. If the identity provider passes user and group information using SCIM 2.0, the authentication response includes additional SCIM attributes such as Display Name, Employee Number, and Organization.

Map the IDMC user fields to corresponding SAML attributes on the **SAML Setup** page.

Note: The attribute format differs based on your identity provider. Refer to the provider documentation for more information.

The following table describes the SAML attribute mapping properties:

includes user login attributes such as name, email address, and user role **includes user login attributes such as name, email address, and user role** **The authentication response from the identity provider to** **Property**	**Description**
Use friendly SAML attribute names	If selected, uses the human-readable form of the SAML attribute name which might be useful in cases in which the attribute name is complex or opaque, such as an OID or a UUID.
First Name	SAML attribute used to pass the user first name.
Last Name	SAML attribute used to pass the user last name.
Job Title	SAML attribute used to pass the user job title.
Email Addresses	SAML attribute used to pass the user email addresses. This property is required.
Emails Delimiter	Delimiter to separate the email addresses if multiple email addresses are passed.
Phone Number	SAML attribute used to pass the user phone number.
Time Zone	SAML attribute used to pass the user time zone.
These four properties are enabled when the **Map SAML Groups and Roles** option is enabled:	

includes user login attributes such as name, email address, and user role includes user login attributes such as name, email address, and user role The authentication response from the identity provider to Property	Description
User Roles	SAML attribute used to pass the assigned user roles.
Roles Delimiter	Delimiter to separate the roles if multiple roles are passed.
User Groups	SAML attribute used to pass the assigned user groups.
Groups Delimiter	Delimiter to separate the groups if multiple groups are passed.

The following table describes the additional attributes. These attributes are visible when the **Enable IdP to push users/groups using SCIM 2.0** option is enabled:


Property	Description
Display Name	SCIM attribute used to pass the user displayName.
Employee Number	SCIM attribute used to pass the enterprise user employeeNumber.
Organization	SCIM attribute used to pass the enterprise user organization.
Department	SCIM attribute used to pass the enterprise user department.
Street Address	SCIM attribute used to pass the user streetAddress.
Locality	SCIM attribute used to pass the user locality.
Region	SCIM attribute used to pass the user region.
Post Code	SCIM attribute used to pass the user postalCode.
Country	SCIM attribute used to pass the user country.
Locale	SCIM attribute used to pass the user locale.
Preferred Language	SCIM attribute used to pass the user preferredLanguage.
ID	SCIM attribute used to pass the user id.
External ID	SCIM attribute used to pass the user externalId. For Azure Active Directory, this is the objectID. For Okta, it is the id.

SAML role and group mapping properties

When you use SAML for authentication only, define a default role and optionally a default user group for new users. When you use SAML for both authentication and authorization, you can map specific SAML role and group names to IDMC role names. You can map multiple SAML roles and groups to a single IDMC role.

Note: For instructions on how to map groups with Azure Active Directory, see the HOW TO: Create a SAML Group Mapping with Azure AD Knowledge article.

When the **Map SAML Groups and Roles** option on the **SAML Setup** page is enabled, you can map specific IDMC roles and groups in the **SAML Role Mapping** and **SAML Group Mapping** tabs, as shown in the following image:



You can map multiple IDMC roles and groups, separated by commas.

When the **Map SAML Groups and Roles** option is disabled, all SAML roles and groups become non-editable, except for the following fields at the end of the list:

Property	Description
Default Role	Default user role for single sign-on users. When auto-provisioning is enabled, new users are assigned this role the first time they sign in to IDMC.
Default User Group	Optional, default user group for single sign-on users. When auto-provisioning is enabled, new users are assigned to this user group the first time they sign in to IDMC.

OAuth using JSON web tokens

If your organization is configured to use SAML and the organization uses the IDMC REST API, users can log in and start a REST API session using a JSON web token (JWT).

Using a JWT access token is similar to using a SAML assertion. However, unlike using SAML assertions, users fetch JWT access tokens from the identity provider and include the tokens in login requests.

Before users can use JWT access tokens, complete the following tasks:

- Configure the organization to use SAML and set up users as SAML users.
- Set up an OAuth identity provider. You can use identity providers such as Azure Active Directory and Okta.
- Set up a method to retrieve JWT access tokens from the identity provider.
- Register the identity provider using the IDMC REST API.

To log in, users obtain a JWT access token from the identity provider and include the token in a loginOAuth POST request. The token can be used for one REST API session. If the login request is successful, the response includes a session ID to use in subsequent API calls.

For information about OAuth setup using Azure Active Directory, see the following article:
Set up OAuth with Azure AD

For more information about identity provider configuration, see the identity provider's documentation.

For more information about registering identity providers and logging in using JWT access tokens, see *REST API Reference*.

CHAPTER 4


Users

A user is an individual IDMC account that allows secure access to an organization. A user can perform tasks and access assets based on the roles that are assigned to the user. You can assign roles directly to the user or to a group that the user is a member of.

Administrators can create and configure user accounts for the organization.

The **Users** page lists the users in your organization. To access the **Users** page, in Administrator, select **Users**.

The following image shows the **Users** page:



The **Users** page displays user statistics for the organization and lists each user.

The statistics area displays the total number of users, number of users with each status, number of users in groups, and the number of users that have logged in during the last 30 days. The number of users logged in during the last 30 days is calculated using the organization's time zone and excludes the current day.

The Users area lists each user. If you use Application Integration, the list includes the Application Integration anonymous user and its status. To view detailed information about a user, click the user name.

You can perform the following tasks for a user:

- View and edit user details.
- Create a user.
- Assign and unassign services.

- Disable a user.
- Reset a user.
- Reassign a user's scheduled jobs to a different user.
- Delete a user.

Note: When searching for a user, either search by the user name, or by the user's first or last name. You can't search by the user's full name.

Application Integration anonymous user

IDMC creates a system user called `CAI_Anonymous_<Organization_ID>`. Application Integration needs this user when you invoke an anonymous process that calls a Data Integration task.

Important: Do not edit or delete the Application Integration anonymous user if you need to invoke an anonymous process that calls a Data Integration task.

If you assign custom permissions to a Data Integration task and invoke the Data Integration task through an Application Integration process or a guide, you must complete either of the following tasks:


- Give the Application Integration anonymous user permission to run the associated Data Integration asset.
- Add the Application Integration anonymous user to a user group that has permission to run the associated Data Integration asset.

User statistics

If you have the Admin role or the Read User and Audit Log - View privileges, you can view user statistics for your organization.

The statistics area on the **Users** page displays statistics such as the number of users in the organization, the number of users with each status, and the number of users that logged in during a certain time period.

The following image shows the statistics area:



You can use the statistics area to filter the users on the **Users** page. For example, to display only users with the status Pending Activation, click **Users Pending Activation**. To list all users, click **Total Users**.


If you have the Admin role or the Create User and Audit Log - View privileges, you can view a graph of the numbers of users that logged in per day during the last 7, 30, or 90 days. To view the graph, click **Chart View** and select the appropriate time period. You can also download a report that lists the login date and time for each user during the time period.

To return to the list view of the **Users** page, click **List View**.

User details

You can configure user details such as user name, email, login settings, and assigned user groups and roles on the user details page. To display the user details page, in Administrator, select **Users**, and then click the user name.

The following image shows the user details page:



You can configure the following details for a user:

User information

The following table describes the user information:

Property	Description
First Name	First or given name of the user. Can contain only alphanumeric characters, hyphens, underscores, periods, and apostrophes.
Last Name	Last or family name of the user. Can contain only alphanumeric characters, hyphens, underscores, periods, and apostrophes.
Job Title	User's job title. Can contain only alphanumeric characters, hyphens, underscores, periods, and apostrophes.
Phone Number	Telephone number for the user. Can be 10-25 characters, with only the following characters permitted: numbers, spaces, parenthesis, period, and a plus sign as the first character.

Property	Description
Email	Email address of the user. Must be a valid email address in the format: <local_part>@<domain>. For example, jsmith@mycompany.com. To update the email address, click **Update Email**. IDMC sends a verification email to the new email address. The email contains a link that is valid for 24 hours. When the user clicks the link in the verification email, the new email address is verified, and it appears on the user details page and in the user's profile. If the link expires, you can resend the verification email. You can't update the email address for a SAML user in Administrator. To update a SAML user's email address, update the email address in the identity provider. **Note:** To update a user's email address, you must have access to the user's email address and user credentials.
Description	Optional user description.

Extended user attributes

If your organization uses SAML single sign-on for authentication and authorization and the identity provider pushes user and group information to IDMC using SCIM 2.0, this tab displays SCIM attributes such as the display name, employee number, organization, and department.

This tab does not appear for non-SAML users.

Login settings

The following table describes the login settings:

Property	Description
Authentication	Authentication method. Can be one of the following values: - **Native.** The user is authenticated through IDMC. The user logs in through the IDMC URL. - **Salesforce.** The user is authenticated through Salesforce and signs in through Salesforce or a Salesforce app. - **Azure SSO.** The user is authenticated and signs in through Microsoft Azure. - **IDP with SAML.** The user is authenticated and signs in through a SAML identity provider.
Identity Type	Identity type. Can be one of the following values: - Human. A real person who logs in to IDMC to interact with services. - Non-human. A user account for software, integrations, automated processes, and APIs that access services without human interaction. If multi-factor authentication is enabled, users need to be categorized as human to receive a verification code when they log in.

Property	Description
Activate using verification code / Activate using Salesforce OAuth	Account activation method for Salesforce users. Select one of the following options: - Activate using verification code. Select this option when the user signs in to IDMC through a Salesforce app. When you select this option, the user receives an email with a verification code. The user account is activated when the user logs in to Salesforce, opens the Salesforce app, and enters the verification code. - Activate using Salesforce OAuth. Select this option to activate the user account using Salesforce OAuth. When you select this option, the user receives an email with a **Confirm Account** link. The user account is activated when the user clicks the **Confirm Account** link and enters the Salesforce user name and password. These options are displayed when the authentication method is Salesforce.
Environment	Salesforce organization environment, either production or sandbox. This option displayed when the user activation method is Salesforce OAuth.
User Name	IDMC user name. Can either be a valid email address or a name that contains only alphanumeric characters, hyphens, underscores, periods, and apostrophes. The user name must be unique within the IDMC organization. You can't change the name after you save the user. This property is displayed when the authentication method is Native.
Salesforce User Name	Salesforce user name. Must be unique within the IDMC organization. You cannot change the name after you save the user. For Salesforce users, the IDMC user name is the same as the Salesforce user name unless that name is already used in the IDMC organization. If the name is already used, then IDMC appends the string ".Salesforce," ".Salesforce1," ".Salesforce2," etc. to the end of the Salesforce user name to form a unique IDMC user name. This property is displayed when the authentication method is Salesforce.
Azure User Name	Microsoft Azure user name. Must be unique within the IDMC organization. You cannot change the name after you save the user. For Microsoft Azure users, the IDMC user name is the same as the Azure user name unless that name is already used in the IDMC organization. If the name is already used, then IDMC appends the string ".Azure," ".Azure1," ".Azure2," etc. to the end of the Azure user name to form a unique IDMC user name. This property is displayed when the authentication method is Azure SSO.
SAML User Name	SAML user name. Must be unique within the IDMC organization. You cannot change the name after you save the user. For SAML users, the IDMC user name is the same as the SAML name identifier unless that name is already used in the IDMC organization. If the name is already used, then IDMC appends the string ".SAML," ".SAML1," ".SAML2," etc. to the end of the SAML name identifier to form a unique IDMC user name. This property is displayed when the authentication method is IDP with SAML.
Max Login Attempts	Maximum number of incorrect login attempts that the user can make before the user is locked out. Select a number. Default is 3. If locked out, the user can click the **Forgot your password** link on the Login page, or the organization administrator can reset the user on the **Users** page. This property is displayed when the authentication method is Native.

Property	Description
Account Status	Account status. Can be one of the following statuses: - Pending Activation. The user account has been created or reset, but the user has not yet activated the account. - Enabled. The user account has been created and validated, and the user can log in to IDMC. - Locked. Applies to native user accounts. The account is locked because the user has exceeded the maximum number of login attempts. To unlock the user, the user can click the **Forgot your password** link on the Login page, or you can reset the user on the **Users** page. - Disabled. The user account has been disabled by an administrator. The user cannot log in to IDMC.
Initial Application	This field is reserved for future use.
Effective Default Service	Default service that opens when user logs in, as set by the administrator. Users can override this setting by selecting a default service on the **My Services** page.
Force password reset on next login	Forces the user to reset the password the next time the user tries to log in. This property is displayed when the authentication method is Native.

Group, role, and service assignments

You must assign at least one user group or role to each user.

When you assign a group to a user, all roles that are associated with the group become enabled. You cannot remove these roles individually. To remove the roles, you must remove the group.

You can let a user's group membership define the user's service assignments, or you can assign a service to a user regardless of whether the user's group membership allows access to the service.

Note: If your organization uses SAML for authentication and authorization, you cannot edit user details for a SAML user. User details are mapped automatically according to the mapped attributes, roles, and groups on the **SAML Setup** page.

Creating a user

Create a user on the **Users** page. When you create a user, the user status is set to Pending Activation or to Enabled based on the authentication method.

1. In Administrator, open the **Users** page.
2. Select **Add User**.
3. Enter the user information.
4. In the **Login settings** section, select the authentication method and enter the appropriate login settings.
   - For a native user, select the identity category, enter the IDMC user name, and select the maximum number of login attempts.
   - For a Salesforce user, specify whether to activate the user account using a verification code or Salesforce OAuth. Then, enter the user name in the third-party identity provider's system.
   - For a Microsoft Azure or SAML user, enter the user name in the third-party identity provider's system.

The user name must be unique within the IDMC organization. You can't change the user name after you create a user.

5. In the **Group, Role, and Service Assignment** section, select the user groups or roles that you want to assign to the user.

   You can assign system-defined and custom roles to a user. If you assign a group, the user inherits all roles that are associated with the group.

6. Optionally, assign services to the user and set the default service to open when the user logs in.

   By default, the user can access services based on the organization's licenses and the user groups that the user belongs to.
   Users can override the default service that you select when they select a default service on the **Services** page.

7. Click **Save**.

After you create a user, the user status is set as follows based on the authentication method:

- Native users are set to Pending Activation. The user receives an email to confirm the account. When the user clicks the **Confirm Account** link in the email, the user is prompted to set up a password and security question. After the user does this, the status changes to Enabled, and the user can log in to IDMC.
- Salesforce users are set to Pending Activation.

  If you activate the user using a verification code, the user receives an email with a verification code. The user account is activated when the user logs in to Salesforce, opens the Salesforce app, and enters the verification code.

  If you activate the user using Salesforce OAuth, the user receives an email with a **Confirm Account** link. The user account is activated when the user clicks the **Confirm Account** link and enters the Salesforce user name and password.
- Microsoft Azure and SAML users are set to Enabled. The user can sign in through the user's identity provider.

Assigning and unassigning services

When you create a user, the user can access services based on the organization's licenses, the user's roles, and the groups to which the user belongs.

Users normally inherit the services assigned to their user groups. However, you can specifically allow or deny access to services on the **Users** page.

When a user has access to a service, the service is visible on the **Services** page. The user can access and use the service as long as access is allowed.

When a user loses access to a service, the user can no longer see the service on the **Services** page.

Important: Allowing or denying a service only reveals or hides the service from the user interface. The user retains all privileges associated with their assigned roles, even if you explicitly deny a service. This means that the user might be able to perform an action through the API even if access is denied. As a best practice, only assign privileges that align with services assigned to a user.

From the services assigned to a user, you can select the default service to open when the user logs in.

You can set the default service at the user level or the user group level. The user can also select the default service on the **Services** page. If the default service is set at multiple levels, the setting that the user makes on the **Services** page takes precedence, followed by the user level, and then the user group level.

1. In Administrator, select **Users**.
2. From the list of users, click the user's name.
3. In the **Group, Role, and Service Assignment** section, on the **Services** tab, perform one of the following tasks for each service:
   - To let the user's group memberships define whether the user can access the service, leave both the **Allow** and **Deny** options deselected. If the group's services change, the user's access to services changes automatically.
   - To allow access to the service regardless of what's defined in the user's group, select the **Allow** option.

     Tip: If you don't see the service you wish to assign, that means the service isn't present in the organization's license.
   - To deny access to the service, regardless of whether the user's group allows it, select the **Deny** option.
4. Optionally, select the default service to open when the user logs in.
5. Click **Save**.

Disabling a user

Disable a user on the **Users** page. When you disable a user, the user can no longer log in to IDMC.

Before you disable a user, verify that the user did not schedule any tasks or taskflows. If you disable a user who has scheduled tasks or taskflows, the scheduled jobs fail.

When you disable a user, the user remains in the organization and in the IDMC repository. You can view the user details, but you cannot edit them. Assets that the user created or updated also remain in the organization. On the Explore page, the Created by and Updated by columns indicate that the user is disabled.

1. In Administrator, select **Users**.
2. In the row that contains the user whom you want to disable, click **Actions** and select **Disable**.

   Note: When you use a file listener in Mass Ingestion Files (as a trigger or as a source) and in taskflow (as a trigger), you must reassign the ownership of the file listener association from one user to another using the REST API before you disable a user. For more information, see *REST API Reference*.

Resetting a user

Reset a user on the **Users** page. You can reset a user whose account is disabled or locked. When you reset a user, the user status is set to Pending Activation or to Enabled based on the authentication method.

You can't reset a SAML user who was provisioned using SCIM or who is pending activation. For password assistance in these instances, contact your SAML administrator.

1. In Administrator, select **Users**.
2. In the row that contains the user, click **Actions** and select **Reset**.

After you reset a user, the user status is reset differently based on the authentication method:

- Native users are set to Pending Activation. The user receives an email to confirm the account. When the user clicks the **Confirm Account** link in the email, the user is prompted to reset the password and security question. The user can then log in to IDMC.
- Salesforce users are set to Pending Activation.

  If you activated the user using a verification code, the user receives an email with a verification code. The user account is activated when the user logs in to Salesforce, opens the Salesforce app, and enters the verification code.

  If you activated the user using Salesforce OAuth, the user receives an email with a **Confirm Account** link. The user account is activated when the user clicks the **Confirm Account** link and enters the Salesforce user name and password.
- Microsoft Azure and SAML users are set to Enabled. The user can sign in through the user's identity provider.

Reassigning a user's scheduled jobs

Reassign a user's scheduled jobs on the **Users** page. You might want to reassign scheduled jobs when a user that has scheduled tasks or taskflows leaves the organization. You must reassign a user's scheduled jobs before you can delete or disable the user.

The owner of a scheduled job is the last person that saves the scheduled task or taskflow. For example, in your organization, user Arun creates a schedule, user Beth creates a mapping task and assigns the schedule to the task, and then user Chandra updates and saves the task. Chandra becomes the owner of the scheduled job. If Chandra leaves the organization, you must reassign her scheduled jobs to another user before you can delete or disable her user account.

1. In Administrator, select **Users**.
2. In the row that contains the user, click **Actions** and select **Reassign Scheduled Jobs**.
3. Select a user to whom to reassign the scheduled jobs.

   The user you select must be an enabled user.
4. Click **Reassign**.

You can reassign the ownership of a file listener association from one user to an another using REST API. For more information, see *REST API Reference*.

Deleting a user

Delete a user on the **Users** page. When you delete a user, the user is removed from the organization and from the IDMC repository. If your organization uses SAML for authentication and authorization, you cannot delete a SAML user that you did not create in Administrator.

Before you can delete a user, you must reassign the user's scheduled jobs to a different user.

Note: You cannot reset a deleted user. If you think you might need to reactivate the user account, disable the user instead of deleting the user.

1. In Administrator, select **Users**.

2. In the row that contains the user whom you want to delete, click **Actions** and select **Delete**.
3. If the user is the owner of any scheduled tasks or taskflows, Administrator prompts you to reassign the jobs to a different user. Select the user to whom you want to reassign the jobs and click **Reassign and Delete**.

   Note: When you use a file listener in Mass Ingestion Files (as a trigger or as a source) and in taskflow (as a trigger), you must reassign the ownership of the file listener association from one user to another using the REST API before you delete a user. For more information, see *REST API Reference*.

If the user did not own scheduled tasks or taskflows, Administrator deletes the user. If the user was the owner of any scheduled tasks or taskflows, Administrator reassigns the jobs and then deletes the user.

CHAPTER 5


User groups

A user group is a group of users in which all members can perform the same tasks and have the same access rights for different types of assets. Members of a group can perform tasks and access assets based on the roles that you assign to the group.

Administrators can configure user groups for the organization.

The **User Groups** page displays a list of all user groups in the organization. To access the **User Groups** page, in Administrator, select **User Groups**.

The following image shows the **User Groups** page:




You can perform the following tasks for a user group:

- View and edit group details.
- Create a group.
- Rename a group.
- Delete a group.

User group details

You can configure details about a user group that include the group information, assigned roles, group members, assigned services, and default service to open at login. To display the group details page, in Administrator, click **User Groups**, and then click the group name.

The following image shows the group details page:



You can configure the following details for a user group:

Property	Description
Name	Required. Name of the user group. Must be unique within an organization. You can change the group name after you create it.
Description	Optional description for the user group.
Roles	Roles that are assigned to all members of the group. You must assign at least one role to each group.

Property	Description
Members	Users who are assigned to the group. Use the **Manage Users** button to add or remove users from the list. When you assign a user to a group, the user is automatically assigned all roles and services that are assigned to the group.
Services	Services to which the group has access and the default service to open when a user who's a member of the user group logs in. The list includes all the services in the organization's license. By default, a user group is assigned all the services the organization is licensed to use. When you add a user to a group, that user gains access to all of the group's services provided that all the following conditions are met: - At least one of the user's roles allow access to the service. - The user is not explicitly "denied" access to the service. For more information about a user's role, see "User details" on page 34. For more information about explicitly allowing or denying access to services for a user, see "Assigning and unassigning services " on page 38. **Note:** By explicitly allowing access, it is possible for a user to have access to a service that is not included in the user's group membership.

Note: You cannot edit group details for a SAML group. SAML groups are identified with the label **Mirrors the SAML group: <group name>** in the Group Information area.

Creating a user group

Create a user group when multiple users in your organization need to perform the same tasks and need the same access rights for different types of assets, or if they need access to the same services. Group members can perform tasks and access assets based on the roles that you assign to the group. Create a user group on the **User Groups** page.

1. In Administrator, select **User Groups**.
2. Click **Add Group**.
3. Enter a group name and optional description.

   The group name must be unique within an organization.
4. In the **Role, Membership, and Service Assignment** section, on the **Roles** tab, select the roles that you want to assign to the group.

   You can assign system-defined and custom roles to a group. The roles apply to all members of the group.
5. Optionally, assign users to the group.

   To assign a user to the group, on the **Members** tab, click **Manage Users** and select the user from the list. The list of available users does not include SAML users because you can't assign SAML users to a group.

   You can also assign a user to a group when you create or edit a user.
6. On the **Services** tab, select the services that are enabled for the group.

You can override service access at the user level, so that members of this user group can have access to services that differ from the user group.

7. Optionally, select the default service that will open when users who are members of the user group log in.

   If a user belongs to multiple user groups, the last modified user group that has a specified default service is used to determine the service that opens when the user logs in. If the default service isn't accessible to the user, the next user group with a default service that the user can access is used.

8. Click **Save**.

Renaming a user group

Rename a user group on the **User Groups** page. You can also edit the user group and change the group name on the Group Details page. You cannot rename a SAML group.

1. In Administrator, select **User Groups**.
2. In the row that contains the user group, click **Actions** and select **Rename**.
3. Enter the new name and click **Save**.

Deleting a user group

Delete a user group on the **User Groups** page. You cannot delete a SAML group if your organization uses SAML SSO for authentication and authorization.

Tip: Before you delete a user group, verify that all group members have appropriate roles or are assigned to other groups so that they can continue to use IDMC without interruption.

1. In Administrator, select **User Groups**.
2. In the row that contains the user group, click **Actions** and select **Delete**.

CHAPTER 6

User roles

A role is a collection of privileges that you can assign to users and groups. To ensure that every user can access assets and perform tasks in your organization, assign at least one role to each user or user group.

A role defines the privileges for different types of assets and service features. For example, users with the Designer role can create, read, update, delete, and set permissions on most types of data integration assets. However, they have no access to certain Administrator service features such as sub-organizations and audit logs.

Organization administrators can configure and assign roles for the organization.

You can assign the following types of roles:

System-defined


System-defined roles are pre-defined roles that define access privileges for the services that your organization uses. The system-defined roles that you can assign to users and user groups vary based on your organization's licenses. You can't edit, rename, or delete system-defined roles. You can clone system-defined roles except for the Admin role.

Custom roles

Custom roles are roles that you create to set privileges individually. To create custom roles, you need the appropriate license. You can edit, clone, rename, and delete custom roles.

You can view both system-defined and custom roles on the **User Roles** page. The **User Roles** page displays a list of all roles in the organization. To access the **User Roles** page, in Administrator, select **User Roles**.

The following image shows the **User Roles** page:



The Status column indicates whether the role is enabled or disabled for your organization. A role is disabled when the license expires.


You can assign multiple roles to a user or user group. When you assign multiple roles, the user or group inherits the access privileges associated with all of the roles.

Role details

The role details page displays information about a role, including the asset and feature privileges that are associated with the role. For system-defined roles, you can view the role information and privileges. For custom roles, you can view and change the role information and the assigned asset and feature privileges.

To display the role details page, in Administrator, select **User Roles**, and then click the role name.

The following image shows the role details page:



Each role has the following properties:

Role name

Name of the role. For custom roles, you can change the role name.

Description

Role description. For custom roles, you can change the role description.

Services

Name of the service for which privileges are enabled or disabled. Select a service to view the asset and feature privileges that are associated with the service.

If the license for a service expires, the service is marked as disabled. You can view the asset and feature privileges that are associated with a disabled service.

Assets

Asset privileges for the selected service. Asset privileges control access to different types of assets. For example, users with the Service Consumer role can view and run mappings in Data Integration, but they can't create, update, delete, or set permissions on mappings.

If a privilege doesn't apply to an asset type, the privilege is disabled. For example, the run privilege is disabled for folders.

For custom roles, you can enable and disable the asset privileges for a service as long as the service is not disabled.

Features

Feature privileges for the selected service. Feature privileges are general privileges that control the ability to use the features of a service. For example, users with the Designer role have the ability to perform data catalog discovery in Data Integration but not to preview data.

For custom roles, you can enable and disable feature privileges for a service as long as the service is not disabled.

For more information about asset and feature privileges, see "Role asset and feature privileges" on page 68.

System-defined roles

IDMC provides system-defined roles that you can assign to users or user groups. You can't change or delete the system-defined roles.

The system-defined roles that you can assign to users and groups vary based on your organization's licenses. For example, if your organization has no access to Application Integration, you can't assign the Application Integration Business Manager or Application Integration Data Viewer role to any user or group in your organization.

There are two types of system-defined roles:

Cross-service roles

Cross-service roles define access privileges across multiple services. For example, users with the Deployer role can access some features in API Center, Application Integration, Application Integration Console, Data Quality, and Data Ingestion and Replication.

Service-specific roles

Service-specific roles define access privileges for one service or for a group of closely related services. For example, users with the Governance User role can access Data Governance and Catalog but have no access to other services unless you assign additional roles.

Note: Don't assign the system-defined role "Dataloader admin" to any users. This role is used with Informatica Data Loader only.

Cross-service roles

Cross-service roles are system-defined roles that define access privileges across multiple services.

The following table describes the cross-service roles:

Cross-service role	Provides access to...	Description
Admin	All services	Role for organization administrators. Provides full access to all licensed services with the following exceptions: - Doesn't provide privileges to enable or disable the use of customer managed encryption keys for the organization. To provide these privileges, assign the user both the Admin and Key Admin roles. - Doesn't provide full access to all MDM services. For example, doesn't allow the user to access the workflow inbox or create hierarchies in MDM business services. To provide full access to MDM services, assign the user an appropriate MDM service-specific role. **Tip:** Best practice is to assign the Admin role to one or two trusted users and assign the users to an administrative user group that has full permissions on all asset types. These users can act as alternative organization administrators and can help troubleshoot access control and other organization security issues.
Data Integration Data Previewer	- Data Integration - Data Profiling - Data Quality - Data Validation	Supplemental role that allows designers to preview data while creating mappings, tasks, profiles, and test cases. Allows users to perform the following tasks: - Preview data in a mapping or task in Data Integration. - Preview data on a data quality transformation in a mapping in Data Integration. - View source object data for profiles and profile results in Data Profiling. - Preview data while creating test cases in Data Validation. **Note:** This is a supplemental role. Assign this role with another role, such as the Designer role, to ensure that users can access Data Integration, Data Profiling, and Data Validation.
Data Integration Task Executor	- Data Integration - Data Access Management	Role for running tasks and taskflows and executing data access policies. Allows users to perform the following tasks: - View assets and asset details in Data Integration. - Run tasks and taskflows and test-run mappings in Data Integration. - View user's own data integration jobs and job details in Data Integration. - Start and stop user's own jobs in Data Integration. - Download session logs in Data Integration. - Execute data access policies in Data Integration. - Access Data Access Management. - View data access policies in Data Access Management.
Deployer	- API Center - Application Integration - Application Integration Console - Data Ingestion and Replication - Data Quality - Data Validation	Role for users that deploy assets and processes. Allows users to perform the following tasks: - View and deploy assets, assign policies, manage organization settings, and add OAuth 2.0 clients in API Center when assigned with the Service Consumer role. - View asset details in Application Integration. - Deploy assets, view settings, and upload and deploy Process Developer-generated orchestration artifacts (BPRs) in Application Integration Console. - View asset details except dictionary data in Data Quality. - View application ingestion, database ingestion, and streaming ingestion tasks in Data Ingestion and Replication. - View test cases, test suites, and reports in Data Validation. - Run test cases and test suites in Data Validation.

Cross-service role	Provides access to...	Description
Designer	- Administrator - API Center - Application Integration - Application Integration Console - B2B Gateway - Data Ingestion and Replication - Data Integration - Data Profiling - Data Quality - Data Validation - Integration Hub - Monitor	Role for users that create assets, tasks, and processes. Allows users to perform the following tasks: - Create assets, tasks, and processes. Includes creating and summarizing assets using CLAIRE Copilot. - Configure connections, schedules, and runtime environments. - Monitor jobs and advanced clusters, except in Mass Ingestion. - View, create, and edit test cases and test suites in Data Validation. Provides full access to Application Integration, B2B Gateway, Data Integration, Data Profiling, Data Quality, and Monitor. Provides full access to API Center when the Service Consumer role is also assigned. Provides partial access to Administrator, API Center, Application Integration Console, Data Ingestion and Replication, Integration Hub, and Data Validation.
Monitor	- Administrator - API Center - Application Integration - Application Integration Console - B2B Gateway - Data Ingestion and Replication - Data Integration - Data Profiling - Data Quality - Integration Hub - Monitor	Role for users that monitor jobs. Allows users to perform the following tasks: - Monitor API Center assets, Data Integration jobs, Data Quality assets, Integration Hub assets, Data Ingestion and Replication jobs, and Application Integration process instances. - View schedules and upgrade settings for Secure Agent services in Administrator. - Start and stop file servers, configure proxy servers, and view file server settings in Administrator. - View asset details in Application Integration, B2B Gateway, Data Integration, Data Profiling, and Integration Hub. - View asset details except dictionary data in Data Quality. - Summarize assets using CLAIRE Copilot. - View settings in Application Integration Console. - View API invocation logs in API Center. - View application ingestion, database ingestion, and streaming ingestion jobs and job details in Data Ingestion and Replication. - View data integration and job details in Monitor.
Operator	- Application Integration - Application Integration Console - Data Profiling - Data Quality - Operational Insights	Role for users that manage processes. Allows users to perform the following tasks: - View asset details in Application Integration and Data Profiling. - Manage process instances and modify some operational server parameters in Application Integration. - View and edit Process Server settings and some Cloud Server settings in Application Integration Console. - View asset details except dictionary data in Data Quality. - View cloud and domain infrastructure and Secure Agent alert settings in Operational Insights.
Service Consumer	- Administrator - Application Integration - Data Integration - Data Quality	Role for users that run tasks and processes. Allows users to perform the following tasks: - View schedules, Swagger files, and upgrade settings for Secure Agent services, start and stop file servers, configure proxy servers, and view other file server settings in Administrator. - Invoke processes in Application Integration. - View tasks, run tasks, test-run mappings, run taskflows, and download workflow XML in Data Integration. - View asset details except dictionary data in Data Quality.

Administrator roles

To provide access to the Administrator service, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Administrator:

Role	Description
Admin*	Provides full access to Administrator except for privileges to enable or disable the use of customer managed encryption keys for the organization. To allow this ability, assign the user both the Admin and Key Admin roles.
Designer*	Allows users to perform the following tasks in Administrator: - Configure connections, runtime environments, schedules, Swagger files, and advanced configurations. - Install add-on connectors and install and uninstall add-on bundles. - View upgrade settings for Secure Agent services. - Start and stop file servers, configure proxy servers, and view other file server settings.
Elastic RTE Manager	Allows users to manage elastic runtime environments. Users can perform the following tasks: - Deploy an elastic runtime environment. - Get information about elastic runtime environment images from Informatica's artifactory. - Perform operations on the tokens that are required to pull images.
Key Admin	Allows users to enable and disable the use of customer managed encryption keys for their organization on the **Security** tab of the **Settings** page. Assign this role to a user who also has the Admin role. If the user doesn't have both roles, they can't see the **Security** tab. For more information about customer managed encryption keys, see *Organization Administration*.
Monitor*	Allows users to perform the following tasks in Administrator: - View schedules and upgrade settings for Secure Agent services. - Start and stop file servers, configure proxy servers, and view other file server settings.
Service Consumer*	Allows users to perform the following tasks in Administrator: - View schedules, Swagger files, and upgrade settings for Secure Agent services. - Start and stop file servers, configure proxy servers, and view other file server settings.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

AI Agent Engineering roles

To provide access to AI Agent Engineering, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to AI Agent Engineering:

Role	Description
Admin*	Provides full access to AI Agent Engineering.
Designer*	Provides full access to AI Agent Engineering.
Monitor*	Allows users to view MCP servers and deployed MCP server instances.

Role	Description
Operator*	Allows users to view MCP servers and update composite MCP servers. Also allows users to view, update, delete, and run composite deployed MCP server instances.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

API Center roles

To provide access to API Center, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to API Center:

Role	Description
Admin*	Provides full access to API Center.
API Policy Manager	Allows users to define policies. Allows users to access the following pages in API Center: - Explore (read-only) - Policies
Deployer*	When assigned with the Service Consumer role, allows users to view and deploy assets, assign policies, manage organization settings, and add OAuth 2.0 clients in API Center. Allows users to access the following pages: - Explore (read-only) - API Console - Configuration **Note:** To provide these privileges, you must assign both the Deployer and Service Consumer roles.
Designer*	When assigned with the Service Consumer role, provides full access to all asset privileges and allows users to assign policies in API Center. Allows users to access the following pages: - New Asset - Explore **Note:** To provide these privileges, you must assign both the Designer and Service Consumer roles.
Monitor*	Allows users to monitor API Center assets. Allows users to access the following pages: - Explore (read-only) - API Monitor
Service Consumer*	Allows users to access API Center when the Designer or Deployer role is also assigned.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

For more information about API Center roles, see the API Center help.

Application Integration and Application Integration Console roles

To provide access to Application Integration and Application Integration Console, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Application Integration and Application Integration Console:

Role	Description
Admin*	Provides full access to Application Integration and Application Integration Console. Has the execution privileges.
Application Integration Business Manager	Role for monitoring business activity. Users with this role can view information about assets and process instances, but they can't change them. Allows users to perform the following tasks: - View folder and asset lists and asset details in Application Integration. - Access the Processes, APIs, and Connections pages in Application Integration Console.
Application Integration Data Viewer	Supplemental role that allows users to view detailed logs in Application Integration Console. Assign this role along with at least one other role. For example, if you want a user with the Designer role to view detailed Process Server logs, assign the user the Application Integration Data Viewer and the Designer roles, and set the Process Server logging level to verbose. **Note:** Users can view detailed logs for an artifact when the logging level is set to verbose.
Deployer*	Allows users to perform the following tasks in Application Integration and Application Integration Console: - View asset details in Application Integration. - Deploy assets and view settings on the Processes, Logs, Server Configuration, Deployed Assets, and Resources pages in Application Integration Console. - Upload and deploy Process Developer-generated orchestration artifacts (BPRs) in Application Integration Console. Assign this role in a production environment where deployment access is typically restricted.
Designer*	Provides full access to Application Integration. Allows users to view and edit all settings except server configuration properties in Application Integration Console.
Monitor*	Allows users to perform the following tasks in Application Integration and Application Integration Console: - View asset details in Application Integration. - View settings in Application Integration Console.
Operator*	Allows users to perform the following tasks in Application Integration and Application Integration Console: - View asset details in Application Integration. - View and edit Process Server settings and some Cloud Server settings in Application Integration Console. For example, a user with the Operator role can create an alert service but can't view tenant details.
Service Consumer*	Allows users to execute Application Integration processes through APIs.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

B2B Gateway roles

To provide access to B2B Gateway, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to B2B Gateway:

Role	Description
Admin*	Provides full access to B2B Gateway.
Designer*	Provides full access to B2B Gateway.
Monitor*	Allows users to view asset details.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

B2B Partners Portal roles

If your organization uses B2B Gateway, you might want to enable access to B2B Partners Portal for your external trading partners. To give your trading partners access to B2B Partners Portal, create a custom role and assign it to partner users.

Note: There is no system-defined role for B2B Partners Portal external trading partners. Therefore, you'll need to create a custom role for them.

When you create a custom role for partner users, name the role so that you know it is for B2B Partners Portal users. For example, you might name the role "B2B Partners Portal User."

Optionally, you can give the role a description. Clearly describe the role so that you know it is for users from partner companies. For example, you might describe the role as "Role for users from partner companies to access the B2B Partners Portal service."

When you create a custom role for B2B Partners Portal users, enable the Partners Portal feature privilege for the B2B Partners Portal service. For more information about creating custom roles, see "Creating a custom role" on page 66.

Assign the custom role to users from your partner companies. You only need to create one role for B2B Partners Portal users. Assign the same role to all external B2B Partners Portal users.

Business 360 Console roles

To provide access to Business 360 Console, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Business 360 Console:

Role	Description
Admin*	Provides full access to Business 360 Console. Allows users to perform solution upgrades. **Note:** To provide full access to Business 360 Console, assign users the Admin, Designer, and MDM Designer user roles. To allow users to perform only the configuration tasks in Business 360 Console, you can assign users the Admin role or both the Designer and MDM Designer roles.
Business 360 Process Executor	Required role for users with custom user roles to perform tasks in Business 360 Console and business applications. Allows users to update business entities in Business 360 Console. Allows users to perform the following tasks in business applications: - Save records and custom reports. - View, create, update, and delete hierarchies. - Import records, related records, and hierarchy data. - Access the **Workflow Inbox** page.
Designer*	Allows users to perform tasks in Business 360 Console that require integration with other services such as Data Integration and Data Quality. Allows users to perform the following tasks in Business 360 Console: - Create MDM SaaS assets except reference data assets. - Define a data model and source systems. - Define and monitor jobs, such as ingress and egress. - Configure data quality, match and merge, survivorship, business events, and global settings. Doesn't allow users to define reference data assets.
Job Executor	Allows users to run ingress and egress jobs in Business 360 Console. **Note:** This role is not required to run jobs that business applications run when users perform tasks, such as file import.
MDM Designer	Allows users to perform the following tasks in Business 360 Console: - Create MDM SaaS assets. - Define a data model and source systems. - Define and monitor jobs, such as ingress and egress. - Configure data quality, match and merge, survivorship, business events, and global settings. - Export and import assets when the user also has the Designer role.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

For more information about Business 360 Console roles, see the Business 360 Console help.

CLAIRE GPT roles

To provide access to CLAIRE GPT, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined user role that provides access to CLAIRE GPT:

Role	Description
CLAIRE GPT User	Provides full access to all the capabilities of CLAIRE GPT.

For more information about CLAIRE GPT user roles, see the CLAIRE GPT help.

Cloud Data Integration for PowerCenter (CDI-PC) roles

To provide access to the CDI-PC service, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to CDI-PC:

Role	Description
Domain Management	Provides full access to CDI-PC.

Customer 360 SaaS roles

To provide access to MDM - Customer 360 SaaS, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to MDM - Customer 360 SaaS:

Role	Description
Customer 360 Analyst	Role for creating records. Allows users to create, edit, and delete records in MDM - Customer 360 SaaS. When a Customer 360 Analyst creates or edits a record, the changes trigger a review process that requires approval from a Customer 360 Manager.
Customer 360 Data Steward	Role for creating records and hierarchies. Allows users to perform any task in Customer 360 SaaS, including the following tasks: - Create, edit, and delete records without approval. - Run jobs. - Review and approve customer records.
Customer 360 Manager	Role for managing records. Allows users to perform the following tasks: - Review and approve or reject customer records. - Create, edit, and delete records without approval.
MDM Business User	Allows users to view records in Customer 360 SaaS but not create or edit them.

For more information about Customer 360 SaaS roles, see the MDM - Customer 360 SaaS help.

Data Governance and Catalog roles

To provide access to Data Governance and Catalog, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Data Governance and Catalog:

Role	Description
Admin	Role for exporting assets in Data Governance and Catalog.
Data Access Owner	Role for viewing and managing data access assets on the Data Access Management page.
Governance Administrator*	Role for administering and managing assets in Data Governance and Catalog and Metadata Command Center. Allows users to perform the following tasks in Data Governance and Catalog: - Export and import assets. - Participate in change approvals. - View the Data Access Management page. - View the latest preview of failed rows for data quality rule occurrences.
Governance Owner*	Role for managing assets in Data Governance and Catalog. Allows users to perform the following tasks in Data Governance and Catalog: - Export and import assets. - Participate in change approvals. - View the latest preview of failed rows for data quality rule occurrences.
Governance User*	Role for exporting assets in Data Governance and Catalog. Allows users to export assets in Data Governance and Catalog.
*Also provides access to Data Marketplace and Metadata Command Center. For more information, see "Data Marketplace roles" on page 59 and "Metadata Command Center roles" on page 63. To perform cataloging and governance tasks, the administrator must create and assign access policies to these user roles in Metadata Command Center. For more details, see *Administration* in the Metadata Command Center help.	

For more information about Data Governance and Catalog roles, see the Data Governance and Catalog help.

Data Ingestion and Replication roles

To provide access to Data Ingestion and Replication, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Data Ingestion and Replication:

Role	Description
Admin*	Provides full access to Data Ingestion and Replication.
Deployer*	Allows users to view application ingestion, database ingestion, and streaming ingestion tasks.
Designer*	Allows users to create, view, edit, delete, run, and set permissions on application ingestion, database ingestion, and streaming ingestion tasks. Also allows users to create and summarize assets using CLAIRE Copilot.

Role	Description
Monitor*	Allows users to view application ingestion, database ingestion, and streaming ingestion jobs and job details. Also allows users to summarize assets using CLAIRE Copilot.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

Data Integration roles

To provide access to Data Integration, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Data Integration:

Role	Description
Admin*	Provides full access to Data Integration.
Data Integration Data Previewer*	Supplemental role that allows users to perform the following tasks in Data Integration: - Preview data when they select a source, target, or lookup object for use in a mapping or task. - Preview data when on a data quality transformation that they select in a mapping. Assign this role with another role, such as the Designer role, to ensure that users can access Data Integration.
Data Integration Task Executor*	Role for running tasks and taskflows. Allows users to perform the following tasks in Data Integration: - View assets and asset details. - Run tasks and taskflows and test-run mappings. - View user's own data integration jobs and job details. - Start and stop user's own jobs. - Download session logs.
Designer*	Provides full access to Data Integration.
Monitor*	Allows users to view asset details in Data Integration. Also allows users to summarize assets using CLAIRE Copilot.
Service Consumer*	Allows users to view tasks, run tasks, test-run mappings, run taskflows, and download workflow XML in Data Integration.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

Data Marketplace roles

To provide access to Data Marketplace, assign users the appropriate roles. You can assign a system-defined role to Data Marketplace users.

The following table describes the system-defined roles that provide access to Data Marketplace:

Role	Description
Data Marketplace Administrator	Role for performing administrative tasks. Provides full access to access to Data Marketplace.
Data Marketplace Category Owner	Role for users that have the rights to a category. Allows users to perform the following tasks: - Create and bulk create data collections within the user's category. - Add and remove data assets inside data collections within the user's category. - Approve and reject data orders for data collections. - Approve and reject data collection requests on categories that the user is responsible for. - Add and edit delivery targets inside data to collections within the user's category. - Link and remove variants to data collections within the user's category. - Delete data collections within the user's category. - Rate data collections that the user has access to against the context the user has access with. - Search for published data collections. - Compare collections. - Add and bulk add data assets to data collections. - Create an order and raise data collection requests. - Create, bulk create, modify, and delete categories. - Add and remove terms of use inside data collections within the user's category. - Participate in public discussion channels. - Comment on private channels that the user has access to.
Data Marketplace Data Collection Owner	Role for users that have rights to a data collection. Allows users to perform the following tasks: - Create, bulk create, modify, and delete data collections. - View data collections that the user owns. - Add and bulk add terms of use and data assets to data collections that the user owns. - Remove terms of use and data assets from data collections that the user owns. - Search for published data collections. - Compare collections. - Add and edit delivery targets inside the data collections that the user owns. - Rate data collections that the user has access to against the context the user has access with. - Create an order for collections and raise data collection requests against collections or categories. - Complete and reject data collection requests raised on data collections that the user owns. - Approve and reject data collection access requests. - Link variants. - Participate in public discussion channels. - Comment on private channels that the user has access to.

Role	Description
Data Marketplace Data Collection Technical Owner	Role for users that have technical rights to a data collection. Allows users to perform the following tasks: - View orders for data collections. - Add and edit delivery targets to data collections. - Request withdrawal and withdraw access to data collections. - Add and remove data assets and terms of use inside data collections. - Rate data collections that the user has access to against the context the user has access with. - Search for published data collections. - Compare collections. - Create an order on collections and raise data collection requests against collections and categories. - Bulk create "terms of use - data collection" relationships and "delivery target - data collection" relationships. - Deliver data that is ordered by a data user. - Participate in public discussion channels. - Comment on private channels that the user has access to.
Data Marketplace Delivery Owner	Role for managing the delivery option for delivering data collections. Allows users to perform the following tasks: - Search and compare data collections. - Rate data collections that user has access to. - Create delivery options and delivery targets. - Bulk create delivery formats, delivery methods, delivery templates, and "delivery target - data collection" relationships. - Request withdrawal of consumer access, withdraw consumer access, and fulfill data orders for data collections that have a delivery option that the user is responsible for. - Participate in public and private discussion channels that the user has access to.
Data Marketplace Technical Administrator	Role for performing technical administrative tasks. Allows users to perform the following tasks: - View data orders for and add delivery targets to data collections. - Deliver requested data collections to data users. - Search and compare data collections. - Rate data collections that the user has access to. - Add data assets, delivery targets, and terms of use to data collections. - Bulk create data elements, data assets, and consumer accesses. - Delete data elements and data assets. - Modify object labels. - Configure data delivery formats and methods. - Configure default delivery targets to deliver data. - Import assets from Data Governance and Catalog. - Configure the general "terms of use" message and create new terms of use. - Create cost centers. - Request withdrawal and withdraw consumer accesses. - Bulk create cost centers, delivery formats, delivery methods, delivery templates, "terms of use - data collection" relationships, and "delivery target - data collection" relationships. - Configure star owners. - Participate in public and private discussion channels that the user has access to. - Customize the Data Marketplace user interface.
Data Marketplace User	Role for using data collections. Allows users to perform the following tasks: - Order, and compare data collections. - Search for published data collections. - View requested and delivered data collections. - View data collection details. - Rate data collections that the user has access to. - Create and cancel data collection requests on collections and categories. - Participate in public and private discussion channels.

Role	Description
Governance Administrator	Role for using data collections. Allows users to perform the following tasks: - Order, and compare data collections. - Search for published data collections. - View requested and delivered data collections. - View data collection details. - Rate data collections that the user has access to. - Create and cancel data collection requests on collections and categories. - Participate in public and private discussion channels.
Governance User	Role for using data collections. Allows users to perform the following tasks: - Order, and compare data collections. - Search for published data collections. - View requested and delivered data collections. - View data collection details. - Rate data collections that the user has access to. - Create and cancel data collection requests on collections and categories. - Participate in public and private discussion channels.

For more information about Data Marketplace roles, see the Data Marketplace help.

Data Profiling roles

To provide access to Data Profiling, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Data Profiling:

Role	Description
Admin*	Provides full access to Data Profiling.
Data Integration Data Previewer*	Supplemental role that allows users to preview source object data when they create a profile or view profile results. Assign this role with another role, such as the Designer role, to ensure that users can access Data Profiling.
Designer*	Provides full access to Data Profiling.
Monitor*	Allows users to view asset details in Data Profiling.
Operator*	Allows users to view asset details in Data Profiling.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

Data Quality roles

To provide access to Data Quality, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Data Quality:

Role	Description
Admin*	Provides full access to Data Quality.
Deployer*	Allows users to view asset details except dictionary data in Data Quality.
Designer*	Provides full access to Data Quality.
Monitor*	Allows users to view asset details except dictionary data in Data Quality.
Operator*	Allows users to view asset details except dictionary data in Data Quality.
Service Consumer*	Allows users to view asset details except dictionary data in Data Quality.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

Integration Hub roles

To provide access to Cloud Integration Hub, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Cloud Integration Hub:

Role	Description
Admin*	Provides full access to Cloud Integration Hub.
Designer*	Allows users to create, view, edit, delete and run Cloud Integration Hub assets. Doesn't provide privileges to perform provisioning, set system properties, or set permissions for Cloud Integration Hub assets.
Monitor*	Allows users to view asset details in Cloud Integration Hub.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

For more information about Cloud Integration Hub roles, see the Cloud Integration Hub help.

Metadata Command Center roles

To provide access to Metadata Command Center, assign users the appropriate roles. You can assign a system-defined role or custom roles for users.

The following table describes the system-defined roles that provide access to Metadata Command Center:

Role	Description
Admin*	Role for performing upgrades and updating catalog source configurations in Metadata Command Center. To perform tasks in Metadata Command Center, it is recommended to use the Governance Administrator role.
Governance Administrator**	Role for administering assets and operations in Data Governance and Catalog and Metadata Command Center. Allows users to perform the following tasks in Metadata Command Center: - Run and set permissions on catalog source configurations. - Manage metadata access control, asset groups, asset page customization, custom attributes, data classifications, autonomous enrichment settings, IDMC metadata settings, lineage settings, reference data, system settings, and workflow settings. - Monitor jobs. - View access control, asset groups, asset page customization, custom attributes, data classifications, autonomous enrichment settings, IDMC metadata settings, lineage settings, reference data, system settings, and workflow settings.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49. ** Also provides access to Data Access Management, Data Governance and Catalog, and Data Marketplace. For more information, see "Data Governance and Catalog roles" on page 57. To perform cataloging and governance tasks, the administrator must create and assign access policies to these user roles in Metadata Command Center. For more details, see *Administration* in the Metadata Command Center help.	

For more information about Metadata Command Center roles, see the Metadata Command Center help.

Monitor roles

To provide access to Monitor, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Monitor:

Role	Description
Admin*	Provides full access to Monitor.
Designer*	Provides full access to Monitor.
Monitor*	Allows users to view data integration jobs and job details in Monitor. Doesn't allow users to view export or import jobs.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

Operational Insights roles

To provide access to Operational Insights, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to Operational Insights:

Role	Description
Admin*	Provides full access to Operational Insights.
Operator*	Allows users to perform the following tasks in Operational Insights: - View cloud and domain infrastructure. - View Secure Agent alert settings.
* Provides access to multiple services. For more information, see "Cross-service roles" on page 49.	

Product 360 SaaS roles

To provide access to MDM - Product 360 SaaS, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to MDM - Product 360 SaaS:

Role	Description
Product 360 Manager	Role for managing records. Allows users to perform the following tasks: - Review and approve records. - Create, edit, and delete records without approval.
Product 360 Read-Only	Role for viewing records. Allows users to view records in Product 360 SaaS but not edit them.

For more information about Product 360 SaaS roles, see the MDM - Product 360 SaaS help.

Reference 360 roles

To provide access to MDM - Reference 360, assign users the appropriate roles. You can assign a system-defined role to Reference 360 users.

The following table describes the system-defined roles that provide access to MDM - Reference 360:

Role	Description
Reference 360 Administrator	Administrative role for Reference 360. Allows users to configure the Reference 360 environment.
Reference 360 Business Analyst	Role for analyzing assets. Allows users to view and analyze assets, but not propose changes to them.

Role	Description
Reference 360 Business Steward	Role for the subject matter experts for reference data. Allows users to perform the following tasks: - Create and manage code values in code lists and value mappings in crosswalks. - Approve changes proposed by other users. - Send their own changes for approval or directly publish their changes without approval.
Reference 360 Planner	Role for creating and managing hierarchies. Allows users to perform the following tasks: - Create hierarchy assets, define hierarchy models, and import hierarchy relationships. - Delete hierarchies that are no longer needed. - Assign the Planner stakeholder role to other users for a hierarchy.
Reference 360 Primary Owner	Role for creating and defining reference data structures. Allows users to perform the following tasks: - Create and define reference data structures, such as reference data sets and code lists. - Delete code lists. - Propose changes to code values in code lists. The changes must be approved by Business Stewards. - Assign users access to code lists and reference data sets using Stakeholder roles.
Reference 360 Stakeholder	Role for proposing changes to code values. Allows users to propose changes, but the proposed changes must be approved by Business Stewards.
Reference 360 User	Restricted access role. By default, users with this role can't access any assets. To allow users to access a specific asset, such as a code list or crosswalk, assign this role along with the stakeholder role for the asset.

For more information about Reference 360 roles, see the MDM - Reference 360 help.

Supplier 360 SaaS roles

To provide access to MDM - Supplier 360 SaaS, assign users the appropriate roles. You can assign a system-defined role or create custom roles for users.

The following table describes the system-defined roles that provide access to MDM - Supplier 360 SaaS:

Role	Description
Supplier 360 Analyst	Role for analyzing records. Allows users to create, read, edit, and delete records in Supplier 360 SaaS. When a Supplier 360 Analyst creates or edits a record, the changes trigger a review process that requires approval from a Supplier 360 manager.
Supplier 360 Commodity Manager	Role for managing commodity evaluation tasks. Has the originator and approver privileges. Allows users to perform the following tasks: - Claim and disclaim commodity evaluation tasks. - Act on the commodity evaluation tasks in the approval workflow. - Create, read, edit, and delete records.
Supplier 360 Contract Manager	Role for managing contract evaluation tasks. Has the originator and approver privileges. Allows users to perform the following tasks: - Claim and disclaim contract evaluation tasks. - Act on the contract evaluation tasks in the approval workflow. - Create, read, edit, and delete records.

Role	Description
Supplier 360 Credit Manager	Role for managing credit evaluation tasks. Has the originator and approver privileges. Allows users to perform the following tasks: - Claim and disclaim credit evaluation tasks. - Act on the credit evaluation tasks in the approval workflow. - Create, read, edit, and delete records.
Supplier 360 Data Steward	Role for managing records. Allows users to perform the following tasks: - Create, read, edit, and delete records with or without approval. - Run jobs. - Review and approve records. - Match, merge, and unmerge records.
Supplier 360 Read Only	Role for viewing records in Supplier 360 SaaS. Allows users to view records but not create or edit them.
Supplier 360 Risk Manager	Role for managing risk evaluation tasks. Has the originator and approver privileges. Allows users to perform the following tasks: - Claim and disclaim risk evaluation tasks. - Act on the risk evaluation tasks in the approval workflow. - Create, read, edit, and delete records.
Supplier 360 Task Admin	Role for administering evaluation tasks. Has the originator and approver privileges. Allows users to view all unclaimed evaluation tasks.

For more information about Supplier 360 SaaS roles, see the MDM - Supplier 360 SaaS help.

Custom roles

A custom role is a role that you create based on the needs of your organization. For example, you might want to create a custom administrative role that can configure roles, user groups, and access control, but can't create, edit, or run data integration tasks.

You can edit, rename, and delete custom roles after you create them.

You might want to edit custom roles when your organization gets a new license. Edit the roles to grant access to new asset types and features. IDMC doesn't grant additional privileges to custom roles when your organization gets a new license.

Note: Custom roles can't be assigned privileges to create, update, or delete roles. If you need to modify roles, log in to IDMC as a user with the system-defined Admin role.

Creating a custom role

Create a custom role on the **User Roles** page. When you create a role, you must configure the privileges that are associated with the role. You configure privileges separately for each service.

To create a custom role, you can create a new role or clone an existing role. A new role has no privileges until you configure them. A cloned role has the same privileges as the role that you clone, but you can change the privileges.

1. In Administrator, select **User Roles**.

2. Perform either of the following actions:
   - To create a new role, click **Add Role**.
   - To clone an existing role, in the row that contains the role that you want to clone, click **Actions** and select **Clone**. You can clone any role except for the Admin role.
3. Enter a role name and optional description.
4. In the **Services** field, select the service for which you want to configure privileges.

   For example, to configure privileges for Data Integration, select **Data Integration**. To configure administrative privileges, select **Administrator**.
5. To configure the asset privileges, select **Assets**, and enable or disable the appropriate privileges for each asset type.

   For example, to enable users with the role to create folders, enable **Create** next to **Folder**.
6. To configure the feature privileges, select **Features**, and enable or disable the appropriate privileges.

   For example, to prevent users with the role from importing assets, disable **Asset - import**.
7. Repeat steps 4 through 6 for each service.
8. Click **Save**.

After you create a role, you can assign it to a user or user group. To assign the role to a user or group, edit the user or group.

Renaming a role

Rename a role on the **User Roles** page. You can rename a custom role. You can't rename a system-defined role.

1. In Administrator, select **User Roles**.
2. In the row that contains the role that you want to rename, click **Actions** and select **Rename**.
3. Enter a new name for the role.
4. Click **Save**.

Deleting a role

Delete a role on the **User Roles** page. You can't delete a custom role if it is assigned to any user or user group. You can't delete a system-defined role.

1. In Administrator, select **User Roles**.
2. In the row that contains the role that you want to delete, click **Actions** and select **Delete**.

Role asset and feature privileges

Every role is associated with a set of asset or feature privileges. These privileges allow users to perform specific functions while working with assets and service features. Assign asset and feature privileges when you create a custom role.

Asset privileges provide CRUD, Run, and Set Permission privileges for different types of assets. For example, if you assign the Create privilege for mappings to a role, users with the role can create, view, and update mappings.

The following table describes the asset privileges:

Privilege	Description
Create	Create assets of the selected type. For Secure Agents, this privilege allows users to download and install the Secure Agent. Automatically grants the Read and Update privileges.
Read	Open assets of the selected type. For tasks, this privilege also allows users to use a connection or schedule in the task.
Update	Edit assets of the selected type. Automatically grants the Read privilege.
Delete	Delete assets of the selected type.
Run	Run assets of the selected type. For the Data Integration service, users can run mappings, tasks, or taskflows. Users can also monitor, stop, and restart instances of the mapping, task, or taskflow. For the Cloud Integration Hub service, users can run publications or subscriptions.
Set permission	Configure permissions for assets of the selected type. For example, if you grant this privilege for projects, users with the role can select a project and enable other users and groups to read, update, delete, or change permissions for the selected project. To configure this privilege, your organization must have the appropriate license.

Feature privileges control the ability to use certain features of a service. For example, the Data Quality "Data Preview - Dictionaries" privilege allows users to view the contents of a dictionary.

Assign asset and feature privileges on the role details page when you create a custom role. For more information about the role details page, see “Role details” on page 47.

You can't change the asset and feature privileges associated with a system-defined role.

Administrator asset and feature privileges

Use the Administrator asset and feature privileges to allow users access to specific functionality while working with Administrator. You can enable asset and feature privileges when you create a custom role.

Administrator asset privileges

The following table describes the Administrator asset privileges:

Asset privilege	Description
Connection	Allows users to create, read, update, delete, or set permissions on connections.
Advanced Configuration	Allows users to create, read, update, delete, or run advanced configurations.
Folder	Allows users to create, read, update, delete, or set permissions on project folders.
Group	Allows users to create, read, update, or delete user groups.
OAuth Client	Allows users to create, read, update, or delete OAuth 2.0 clients. For more information about creating and managing OAuth 2.0 clients, see the help for API Center.
Organization	Allows users to read and update organization information.
Privilege	Allows users to view the asset and feature privileges associated with each role.
Project	Allows users to create, read, update, delete, or set permissions on projects.
Role	Allows users to view users' roles and the **User Roles** page in Administrator.
Schedule	Allows users to create, read, update, delete, or set permissions on project schedules.
Scheduler Blackout	Allows users to create, read, update, or delete schedule blackout periods.
Scheduler Job	Allows users to run assets on a schedule, view schedule information for assets, update the schedule for an asset, or delete a schedule from an asset.
Secure Agent	Allows users to create, read, update, delete, or set permissions on Secure Agents.
Secure Agent Group	Allows users to create, read, update, delete, or set permissions on Secure Agent groups.
User	Allows users to create, read, update, and delete user accounts.

Administrator feature privileges

The following table describes the Administrator feature privileges:

Feature privilege	Description
AdditionalOrg creation privilege	Allows users to create additional production and sandbox organizations when the AdditionalOrg view privilege is also granted.
AdditionalOrg view privilege	Allows users to view additional production and sandbox organizations from the production organization. This privilege is required to create additional production and sandbox organizations.
Asset - check in/out	Allows users to check in and check out assets from the source control repository.
Asset - export	Allows users to export assets from the organization.
Asset - import	Allows users to import assets into the organization.
Asset - pull version	Allows users to pull assets from the source control repository.
Asset - Source Control Logs	Allows users to view the source control logs.
Audit Log - view	Allows users to view the audit log.
Bundle - create	Allows users to create bundles when the "Bundle - view" privilege is also granted.
Bundle - delete	Allows users to delete bundles when the "Bundle - view" privilege is also granted.
Bundle - install	Allows users to install bundles so that they are available to your organization when the "Bundle - view" privilege is also granted.
Bundle - publish	Allows users to publish bundles when the "Bundle - view" privilege is also granted.
Bundle - update	Allows users to update bundles when the "Bundle - view" privilege is also granted.
Bundle - view	Allows users to view bundles. This privilege is required to create, delete, install, publish, and update bundles.
Configure Custom Repository Source Control	Allows users to configure a project-specific repository URL and branch name for project-level source control repositories when the Configure Source Control privilege is also granted.
Configure Source Control	Allows users to configure source control to enable version management for projects, folders, and assets.
Connectors - view	Allows users to view the connectors available to their organization and to view the **Add-On Connectors** page in Administrator.
Force Undo Checkout	Allows users to undo the checkout of an object that has been checked out by another user.
Elastic runtime environment - get images	Allows users to run the API that gets information about elastic runtime environment images from Informatica's artifactory. Users must have this privilege to run the cluster installer script that deploys an elastic runtime environment.

Feature privilege	Description
Elastic runtime environment - manage tokens	Allows users to perform operations on the tokens that are required to pull elastic runtime environment images from Informatica's artifactory. Users must have this privilege to run the cluster installer script that deploys an elastic runtime environment.
KMS View managed Key	Allows users to view the **Customer Managed Keys** area on the **Security** tab of the **Settings** page.
Manage Billing	Allows users of Data Integration-PayGo to manage their payment information. For more information about Data Integration-Free and PayGo, see "Introducing Informatica Cloud Data Integration-Free and PayGo."
Manage key rotation settings	Allows customers to manage key rotation for their organization through the platform REST API version 3 key resource. For more information about the v3 key resource, see *REST API Reference*.
Manage user notifications	Allows administrators to configure notification settings for all users in the organization.
Metering.admin	Allows users to manage metering tasks.
ratecard.view	Allows users to view the current rate card for their organization on the Metering page.
SMS Manage Connection	Allows users to enable and disable the use of a secrets manager for the organization and to configure and update the secrets manager settings.
SMS View Connection	Allows users to view the **Secret Vault** area on the **Security** tab of the **Settings** page.
Suborg - create	Allows users to create sub-organizations when the "Suborgs - view" privilege is also granted.
Suborg - delete	Allows users to delete sub-organizations when the "Suborgs - view" privilege is also granted.
Suborg - update	Allows users to edit sub-organization settings when the "Suborgs - view" privilege is also granted.
Suborgs - link	Allows users to link sub-organizations when the "Suborgs - view" privilege is also granted.
Suborgs - manage licenses	Allows users to manage licenses for the organization's sub-organizations when the "Suborgs - view" privilege is also granted.
Suborgs - unlink	Allows users to unlink sub-organizations from the parent organization when the "Suborgs - view" privilege is also granted.
Suborgs - view	Allows users to view sub-organizations and switch into sub-organizations from the parent organization. This privilege is required to create, delete, update, link, manage the licenses of, and unlink sub-organizations.
Upgrade SDI	Allows users to upgrade Data Integration-Free organizations to PayGo organizations. For more information about Data Integration-Free and PayGo, see "Introducing Informatica Cloud Data Integration-Free and PayGo."

AI Agent Engineering asset and feature privileges

Use the AI Agent Engineering asset and feature privileges to allow users access to specific functionality while working with AI Agent Engineering. You can enable asset and feature privileges when you create a custom role.

AI Agent Engineering asset privileges

The following table describes the AI Agent Engineering asset privileges:

Asset privilege	Description
Deployed MCP Server	Allows users to create, read, update, delete, run, or set permissions on deployed MCP server instances.
MCP Server	Allows users to create, read, update, delete, run, or set permissions on composite MCP servers.

AI Agent Engineering feature privileges

The following table describes the AI Agent Engineering feature privileges:

Feature privilege	Description
Execute Managed MCP Servers	Allows users to execute shared (Informatica-managed) MCP servers in AI Agent Engineering.
View AI Agent Engineering Designer	Allows users to access AI Agent Engineering.
View Managed MCP Servers	Allows users to view shared MCP servers in AI Agent Engineering.

Application Integration feature privileges

Assign Application Integration feature privileges when you create custom roles for Application Integration and Application Integration Console.

Important: You must assign the Folder and Project asset privileges to the user's role. To do this, select the Data Integration service, and then select the CRUD privileges for the folder and project assets.

The following table describes the Application Integration feature privileges:

Feature privilege	Description
Administration	Gives users complete design-time and run-time administrative access to the Application Integration and Application Integration Console. Allows users to perform the following tasks: - View, create, update, and delete all Application Integration assets. - Manage and invoke services. - Stop running processes. - View instances and logs for deployed process. - Deploy Process Developer BPR files to the Application Integration Console. - Manage deployed catalogs. - View WSDL files deployed across multiple systems. - View Process Server metrics. - Activate and deactivate process APIs. - View, start, and stop event sources in listener-based connections. **Note:** This privilege doesn't give users organization administration privileges. For example, a user with the only the Application Integration Administration privilege can't create sub-organizations.
Console Administration	Gives users near-complete access to the Application Integration Console. Allows users to perform the following tasks: - View instances for deployed process. - Stop running processes. - View deployed Process Developer BPRs and catalogs. - View WSDL files deployed across multiple systems. - View Process Server metrics. - Activate and deactivate process APIs. - View, start, and stop event sources in listener-based connections. This privilege doesn't allow users to deploy BPR files.
Data Viewer	Gives users access to detailed logs in the Application Integration Console. For example, you might assign this privilege to a someone who needs to see all logs across the organization. You would not normally assign this role to a developer. **Note:** The process logging level must be set to verbose to get detailed logs.
Development	Gives users the ability to debug processes. Allows users to perform the following tasks: - View, create, update, and delete all Application Integration assets. - Invoke services. - View the **Detailed Process Instance** page on the Application Integration Console. - Manage processes instances. - Activate and deactivate process APIs. - View, start, and stop event sources in listener-based connections.
Monitoring	Gives users the ability to view all parts of the Application Integration Console except for detailed logs. Allows users to perform the following tasks: - Activate and deactivate process APIs. - View, start, and stop event sources in listener-based connections.
Publish Application Integration Assets	Gives users the ability to publish Application Integration processes, guides, connections, and service connectors.

Feature privilege	Description
View Application Integration Console	Gives users access to the Application Integration Console. You must assign this privilege to any role that has privileges that include working on the Application Integration Console. For example, assign this privilege with the Development privilege.
View Application Integration Designer	Gives users access to Application Integration. You must assign this privilege to any role that has privileges that include working on the Application Integration Console. For example, assign this privilege with the Publish Application Integration Assets privilege.

Data Governance and Catalog feature privileges

Use the Data Governance and Catalog feature privileges to allow users access to specific functionality while working with Data Governance and Catalog. You can enable feature privileges when you create a custom role.

The following table describes the Data Governance and Catalog feature privileges:

Feature	Description
Access Data Governance and Catalog application	Enable this feature to grant access to Data Governance and Catalog. If disabled, you can't access Data Governance and Catalog to perform any governance tasks.
Export	Allows users the ability to export assets from Data Governance and Catalog.
Export Usage Metrics	This privilege is not in use.
Force Delete	Allows users the following privileges: - Delete assets with incoming relationships. - Delete assets with all the child assets in the hierarchy through bulk import.
Import	Allows users the ability to download predefined templates and import business assets into Data Governance and Catalog. To enable this privilege, also grant users the following asset privileges to import assets: - Business assets. Create and update privilege - Technical assets. Update privilege
Manage Tickets	Allows users the following privileges: - Resolve or cancel tickets without being a stakeholder of the asset. - Receive notifications for manual tickets without being a stakeholder of the asset.
Manage Workflow Tasks	Allows users the following privileges: - View all the tasks on the **Tasks Inbox** page in Data Governance and Catalog. - Manage tasks in Data Governance and Catalog. - Assign and reassign tasks in Data Governance and Catalog.

Feature	Description
Participate in Change Approvals	Allows users the following privileges: - Participate in workflow approvals in Data Governance and Catalog. The role for which you grant this privilege appears in the **Role** in Metadata Command Center when a user creates or modifies a workflow task. - Add stakeholders to assets in Data Governance and Catalog. - Configure workflows in Metadata Command Center.
Preview Data	Allows user to view the latest preview of failed rows for data quality rule occurrences in Data Governance and Catalog. **Important:** Effective in the July 2026 release, the Preview Data feature privilege is deprecated. Deprecated functionality is supported, but Informatica intends to drop support in a future release.
View Reference Data	Allows users to view reference data on the **Reference Data** tab for business terms, metrics, manual data elements, and data elements.
View Restricted Metrics	Allow users to view restricted metric data on usage analytics dashboards.
View Usage Metrics	Allows users to view metric data, to edit widgets on usage analytics dashboards, and to clone and share usage analytics dashboards.

Data Ingestion and Replication minimum asset and feature privileges

Assign Data Ingestion and Replication Database asset and feature privileges when you create custom roles for Data Ingestion and Replication Database.

To create, view, or edit database ingestion and replication tasks, assign a user role that includes the minimum required privileges. You can use a system-defined role such as Admin or Designer that includes these privileges, or you can define a custom role that includes them.

Minimum asset privileges

The following table describes the minimum required asset privileges:

Service	Asset type	Asset privileges
Data Ingestion and Replication	Database Ingestion Task	Create, Read, Update
Administrator	Connection	Read
Administrator	Secure Agent Group	Read

Minimum feature privileges

The following table describes the minimum required feature privileges:

Service	Feature privileges
Administrator	Connectors - view

Data Integration asset and feature privileges

Use the Data Integration asset and feature privileges to allow users access to specific functionality while working with Data Integration. You can enable asset and feature privileges when you create a custom role.

Data Integration asset privileges

The following table describes the Data Integration asset privileges:

Asset privilege	Description
API Collection	Allows users to create, read, update, delete, run, and set permissions on API collections.
Azure Data Sync Task	This privilege is not used.
Business Service Definition	Allows users to create, read, update, delete, and set permissions on business services.
Data Loader Task	Allows users to create, read, update, delete, run, and set permissions on data loader tasks.
Data Masking Task	Allows users to create, read, update, delete, run, and set permissions on data masking tasks.
Data Transfer Task	Allows users to create, read, update, delete, run, and set permissions on data transfer tasks.
Dynamic Mapping Task	Allows users to create, read, update, delete, run, and set permissions on dynamic mapping tasks.
File Listener	Allows users to create, read, update, delete, run, and set permissions on file listeners.
Fixed-Width File Format	Allows users to create, read, update, delete, run, and set permissions on fixed-width file formats.
Hierarchical Schema	Allows users to create, read, update, delete, run, and set permissions on hierarchical schemas.
Industry Data Services	Allows users to create, read, update, delete, run, and set permissions on data services from the data services repository. Also allows users to use them in assets such as industry data service customizers, hierarchical mappers, and the Data Services transformation in a mapping.
Intelligent Structure Task	Allows users to create, read, update, delete, run, and set permissions on intelligent structure models.

Asset privilege	Description
Linear Taskflow	Allows users to create, read, update, delete, run, and set permissions on linear taskflows.
Mapping	Allows users to create, read, update, delete, run, and set permissions on mappings. To run a mapping, users must have Run permission on both mappings and mapping tasks.
Mapping Task	Allows users to create, read, update, delete, run, and set permissions on mapping tasks. To run a mapping task, users must have Run permission on both mappings and mapping tasks.
Mapplet	Allows users to create, read, update, delete, run, and set permissions on mapplets.
PowerCenter task	Allows users to create, read, update, delete, run, and set permissions on PowerCenter tasks.
Replication Task	Allows users to create, read, update, delete, run, and set permissions on replication tasks.
Saved Query	Allows users to create, read, update, delete, run, and set permissions on saved queries.
Sequence Generator	Allows users to create, read, update, delete, and set permissions on shared sequences.
Swagger	Allows users to create, read, update, and delete Swagger files.
Synchronization Task	Allows users to create, read, update, delete, run, and set permissions on synchronization tasks.
Taskflow	Allows users to create, read, update, delete, run, and set permissions on taskflows.
User-Defined Function	Allows users to create, read, update, delete, run, and set permissions on user-defined functions.

Data Integration feature privileges

The following table describes the Data Integration feature privileges:

Feature privilege	Description
Access CDI error logs	Allows users to preview error rows files from the **All Jobs**, **Running Jobs**, and **My Jobs** pages, and from the job details.
Access Data Integration Copilot	Allows users to use CLAIRE Copilot for Data Integration and Data Ingestion and Replication. The tasks that the user can perform in CLAIRE Copilot depend on the user's asset privileges. For example, to create a mapping in CLAIRE Copilot, the user must have a privilege to create mappings in Data Integration. To create a database ingestion and replication task in CLAIRE Copilot, the user must have a privilege to create database ingestion and replication tasks in Data Ingestion and Replication.
Data - preview	Allows users to preview data in mappings and when they run SQL ELT optimization data preview jobs. Also allows users to select sample files and preview data for fixed-width file formats.

Feature privilege	Description
Disable Pre and Post Processing Commands	Prevents users from editing pre- and post-processing commands. Pre-existing commands still run, but can't be edited.
EDC for IICS Discovery	Allows users to use data catalog discovery to find objects from Enterprise Data Catalog and use them in mappings and some types of tasks. **Note:** Before users can perform data catalog discovery, you must configure the Enterprise Data Catalog integration properties on the **Organization** page.

Data Marketplace feature privileges

View the features privileges in IDMC Administrator that are available to a user role for the Data Marketplace service.

The following table describes the Data Marketplace feature privileges:

Data Profiling feature privileges

Use the Data Profiling feature privileges to allow users access to specific functionality while working with Data Profilingassets. You can enable asset and feature privileges when you create a custom role.

The following table describes the Data Profiling feature privileges:

Privilege	Description
Data Profiling	Create, read, update, delete, run, and set permissions for a data profiling task.
Data Profiling - Compare Columns	Compare columns in a profile run.
Data Profiling - Compare Data Profiling Runs	Compare multiple profile runs.
Data Profiling - Data Profiling Results - View*	- View the profiling results for a data profiling task for any user including the user who created the data profiling task. - View the valid and invalid rows in the Data Governance and Catalog scorecard using the **Preview of Successful Rows** and **Preview of Unsuccessful Rows**.
Data Profiling - Drill down*	View and select the drill-down option when you create a data profiling task.
Data Profiling - Export Data Profiling Results	Export the profiling results to a Microsoft Excel file.
Data Profiling - Manage Rules	Add or delete rules for a data profiling task.
Data Profiling - Query - Create	Create a query.
Data Profiling - Query - Submit	Run a query and view query results.
Data Integration - Data Preview	View source object data in the **Data Preview** area.

Privilege	Description
Data Profiling Sensitive Data - view	Hide sensitive information for a particular user role. When the **Sensitive Data - view** privilege is configured, you cannot view the minimum value, maximum value, and most frequent values information in the **compare column** tab.
Data Profiling Disable Data Value Storage	Does not store minimum, maximum, and most frequent values in the profiling warehouse. When you configure the **Disable Data Value Storage** feature, the sensitive information is not stored in the profile results and the source system. The values are not stored even if you have permissions to view the sensitive data, or if you configure a profiling task with the **Maximum Number of Value Frequency Pairs** option. By default, this feature is disabled. When the feature is disabled, the values are stored as expected.
* To perform drill down, and to view the **Preview of Successful Rows** and **Preview of Unsuccessful Rows** in a Data Governance and Catalog scorecard, you need the following privileges: - Data Profiling - Query - Create - Data Profiling - Query - Submit - Data Profiling - Data Profiling Results - View - Data Profiling Sensitive Data - view	

The following table describes how the **Disable Data Value Storage** and **Sensitive Data- view** features function when you configure for different user roles:

Features	Custom role	Administrator or Designer	Result
Disable Data Value Storage	Inactive	Active	Sensitive information is not stored.
	Active	Inactive	Sensitive information is not stored.
Sensitive Data- view	Inactive	Active	Sensitive information is displayed.
	Active	Inactive	Sensitive information is displayed.

Note: When you activate the **Disable Data Value Storage** feature, Data Profiling or the source system does not store the sensitive information.

Data Quality feature privileges

Use Data Quality feature privileges to grant users access to the preview functionality in data quality assets. You can enable feature privileges when you create a custom role.

The Data Quality feature privileges are enabled by default for the Admin and Designer roles.

The following table describes the Data Quality feature privileges:

Feature privilege	Description
Data Preview - Dictionaries	Allows users to view the contents of a dictionary in the following cases: - The user opens the dictionary from the **Explore** page. - The user selects the dictionary in a Data Quality asset.
Data Preview - Test Panel	Allows users to view data in the Test panel in a Data Quality asset. **Note:** To run a test in a Data Quality asset, your role must also have the **Run** privilege for mappings in Data Integration.
Exceptions Data - Delete	Enables users to delete the exception data associated with an exception management job from the exception data store. Find the exception management job on the **My Jobs** page in Data Quality, Data Profiling, or Data Integration.
Exceptions Data - View	Enables users to download the exception records that an exception management job identifies. Find the exception management job on the **My Jobs** page in Data Quality, Data Profiling, or Data Integration.

Note: The Data Preview - Dictionaries feature privilege and the Read privilege for dictionary assets work independently of each other. The Read privilege allows you to open the dictionary from the **Explore** page. The Data Preview - Dictionaries privilege allows you to view the dictionary data. If you open a dictionary without the Data Preview - Dictionaries privilege, Data Quality displays a message to notify you that you do not have sufficient permissions to view the data.

Domain Management Service asset and feature privileges

Use the Domain Management Service asset and feature privileges to allow users access to specific functionality while working with CDI-PC. You can enable asset and feature privileges when you create a custom role.

Important: You must assign Read access on the Secure Agent and Secure Agent Group assets to the user's role. To do this, select the Administrator service and assign Read privilege for the assets.

Domain Registration asset privileges

The following table describes the Domain Registration asset privileges:

Asset privilege	Description
Read	Allows users to view registered domains and domain details.
Create	Allows users to perform the following tasks: - View registered domains and domain details. - Register a domain. - Deregister a domain. - Retry registration. - Edit domain details. - Reconcile a domain. Create includes the Read and Update privileges.

Asset privilege	Description
Update	Allows users to perform the following tasks: - View registered domains and domain details. - Deregister a domain. - Retry registration. - Edit domain details. - Reconcile a domain. Update includes the Read privilege.
Delete	Allows users to perform the following tasks: - View registered domains and domain details. - Delete a deregistered domain. Delete includes the Read privilege.

Domain Registration feature privileges

The following table describes the Domain Registration feature privileges:

Domain Registration feature privilege	Description
Domain Update	Allows users to update a domain.

Human Task asset and feature privileges

Use the Human Task asset and feature privileges to allow users access to specific functionality while working with human task assets. You can enable asset and feature privileges when you create a custom role.

Human Task asset privileges

The following table describes the Human Task asset privileges:

Asset privilege	Description
Human Task Assets	Allows users to perform the following actions: - Create, read, update, or delete human task assets. - Run processes that contain Human Task steps, which generate human tasks. - Assign permissions to other user roles so that they can access human task assets.

Human Task feature privileges

The following table describes the Human Task feature privileges:

Feature privilege	Description
Development	Allows users to create and edit human task assets and use Human Task steps in Application Integration processes.
View Human Task Application	Allows users to view and access the Human Task service.
View Tasks	Allows users to access the Human Task Inbox in the Human Task service.

Metadata Command Center feature privileges

Use Metadata Command Center feature privileges to allow users access to specific functionality while working with Metadata Command Center. You can enable feature privileges when you create a custom role.

The following table describes the Metadata Command Center feature privileges:

Feature	Description
Access Metadata Command Center application	Grants access to Metadata Command Center. If disabled, users can't access Metadata Command Center.
Manage Autonomous Enrichments	Allows users to enable and manage global Autonmous Enrichment settings.
View Autonomous Enrichments	Allows users to view global Autonomous Enrichment settings.
Manage Custom Attributes	Allows users to manage asset relationships, predefined attributes, and custom attributes for asset types that appear in Data Governance and Catalog.
View Custom Attributes	Allows users to view attributes for asset types in Data Governance and Catalog.
Manage Data Classifications	Allows users to create and manage data classification inclusion rules.
View Data Classifications	Allows users to view data classifications in Data Governance and Catalog after you enable the capability and run the catalog source job in Metadata Command Center.
Manage Lookup Tables	Allows users to import and publish lookup tables that you can use in data classification.
View Lookup Tables	Allows users to view lookup tables in Metadata Command Center.
Monitor Jobs	Allows users to monitor jobs.
Manage Lineage Settings	Allows users to perform the following tasks: - Assign or unassign connections to one or more catalog sources. - Link catalog sources to generate lineage.
View Lineage Settings	Allow users to view data lineage from the Lineage tab.
Manage Access Control	Allows users to create and manage stakeholder roles and access policies. Also allows users to share saved searches, dashboards, and set default dashboards for other users.
View Access Control	Allows users to view access policies.
Manage Asset Groups	Allows users to create, update, or delete asset groups.
View Asset Groups	Allows users to view asset groups.
Manage Workflows	Allows users to create or modify workflows.
View Workflows	Allows users to view workflows.
Workflow Designer	Allows users to design new workflows.
Manage System Settings	Allows users to modify system settings.

Feature	Description
View System Settings	Allow user to view the **Reference IDs** tab.
Manage Asset page customization	Allows users to create, update and delete the layout of pages and preview panes of assets. Also allows users to assign default layouts to other users based on their roles, user groups, or to all users in the organization.
View Asset page customization	Allows users to view the layout of pages.
Manage IDMC Metadata Settings	Allows users to synchronize metadata from Data Integration tasks and Application Integration objects with the catalog.
View IDMC Metadata Settings	Allow users to view IDMC metadata.
Manage Upgrade	Allows users to initiate upgrades to the latest version of Data Governance and Catalog.
Manage Usage Analytics	Allows users to enable and disable usage analytics.
Super Admin	Allows users access to unique administrator capabilities beyond the Governance Administrator role.

Monitor feature privileges

Use the Monitor feature privileges to allow users access to specific functionality while working with Monitor. You can enable feature privileges when you create a custom role.

The following table describes the Monitor feature privileges:

Feature privilege	Description
Job Results - view	Allows users to view job results on the **All Jobs**, **Running Jobs**, and **My Jobs** pages.
Logs - View and Download	Allows users to view and download job log files.

Operational Insights feature privilges

Use the Operational Insights feature privileges to allow users access to specific functionality while working with Operational Insights. You can enable feature privileges when you create a custom role.

The following table describes the Operational Insights feature privileges:

Feature	Description
Anomaly alert settings - modify	Allows users to create and modify CLAIRE alerts for PowerCenter projects.
Data Integration Job Alerts	Allows users to view the **Data Integration Alerts** page and to create and modify alerts for Data Integration jobs.
Domain infrastructure - modify	Allows users to register, edit, and unregister domains and view the **Infrastructure Alerts** page.

Feature	Description
Domain infrastructure alert settings - modify	Allows users to modify domain alerts on the **Infrastructure Alerts** page.
Domain job analytics - view	Allows users to view the **Domains** page for PowerCenter, Data Engineering, and Data Quality.
Domain projects - modify	Allows users to create and edit PowerCenter projects. Also allows users to view projects for Data Engineering Integration and Data Quality.
Infrastructure - modify	Allows users to edit the domain map.
Infrastructure - view	Provides users with access to Operational Insights and allows users to view the **Home** page. Also allows users to view the **Secure Agents and Groups** tab on the **All Infrastructure** page. Allows users to view the **Infrastructure** and **PowerCenter** alerts pages.
Job alert settings - modify	Allows users to create and modify alerts for PowerCenter jobs.
Mass Ingestion Job Alerts	Allows users to view, create, and modify alerts for Data Ingestion and Replication jobs.
Operational Insights - view	Allows users to view the following panels and pages: - Rows Loaded panel on the **Home** page. - Domains tab on the **All Infrastructure** page. - **PowerCenter**, **Data Engineering Integration**, and **Data Quality** pages. - Recommendations on the **PowerCenter** page. - Alert Settings on the **PowerCenter Alerts** page. - **Alerts Received** page. Also allows users to view their assigned projects and view CLAIRE alerts for their projects.
Secure Agent runtime alert settings - modify	Allows users to edit Secure Agent alerts on the **Infrastructure Alerts** page.

Workbench Service asset and feature privileges

Use the Workbench Service asset and feature privileges to allow users access to specific functionality while working with Cloud Data Integration for PowerCenter (CDI-PC). You can enable asset and feature privileges when you create a custom role.

Workbench Service asset privileges

The following table describes the Workbench Service asset privileges:

Asset privilege	Description
Assessment Repoint Configuration	Allows users to create, read, update, delete, run, and set permissions on asset repoint configuration tasks.
Assessment Task	Allows users to create, read, update, delete, run, and set permissions on PowerCenter repository assessment tasks.

Asset privilege	Description
Bulk Update Task	Allows users to create, read, update, delete, and set permissions on bulk asset metadata update tasks.
Connection Map Configuration	Allows users to create, read, update, delete, run, and set permissions on connection map configuration tasks.
Conversion Property Configuration	Allows users to create, read, update, delete, run, and set permissions on conversion property configuration tasks.
Conversion Task	Allows users to create, read, update, delete, run, and set permissions on asset conversion tasks.
Parameter File Conversion Task	Allows users to create, read, update, delete, run, and set permissions on parameter file conversion tasks.

Workbench Service feature privileges

The following table describes the Workbench Service feature privileges:

Feature privilege	Description
Download Artifacts	Allows users to download the files generated from an assessment, conversion, or a bulk update job.
Repository Assessment	Allows users to assess a repository. **Note:** To run an assessment job, ensure that the Admin role is assigned to the user.
View Assessment Results	Allows users to access the assessment results.
View Configurations	Allows users to view the configurations.
View Jobs	Allows users to view the details of assessment, conversion, parameter file conversion, and bulk update jobs.
View Tasks	Allows users to view the details of the assessment, conversion, parameter file conversion, and bulk update tasks.

CHAPTER 7

Notifications

You receive notifications in IDMC for certain events, including job status updates, license expiration, and workflow progress. You can manage how you receive notifications.

The Notifications icon on the toolbar displays the number of unread notifications. You can click the icon to view the latest unread notifications in the notifications tray. In some services, you can filter the tray to display only notifications from the current service.

You can also view and manage notifications on the **Notifications** page. To access the **Notifications** page, select **View All Unread** from the Actions menu in the notifications tray. On the **Notifications** page, you can filter notifications by service, category, subcategory, status, and date received.

By default, all users receive notifications by email as well. Administrators can edit the default setting for their organization to enable or disable email notifications. Each user can personalize their email notification settings to choose which notifications they want to receive by email.

Configuring email notifications for your organization

You can configure whether users in your organization receive email notifications on the **Settings** page in Administrator.


By default, users receive all email notifications. You can switch your organization default setting to disable email notifications. To configure the organization default, set the property **Enable Email Notifications for Organization** on the **Notifications** tab of the **Settings** page.

The organization default applies to new users and users who haven't personalized their settings. If a user personalizes their settings, their personal settings take precedence.

If needed, you can reset all users to the organization default to override any personal settings.

Users receive an email notification when you make a change that impacts their settings. For example, when you change the organization default, users who haven't personalized their settings are notified about the change. When you reset all users to the default setting, users who previously personalized their settings are notified about the reset.

The following image shows the **Notifications** tab with email notifications enabled for the organization:




Configuring email notifications for yourself

You can configure which notifications you receive by email in your user settings.

To access user settings, click the **User** icon on the toolbar and then select **Settings**. Navigate to the **Notifications** section.

The **Notifications** section lists categories of events that trigger notifications, such as changes in an asset's stakeholders and new comments on an asset. By default, you receive an email notification each time an event occurs. You can disable all email notifications, disable event notifications by category and subcategory, and for some categories you can choose to receive an email summarizing events at an interval that you specify.

The following image shows the **Notifications** section:



Note: Depending on which service you are in, the user settings page might appear different and show different names for the sections.

Notification categories and subcategories

Each event that triggers a notification belongs to a category, such as Administration, and subcategory, such as Stakeholder Changes. You can personalize your email notification settings for each category and subcategory.

Administration

The following table describes the subcategory of the **Administration** category:

Subcategory	Description
Stakeholder Changes	Changes to the stakeholders of an asset, including removal of stakeholders and transfer of ownership

Asset Changes

The following table describes the subcategories of the **Asset Changes** category:

Subcategory	Description
Asset Changes	Changes to an asset or relationship **Note:** This subcategory is not in use in Metadata Command Center and Data Governance and Catalog.
Technical Asset Changes	Changes that are made directly in the source system or to a catalog source. The changes include updates to the attributes of the asset, modifications to the asset structure, and discovery of new child assets. **Note:** You can receive notifications if you are the stakeholder of the catalog source from which the asset was imported. If a catalog source is assigned more than one stakeholder, all the stakeholders receive the notifications.

Collaboration

The following table describes the subcategories of the **Collaboration** category:

Subcategory	Description
Certifications	Changes in the certification status of an asset
Comments	New comments on an asset
Mentions	Someone tagged you in a conversation
Ratings	Changes in the rating of an asset
Shares	Someone shared a saved search with you

Critical Notifications

The following table describes the subcategories of the **Critical Notifications** category:

Subcategory	Description
Critical Administrative Alerts	Updates related to organizations, networking requirements, the Secure Agent, or other operational changes that administrators should be aware of to maintain service availability
Critical Event Alerts	Upcoming releases and service maintenance
Proactive Notifications	Feature or release impact that requires user action

Note: When you disable notifications in the **Critical Notifications** category, it might take up to 10 business days for the change to take effect. Administrators can't disable these notifications for themselves because they might need to take action on the information.

Data Quality

The following table describes the subcategories of the **Data Quality** category:

Subcategory	Description
Data Observability	Events generated by data observability for anomalies in source data
Data Quality	Changes in the data quality score for a data quality rule occurrence, including failures and anomalies

Tickets and Workflow

The following table describes the subcategories of the **Tickets and Workflow** category:

Subcategory	Description
Access	Changes in your access to data
Order	Events generated for an order
Requests	Events generated for a data collection request in Data Marketplace
Tasks	Reminders about tasks you need to complete
Tickets	Events generated for a ticket
Workflow Progress	Events generated for a workflow

User Jobs

The following table describes the subcategories of the **User Jobs** category:

Subcategory	Description
Export Jobs	Events generated for an export job
Import Jobs	Events generated for an import job

CHAPTER 8

User configuration examples

The following examples illustrate ways in which you can configure users, user groups, and roles to control access to IDMC according to your business needs.

You want your development team to create tasks and taskflows in Data Integration. The development team needs to view sample data in development, but you want to restrict access to production data.

1. Create a Developer role for the development team. Configure the role with all privileges for tasks and related assets, but only the Read privilege for connections.
2. Create a Development Team user group and add all members of the development team to the group.
3. Assign the Developer role to the Development Team group.
4. If possible, create development connections to sample data. If you have both development and production connections, configure the production connections so that the Development Team group does not have read permission for these connections. This prevents users in the Development Team group from using production connections in tasks.
5. After testing is complete and tasks are ready to move into production, have an administrator or other qualified user configure the tasks to use production connections.
6. Edit the Developer role and remove the privilege to run tasks. If development is complete for a task type, you can also remove the privileges to read and update the tasks. By removing the read privilege, you prevent users with the Developer role from accessing information about production tasks.

You have a reporting team that needs to run tasks in Data Integration, but does not have the technical knowledge to configure tasks safely.

1. Create a Reporter role for the reporting team. Configure the role with privileges to read and run tasks and taskflows, and privileges to read, create, and update schedules. Do not enable privileges to create, update, delete or set permissions on assets in the organization.
2. Create a Reporting Team user group and add all members of the reporting team to the group.
3. Assign the Reporter role to the Reporting Team group.

You want a security administrator who can assign roles and user groups and configure access control, but cannot create, edit, or run tasks.

1. Create a custom role called Security Administrator.
2. Edit the Security Administrator role and grant all privileges except the privileges to create, update, delete, and run tasks, connections, and schedules.
3. Assign the Security Administrator role to the security administrator.

You want to easily keep track of your organization administrators.

Create a user group called "Organization Administrators" and assign the Admin role to the group. Add all of your organization administrators to the group.

Your organization uses an OrderProcessing API to manage orders to a large supplier. This API consists of processes in Application Integration that include CreateOrder, ApproveOrder, and GetOrder. As an Admin, you want to restrict access to the ApproveOrder process to a few people.

1. Create a custom role called Approver. Configure the Run privilege for Application Integration Assets for the Approver role.
2. Create a user group called Order Approvers.
3. Assign the Approver role to the Order Approvers group.
4. Assign the Service Consumer role to the Order Approvers group. You must do this as the Service Consumer role can access and invoke processes.
5. Assign the users who need to be able to invoke the ApproveOrder process to the Order Approvers group.
6. In the ApproveOrder process, you must configure one of the following fields:
   - To assign access to a group of users, enter the Order Approvers group in the **Allowed Groups** field.
   - To assign access to a specific user, enter the user in the **Allowed Users** field. You can enter more than one user in the field.

Only members of the Order Approvers group or the users specified in the **Allowed Users** field will be able to invoke the ApproveOrder process.

You want an Application Integration developer to be able to perform all functions in the Application Integration Console except for viewing detailed process logs.

1. Create a role called Custom_Dev and configure the role with the following privileges:
   a. Select the Application Integration service, go to the **Assets** tab, and enable all CRUD privileges for **Application Integration Assets**.
   b. Go to the **Features** tab and add the Development, Console Administration, Publish Application Integration Assets, View Application Integration Console, and View Application Integration Designer privileges to the role.
   c. Select the Data Integration service, go to the **Assets** tab, and enable all CRUD privileges for the **Project** and **Folder** assets.
2. Assign the Custom_Dev role to the developer.

CHAPTER 9

Editing your user profile

Your user profile contains the details of your IDMC user account.

You can update the following information in your profile:

- First and last name
- Job title
- Email address
- Phone number
- Time zone (used in the job execution time stamps on the **All Jobs**, **Running Jobs**, **My Jobs**, **Import/Export Logs**, and **My Import/Export Logs** pages)
- Password
- Security question and answer

Note: If you use SAML to log in to IDMC and your organization administrator has enabled SAML group and role mapping on the **SAML Setup** page in Administrator, you can update the time zone attribute. Your enterprise directory updates the other attributes directly each time you log in to IDMC.

1. Click the **User** icon in the top right corner of the IDMC window and then select **Profile**.
2. On the **Profile** page, add or edit personal information such as your name, job title, phone number, and time zone.
3. To update your email address, click **Update Email**.

   After you enter your password to initiate the change, IDMC sends a verification email to your new email address. The email contains a link that's valid for 24 hours. When you click the link in the email, IDMC verifies the new address, and it appears in your profile. If the link expires, you can resend the verification email.
   If multi-factor authentication is enabled in your organizaion, IDMC sends a verification code to your original email address. You must enter the code in the dialog box on your **Profile** page to receive the verification link in your new email address.
4. Optionally, change your password or security question.
5. Click **Save**.

CHAPTER 10

Editing your user settings

In your user settings, you can configure personal preferences, including how you receive email notifications and your source control repository credentials.

To access user settings, click the **User** icon on the toolbar and then select **Settings**. The user settings page includes the following sections:

Notifications

Choose whether and how you receive email notifications.

For more information, see Chapter 7, “Notifications” on page 86.

Source Control Access

Configure repository credentials that allow you to work with source-controlled objects.

For more information, see *Organization Administration*.

Note: Depending on which service you are in, the user settings page might appear different and show different names for the sections.

CHAPTER 11

Inviting users to join your organization

If you have an appropriate role, you can invite users to join your organization when you configure a runtime environment or primary cloud data warehouse. Invite users to join your organization so they can help you set up a runtime environment or connect to your cloud data warehouse.

To invite users to join your organization, click **Invite a friend or colleague to help you**. To invite users, you must have the Admin role, or you must have the Designer role and a custom role that has the "read role" and "create user" Administrator asset privileges. You must assign the user you invite the Admin or Designer role.

If you don't see the **Invite a friend or colleague to help you** option or you want to assign the user a different role, you can add a user on the **Users** page in Administrator.

1. Click **Invite a friend or colleague to help you**.
2. Enter the first name, last name, email address, user name, and role for the person you want to invite.

   The user name must be unique within the organization. You cannot change the user name after you invite the user.
3. Click **OK**.

   The user you invite receives an email with a link to join your organization.

INDEX

A

assets
  assigning privileges 47
authentication
  organizations 13

C

Cloud Application Integration community
  URL 6
Cloud Developer community
  URL 6

D

Data Integration community
  URL 6

E

ecosystem single sign-on
  configuration properties 10
email addresses
  for notification 93

F

fingerprint authentication
  organizations 13

I

Informatica Global Customer Support
  contact information 7
Informatica Intelligent Data Management Cloud
  web site 6
IP address filtering
  configuring 12

J

JWT access tokens 30

M

maintenance outages 7
Microsoft Azure
  single sign-on configuration properties 10

O

OAuth
  using JWT access tokens for REST API calls 30
organizations
  authentication properties 12
  fingerprint authentication 13
  session idle timeout 12

P

passwords
  changing 93
  expiration 12
  minimum character mix 12
  minimum length 12
  reuse 12
privileges
  Administrator asset privileges 69
  Administrator feature privileges 69
  AI Agent Engineering asset privileges 72
  AI Agent Engineering feature privileges 72
  Application Integration feature privileges 72
  asset privileges for roles 68
  assigning to roles 47
  configuring for asset types 47
  Data Ingestion and Replication asset privileges 75
  Data Ingestion and Replication feature privileges 75
  Data Integration asset privileges 76
  Data Integration feature privileges 76
  Data Profiling feature privileges 78
  Data quality feature privileges 79
  Domain Registration asset privileges 80
  Domain Registration feature privileges 80
  feature privileges for roles 68
  Human Task asset privileges 81
  Human Task feature privileges 81
  Monitor feature privileges 83
  privilege descriptions 47
  Workbench Service asset privileges 84
  Workbench Service feature privileges 84
profiles
  editing 93

R

roles
  Admin role 49
  Administrator roles 51
  AI Agent Engineering roles 51
  API Center roles 52
  Application Integration Console roles 53
  Application Integration roles 53
  asset and feature privileges 68

roles *(continued)*
assigning privileges 47
assigning to user groups 43
assigning to users 34
B2B Gateway roles 54
B2B Partners Portal roles 54
Business 360 Console roles 55
CDI-PC roles 56
CLAIRE GPT roles 55
cloning 66
creating 66
cross-service 49
custom 46, 66
Customer 360 roles 56
Data Governance and Catalog roles 57
Data Integration Data Previewer role 49
Data Integration roles 58
Data Marketplace roles 59
Data Profiling roles 61
Data Quality roles 62
definition 8
deleting 67
Deployer role 49
Designer role 49
details 47
enabled and disabled 46
Integration Hub roles 62
Mass Ingestion roles 57
Metadata Command Center roles 63
Monitor role 49
Monitor roles 63
Operational Insights roles 64
Operator role 49
overview 46
Product 360 roles 64
Reference 360 roles 64
renaming 67
Service Consumer role 49
Supplier 360 roles 65
system-defined 46, 48
user configuration examples 91

S

SAML single sign-on
additional attribute mapping properties 28
configuration steps 25
configuring 22
creating users 17, 18
deleting users 17, 18
identity provider configuration properties 26
overview 15
registering a Secure Agent 16
requirements 16
restrictions 16
SAML attribute mapping properties 28
SAML group mapping properties 30
SAML role mapping properties 30
service provider settings 27
SSO configuration properties 25
switching from authentication and authorization 18
switching from authentication only 20
switching to authentication and authorization 20
switching to authentication only 18
user credentials storage 17, 18
user management with SAML authentication 17
user management with SAML authorization 18
SAML single sign-on *(continued)*
using JWT access tokens 30
using SCIM 2.0 20
with trusted IP ranges 16
schedules
reassigning a user's scheduled jobs 40
security questions
editing 93
services
assigning to user groups 43
session idle timeout
configuring 12
status
IDMC 7
sub-organizations
authentication properties 12
system status 7

T

time zones
changing user profile 93
trust site
description 7
trusted IP ranges
configuring 12
with SAML single sign-on 16

U

upgrade notifications 7
user groups
adding and removing members 43
assigning roles 43
assigning to users 34
configuration examples 91
creating 44
definition 8
deleting 45
details 43
editing 43
overview 42
renaming 43, 45
user profiles
editing 93
users
Application Integration anonymous user 33
assigning and unassigning services 38
assigning groups 34
assigning roles 34
assigning to user groups 43
authentication methods 9
configuration examples 91
creating 37
definition 8
deleting 40
details 34
disabling 39
downloading login date and time 33
editing 34
inviting 95
overview 32
reassigning scheduled jobs 40
resetting 39
setting the default service 38
unlocking 39

users *(continued)*
user statistics 33

W

web site 6