Informatica® Cloud Data Integration for PowerCenter

April 2026

PowerCenter Modernization

Informatica Cloud Data Integration for PowerCenter PowerCenter Modernization
April 2026

© Copyright Informatica LLC 2023, 2026

Publication Date: 2026-10-16

Table of Contents

Preface. . . . 5

Chapter 1: Getting started with asset modernization. . . . 6

Modernization process. . . . 7

Roles and privileges. . . . 8

- Asset permissions. . . . 8
- Asset permissions for conversion task. . . . 8
- Asset permissions for bulk update task. . . . 10
- Feature privileges. . . . 11

User interface of CDI-PC. . . . 12

- New Asset dialog box. . . . 14
- Repositories page. . . . 21
- Configurations page. . . . 32
- All Tasks page. . . . 33

Sizing recommendations. . . . 35

- Configuring memory for Secure Agent. . . . 36

Chapter 2: Repository Assessment. . . . 38

Before you begin. . . . 38

Creating a repoint configuration. . . . 39

Creating an assessment task. . . . 40

- Assessing a repository. . . . 40
- Importing assessment results. . . . 41

Re-assessing a repository. . . . 42

Accessing assessment results. . . . 44

Assessment output files. . . . 44

- Assessment report. . . . 48

Chapter 3: Asset Conversion. . . . 51

Before you begin. . . . 51

Configuring the XML Pre-processor file. . . . 52

SQL conversion. . . . 52

- Configuring the SQL conversion files. . . . 53

Creating a connection map configuration. . . . 53

- Advanced properties. . . . 54

Creating a conversion properties configuration. . . . 79

Creating a parameter file conversion task. . . . 81

Creating an asset conversion task. . . . 82

- Creating an asset conversion task for PowerCenter assets. . . . 83
- Creating an asset conversion task for Data Engineering Integration assets. . . . 84

Modifying a conversion task. . . . 85
Running a conversion task. . . . 86
Deleting a conversion task. . . . 86

Chapter 4: Bulk Metadata Update. . . . 88

Before you begin. . . . 90
Updating assets metadata. . . . 90
Exporting assets metadata. . . . 90
Updating assets metadata. . . . 91
Modifying a bulk update task. . . . 93
Running a bulk update task. . . . 93
Deleting a bulk update task. . . . 93

Chapter 5: Jobs. . . . 94

Monitoring an assessment job. . . . 94
Monitoring a conversion job. . . . 95
Monitoring a parameter file conversion job. . . . 95
Monitoring a bulk update job. . . . 96
Downloading job output files. . . . 96

Chapter 6: Configurations. . . . 98

Managing a configuration. . . . 98
Accessing configurations associated with domains and repositories. . . . 99

Index. . . . 100

Preface

Read the *PowerCenter Modernization* guide to learn how to use Cloud Data Integration for PowerCenter to modernize your PowerCenter, Data Engineering Integration, and Data Quality assets in a self-service manner. Learn how to assess PowerCenter and Model repositories, convert the assets to the cloud, bulk update the assets metadata, and monitor assessment, conversion, and bulk update jobs.

Note: Effective in the October 2026 release, CDI-PC supports the assessment of Data Quality assets but does not support conversion of the assets to Data Integration. However, CDI-PC will support conversion of Data Quality assets in the future.

CHAPTER 1

Getting started with asset modernization

Leverage the benefits of Informatica cloud by migrating your on-premises PowerCenter, Data Engineering Integration and Data Quality assets to the cloud.

Cloud Data Integration for PowerCenter (CDI-PC) offers a streamlined solution to modernize your legacy PowerCenter, Data Engineering Integration, and Data Quality assets by seamlessly migrating them to the cloud. The automated and self-service solution minimizes the risks associated with manual migration of your assets and accelerates time to value from the migration process. When you migrate the PowerCenter assets, CDI-PC converts the mappings, mapplets, sessions, and workflows to Data Integration mappings, mapplets, mapping tasks, and taskflows. When you migrate the Data Engineering Integration assets, CDI-PC converts the workflows and mappings to Data Integration workflows and mappings.

You can assess the conversion potential of the following types of Data Quality assets: applications, scorecards, profiles, mappings, mapplets, and workflows.

Migrating your PowerCenter, Data Engineering Integration, and Data Quality assets using CDI-PC offer the following benefits:

- **Cost savings**: CDI-PC automates more than 90% of the migration process, that can save substantial expenses associated with regular PowerCenter upgrades, administrative overhead, and other maintenance activities.
- **Flexibility and self-paced modernization**: You can tailor the migration process to your business priorities, budget, and resource availability. You have the flexibility to migrate your on-premises assets to the cloud at your own pace and in a phased manner.
- **Cloud advantages**: After you move your assets to the cloud, you gain access to the full range of benefits provided by the IDMC platform. The advantages include the utilization of various cloud-native services to meet your end-to-end data management requirements.


Note: Effective in the October 2026 release, CDI-PC supports the assessment of Data Quality assets but does not support conversion of the assets to Data Integration. However, CDI-PC will support conversion of Data Quality assets in the future.

Modernization process

There are multiple steps that you need to perform to modernize your PowerCenter, Data Engineering Integration, and Data Quality assets using CDI-PC.

Begin your modernization journey by registering your on-premise domains in IDMC to establish communication between on-premise domain and cloud. Based on the modernization journey, you can then create required configurations, assess repository, convert the assets to the cloud, and update the metadata of assets.

The following image shows the high-level steps you need to perform to modernize your PowerCenter, Data Engineering Integration, and Data Quality assets:



The modernization process involves the following steps:

Register domain

Before you start your modernization journey, you need to register your on-premise domains in IDMC. When you register a domain, you link the on-premise domain with the cloud and establish communication between them. After you register a domain, you can monitor the domain from the cloud, update the domain, and modernize the assets that are available in the repositories of the domain. For more information about registering a domain, see *Register a domain*.

Create repoint configuration

Create a repoint configuration where you can define various endpoints to which you want to repoint the assets. Use this configuration in assessment tasks to evaluate the feasibility of repointing the assets to another endpoint. For more information about creating a repoint configuration, see the *Creating a Repoint Configuration* topic. In addition to the repoint configuration, Informatica recommends that you copy the parameter files generated from your PowerCenter environment to a shared location.

Assess repository

After you register a domain, you can view a list of repositories within the domain. Assess the PowerCenter or Model repositories to evaluate the feasibility of converting PowerCenter, Data Engineering Integration, and Data Quality assets. Based on the feasibility, CDI-PC categorizes the assets into different categories. After you assess a repository, you can view the folders and workflows within the repository. For more information about assessment, see *Repository Assessment*.

Download assessment output files

The assessment job generates a report that contains a breakdown of the assets along with the list of flags responsible for manual or partial conversion of the assets. For more information about the output files, see *Assessment output files*.

Create connection map and conversion properties configurations

If you want to repoint your endpoint after migrating to the cloud, you need to create a Connection Map configuration to map PowerCenter and Data Engineering Integration connections with Data Integration connections. Additionally, you can create a Conversion Properties configuration to override the default conversion behavior.

Convert assets

Finally, from the repository that you assessed, select the assets that you want to convert and add them to a conversion task. Run the conversion task to convert the PowerCenter or Data Engineering Integration assets to the Data Integration assets. For more information about converting assets, see *Asset Conversion*.

Update asset metadata

After you convert and migrate the PowerCenter or Data Engineering Integration assets to the cloud equivalent assets, you can update the metadata of the assets using bulk update tasks. Add the project and folder location of the assets to the export metadata task and upload the updated metadata to the update metadata task. Run the tasks to export the metadata and update the assets with new metadata. For more information, see *Asset Bulk Update*.

Roles and privileges

Before you can use CDI-PC for modernization, the organization administrator must create the roles that are used for modernization, assign the right permissions and privileges to the roles, and then assign relevant users to the role.

Roles define the activities and tasks that users are allowed to do. When the organization administrator creates roles and sets the correct permissions and privileges, the roles define the boundaries within which the users can act. After the roles are defined, the organization administrator can assign specific users and user groups to the role.

For more information about creating roles and assigning users, see the *User Administration* help.

Asset permissions

The organization administrator can configure permission for assets that user roles can access in CDI-PC for modernization. Depending on the user roles and permissions, you can view or modify assets.

To configure asset permissions for user roles, go to IDMC Administrator service, open a role, select **Workbench Service**, and select one or more permissions on the **Assets** tab for the role.

Additionally, in the same role, select **Domain Management Service**, and assign at least read permission for the Domain Registration asset type. This permission is required to access the CDI-PC service.

For more information about assigning asset permissions to user roles, see the *User Administration* help.

Asset permissions for conversion task

To create or run conversion tasks, you need additional asset permissions from different IDMC services.

To configure asset permissions for user roles, go to IDMC Administrator service, open a role, select the required service, and select one or more permissions on the **Assets** tab for the role.

The following table lists the services along with the asset privileges that are required to create or update a conversion task:

Service	Asset	Privileges
Workbench Service	Assessment Task	Read
	Conversion Task	Create, Read, Update
Administrator	Folder	Create, Read
	Project	Create, Read
	Secure Agent	Read
	Secure Agent Group	Read

The following table lists the services along with the asset privileges that are required to run a conversion task:

Service	Asset	Privileges
Workbench Service	Conversion Task	Read, Run
	Connection Map Configuration	Read
	Conversion Property Configuration	Read
Administrator	Connection	Create, Read, Update
	Folder	Create, Read, Update
	Project	Create, Read, Update
	Secure Agent	Read
	Secure Agent Group	Read
Data Integration	File Listener	Create, Read, Update
	Fixed-Width File Format	Create, Read, Update
	Mapping	Create, Read, Update
	Mapping Task	Create, Read, Update
	Mapplet	Create, Read, Update
	PowerCenter Task	Create, Read, Update
	Sequence Generator	Create, Read, Update

Service	Asset	Privileges
	Taskflow	Create, Read, Update
	User-Defined Function	Create, Read, Update

The following table lists the services along with the asset privileges that are required to run a parameter file conversion task:

Service	Asset	Privileges
Workbench Service	Parameter File Conversion Task	Create, Read, Update
Administrator	Folder	Create, Read, Update
	Project	Create, Read, Update
	Secure Agent	Read
	Secure Agent Group	Read

The following table lists the services along with the asset privileges that are required to run a configuration task:

Service	Asset	Privileges
Workbench Service	Connection Map Configuration	Create, Read, Update
	Conversion Property Configuration	Create, Read, Update
	Assessment Repoint Configuration	Create, Read, Update

Asset permissions for bulk update task

To create or run bulk update tasks, you need additional asset permissions from various IDMC services.

To configure asset permissions for user roles, go to IDMC Administrator service, open a role, select the required service, and select one or more permissions on the **Assets** tab for the role.

The following table lists the services along with the asset privileges that are required to create or update a bulk update task:

Service	Asset	Privileges
Workbench Service	Bulk Update Task	Create, Read, Update
Administrator	Folder	Create, Read

Service	Asset	Privileges
	Project	Create, Read
	Secure Agent	Read
	Secure Agent Group	Read

The following table lists the services and the asset privileges that are required to run a bulk update task:

Service	Asset	Privileges
Workbench Service	Bulk Update Task	Read, Run
Administrator	Folder	Create, Read, Update
	Project	Create, Read, Update
	Secure Agent	Read
	Secure Agent Group	Read
Data Integration	File Listener	Create, Read, Update
	Fixed-Width File Format	Create, Read, Update
	Mapping	Create, Read, Update
	Mapping Task	Create, Read, Update
	Mapplet	Create, Read, Update
	PowerCenter Task	Create, Read, Update
	Sequence Generator	Create, Read, Update
	Taskflow	Create, Read, Update
	User-Defined Function	Create, Read, Update

Feature privileges

The organization administrator can configure specific privileges for user roles in CDI-PC for modernization. Depending on the privileges, users can access certain features while other features are restricted.

To grant feature privileges to user roles, go to IDMC Administrator service, open a role, select **Workbench Service**, and select one or more features on the **Features** tab. For more information about assigning feature privileges to users, see the *User Administration* help.

Features in Workbench Service


The following table explains the features that are available for Workbench Service in IDMC Administrator:

Feature	Description
Download Artifacts	Allows users to download the files generated from an assessment job or a conversion job.
Import Assessment Results	Allows users to import assessment results of PowerCenter and Model repositories from another environment.
Repository Assessment	Allows users to assess a repository. **Note:** To run an assessment job, make sure that the Admin role is assigned to the user.
View Assessment Results	Allows users to access the assessment results.
View Configurations	Allows users to view the configurations.
View Jobs	Allows users to view the details of assessment, conversion, and parameter file conversion jobs.
View Tasks	Allows users to view the details of the assessment, conversion, and parameter file conversion tasks.

User interface of CDI-PC

Use the interactive user interface of CDI-PC to perform the modernization tasks.

The following image shows a sample CDI-PC home page:


tegration for PowerCenter
me
Welcome, John!
What is Cloud Data Integration for PowerCenter?
Cloud Data Integration for PowerCenter (CDI-PC) enables seamless modernization of PowerCenter to Informatica Intelligent Data Management Cloud (IDMC). CDI-PC provides c
capabilities for all your PowerCenter domains on a single IDMC pane. You can leverage the unified interface to monitor the status of your domains, nodes, and services. You can
automatic updates and security-fixes. You can also use the Self Service Capabilities to run assessments on your repositories, plan and migrate PowerCenter workloads to Cloud
industry-leading, cloud-native capabilities.
Download Installers
Download the CDI-PC server, client, Command Line Utility, and Hadoop installers. Additionally, you can download the digital signatures and TLS Utility for these installers.
Download Installers
Register a Domain
Register a domain before you can start using it in CDI-PC. After you register the domain, monitor the domain and node status on the dedicated domain management user interface in CDI-PC.
+ New Domain
Manage your
Monitor the status
domains. View det
domains up-to-dat
options.
Manage y
Assess repositories
Assess your repositories to evaluate the conversion potential of the assets. You can then convert the assets to Cloud Data Integration assets in a self-service mode.
View and Assess Repositories
3
Domain Status
5
AVAILABLE
1
OFFLINE
0
DEREGISTERED
4
Getting Start
Getting Started
PowerCenter (C
Register a Doma
Troubleshoot ar
IDMC Resource
What's New
Release Cadenc

1. Navigation Bar

Navigate to different components of CDI-PC to perform modernization. The navigation bar displays the following menu items:

Menu item	Description
New	Select the modernization configuration or task that you want to create.
Home	View the status of the registered domains, use shortcuts to perform various actions, and access the documentation.
Explore	Explore the domains, repositories, and configurations. You also have the option to explore the complete list of tasks, such as assessment, conversion, and bulk update tasks.
My Jobs	Monitor the status of assessment, conversion, and bulk update jobs.

2. Download Installers, Register a Domain, and Manage your Domains

Use the quick start menu options to download CDI-PC binaries, register a domain, and monitor the registered domains. For more information about domain management, see the *Domain Registration* section.

3. Assess repositories

Use the quick start menu option to view the list of repositories within the registered domains. You can assess a repository and then convert the assets to the cloud.

4. Domain Status

View the status of the registered domains.


5. Getting Started

Access the documentation and other related resources to learn and use CDI-PC effectively.

New Asset dialog box

Use the **New Asset** dialog box to create new configuration files, assessment tasks, workflow conversion tasks, or parameter file conversion tasks.

The following image shows the different tasks or configurations that you can create using the **New Asset** dialog box:




Configuration

A configuration is a collection of parameters that you can use in conversion tasks to override the default conversion behavior, map PowerCenter, Data Engineering Integration, and Data Quality connections to IDMC connections in conversion tasks, or evaluate the feasibility of repointing in assessment tasks.

You can create and manage configurations for assessment and conversion tasks.

The following image shows the configuration types:




You can create the following configurations:

- Conversion Properties. Use this configuration in conversion tasks to override the default conversion behavior.
- Connection Map. Use this configuration in conversion tasks to map the PowerCenter and Data Engineering Integration connections to IDMC connections.
- Repoint Configuration. Use this configuration in assessment tasks to evaluate the feasibility of repointing the assets to another endpoint.

Assessment Task

Create an assessment task to assess a PowerCenter or Model repository that includes reviewing the asset details within the repository and their conversion feasibility to the cloud environment.


The following image shows the **New Assessment Task** page:


Informatica Cloud Data Integration for PowerCenter
New...
Home
Explore
My Jobs
AssessmentTask...
AssessmentTask-5
The assessment process evaluates the feasibility of asset conversion. As p
complete.
Task Operation
Assess repository from Cloud Data Integration for PowerCenter
Im
Name of the task: *
AssessmentTask-5
Task Location: *
Default
Browse...
Runtime Environment: *
Description:
Enter Description
Shared Folder
The assessment job requires the parameter files to be copied to a shared fo
placed in this location.
Shared Folder Location: *
Migrate to a different endpoint
You can choose to migrate your assets to the cloud to another target. To m
one.
Do you want to migrate to a different end point?
Yes
No

Asset Conversion Task

After you complete the assessment of a repository, you can start the conversion process for the assets in the PowerCenter or Model repository. You can create a conversion task to specify the assets that you want to convert to Cloud Data Integration. You can only convert the assets that have their assessment results as automated or partial. Assets that have assessment results as manual require you to manually convert them after the completion of the assessment.


The following image shows the **ConversionTask** page:



Parameter File Conversion Task

You can create a parameter file conversion task to convert PowerCenter parameter files to Cloud Data Integration parameter files.


The following image shows the **New Parameter Conversion Task** page:



Bulk Update Task

After you convert and migrate the PowerCenter and Data Engineering Integration assets to the Cloud Data Integration assets, you can create bulk update tasks to simultaneously update the metadata of several assets. You can create export metadata tasks to export the existing metadata of the assets as Excel template files. After you update the Excel template files with new metadata, you can create update metadata tasks to update the metadata of the assets. You can also create or update multiple connections with one operation by creating an update metadata task.

The following image shows the **New Bulk Update Task** page:




Repositories page

On the **Repositories** page, you can view the repositories associated with the registered domains and assess the repositories.

Click **Explore** from the left navigation menu and select **Repositories** from the drop-down list. The page displays the list of repositories available in the registered domains in a tile view. You can click an assessed repository to view the folders and workflows within the repository.

The following image shows the **Repositories** page:



1. Filter repositories by domain

Select a domain to view the repositories associated with the domain.

2. Toolbar Menu

The toolbar menu contains the following options:

- Switch between list view and tile view
- Refresh repositories
- Sort repository list by repository name, number of assets, and domain name
- Filter repository list by repository name, domain name, and assessment status
- Search for a repository using repository name or domain name

3. Repositories


The repositories available in the selected domain. By default, you can view the repositories in the card view. You can switch to the grid view to display the repository details as a table. The tiles for assessed repositories contain the following information:

- Repository name
- Pie chart that displays the asset count based on the conversion potential
- Total number of assets in the repository
- Availability status of the repository
- Assessment status of the repository
- Actions menu that includes options to assess the repository and download assessment report

If the above details are not available for a repository, assess the repository to get these details.

Folders

When you click an assessed repository, you can view the folder structure of the corresponding PowerCenter or Model Repository Service repository. You can click a folder to view the workflows within the folder. The following image shows sample folders within a repository:




Each folder displays the total number of assets along with the breakdown of the assets based on their conversion potential. You can download the assessment report or assess the repository again to view the latest assessment status.

Workflows

When you click a folder of an assessed repository, the **Workflows** page appears containing the list of workflows within the folder.

The following image shows sample workflows within a folder:



Each workflow displays its assessment result and conversion status. You can click the links in the **Assessment Result Details** column to view the list of flags responsible for manual or partial conversion of a


workflow. You can select workflows with automated or partial assessment, and create a conversion task with these workflows.

Assessment result details

The assessment result of a workflow displays the details of the flags that are responsible for the manual or partial conversion of the workflow.

When you click a link in the **Assessment Result Details** column, the **Assessment Result** page appears containing the details of the flags that are responsible for a manual or partial conversion of a workflow.

The following image shows sample assets in a workflow and the associated flags:



You can view the list of assets of a workflow that can be manually or partially converted on the **Assets** pane. The following table describes the details that you can view for the assets:

Column Name	Description
Status	Shows if you can manually or partially convert the asset.
Asset Name	Name of the asset.
Asset Type	Type of asset, such as mapping, session, and maplet.
Path	Location of the asset in the PowerCenter or Model repository.

You can click an asset to view the list of associated manual and partial flags. The following table describes the details you can view on the **Flags** table:

Column Name	Description
Status	Shows if the flag causes manual or partial conversion.
Flag Name	Name of the flag.

Column Name	Description
Description	Description of the flag.
Suggestion	Recommended actions to perform before you convert the asset.

Repository dashboard

The dashboard of an assessed repository provides a graphical representation of the overall migration status on-premises assets to the cloud.


The dashboard provides a centralized view of the migration of PowerCenter, Data Engineering Integration, or Data Quality assets to Data Integration for a repository. After you assess a repository, you can access the dashboard to graphically analyze and gain insights into the migration progress.

Note: The dashboard displays the migration status of a repository based on the latest assessment and conversion jobs.

PowerCenter repository dashboard

The dashboard of an assessed PowerCenter repository provides a graphical representation of the overall migration status from PowerCenter to Data Integration.

The following image shows a sample dashboard of a PowerCenter repository:


QISCNTR10
Domain Display Name
Repository Name
QISCNTR10
Folder Name
All Folders
Assessment task results
Workflows
Worklets
Sessions
Mappings
Mapplets
Asset Type
0
5k
10k
15k
20k
25k
30k
Number of assets assessed
Manual
Partial
Automated
Converted workflows
Converted
1
Total
25,677
To be converted
25,676
Converted
To be converted
Top 5 manual flags
For the current repository. A "Manual" flag refers to a flag that caused the assessment to end in a "Manual" result.
Workflows
Allow Concurrent Run setting is enable...
Concurrent Execution with unique inst...
Concurrent Execution with same insta...
Flag Name
0
50
100
150
200
250
Asset count
Worklets
No flags found
Flag Name
0
1
Asset count
Sessions
Contains UDT transformaton
Contains unsupported connection types
Unsuppported target transformation
Unsuppported source qualifier
XML source qualifier
Flag Name
0
100
200
300
400
500
600
Asset count
Mappings
Contains unsupported connection types
Contains unsupported transformations
Contains mapplet with data quality tra...
Contains UDT transformaton
Unsuppported target transformation
Flag Name
0
200
400
600
800
Asset count
Mapplets
Contains HTTP transformation
Flag Name
0
10
20
30
40
50
60
70
Asset count
Top 5 partial flags
For the current repository. A "Partial" flag refers to a flag that caused the assessment to end in a "Partial" result.
Workflows
Contains Workflow variables
Allow Concurrent Run setting is enabled
Concurrent Execution is enabled with ...
Concurrent Execution with unique inst...
Concurrent Execution with unique inst...
Flag Name
0
1k
2k
3k
4k
5k
6k
7k
Asset count
Worklets
No flags found
Flag Name
0
1
Asset count
Sessions
Parent mapping has multiple sessions
Parent mapping has multiple session
Lookup attributes are overridden
Lookup cache directory property is ove...
Parent mapping is used multiple sessi...
Flag Name
0
2k
4k
6k
8k
10k
Asset count
Mappings
Parent mapping has multiple session
Parent mapping is used multiple sessi...
Mapplets
Lookup present in parent mapping and...
Lookup sub second property is modifi...

The dashboard displays the following details of a repository:

Assessment result

Provides a graphical representation of the latest assessment task result of a repository. You can view a breakdown of the assets available in the repository based on asset type and conversion potential.

Converted workflows

Displays a graphical comparison of converted and unconverted assets of the repository. For a PowerCenter repository, you can view the conversion details of workflow assets only.

Top 5 Manual Flags

Displays the top five manual flags for each asset type based on the latest assessment result of the repository.

Top 5 Partial Flags

Displays the top five partial flags for each asset type based on the latest assessment result of the repository.


Connection types

Displays the details of supported and unsupported repoint connections of a repository in a tabular format. You can download the connection details in the CSV file format.


Model repository dashboard

The dashboard of an assessed Model repository provides a graphical representation of the overall migration status of Data Engineering Integration and Data Quality assets to Cloud Data Integration.

The following image shows a sample dashboard of a Model repository that contains Data Engineering Integration assets:


Model_Assessment
Domain Display Name
Repository Name
Model_Assessment
Project Name
All Projects
Assessment task results
Mapping count represents the sum of standalone mappings plus mappings contained within workflows.
Assessment results
Profiles
2
Rules
0
Scorecards
2
Mappings
252
Mapplets
20
Workflows
10
Asset Type
Number of assets assessed
Mappings within workflows vs. Standalone mappings
Mappings within workflows
9
Standalone mappings
243
Mappings
Number of mappings assessed
Mappings by runtime environment
Number of mappings assessed
71
51
130
0
Datastricks
Hadoop
Native
Passthrough
Execution Engines
Manual
Partial
Automated
Converted assets
Converted vs To be converted
Number of assets converted
252
10
Mappings
Workflows
Asset Type
Mappings within workflows vs. Standalone mappings
Number of mappings
9
243
Mappings within workf...
Standalone mappings
Asset Type
Converted
To be converted
Top 5 manual flags
For the current repository. A "Manual" flag refers to a flag that caused the assessment to end in a "Manual" result.
Profiles
Profile Task Name
Profile Is Purge Previous Results
Profile Conformancecriteria Minpercen...
Profile Func Dependency Profiling Dete...
Profile Func Dependency Profiling Dep...
Flag Name
Asset count
Rules
No flags found
Scorecards
Scorecard Is Cost Unit Present
Scorecard Is Notification Enabled
Scorecard Is Score Group Present
Scorecard Is Profile Task Present
Workflows
No flags found
Mappings
Noof Source Custom Do
Unsupported Datatype Present in Sour...
Target : Created by Linking dynamic p...
Noof Source Logical Do
Unsupported Datatype Present in Map...
Mapplets
Unsupported Datatype Present in Sour...
Unsupported Datatype Present in Map...
Noof Source Custom Do
Unsupported Datatype Present in Filter
Top 5 partial flags
For the current repository. A "Partial" flag refers to a flag that caused the assessment to end in a "Partial" result.
Profiles
No flags found
Rules
No flags found
Scorecards
No flags found
Workflows
No flags found
Mappings
Target: Delete operation enabled
Target: Insert Operation Enabled
Target Schema Strategy retain present
Target partition type
Target: Maintain row order enabled
Mapplets
Target: Insert Operation Enabled
Target: Delete operation enabled
Connection types (8)
Find
Connection types that are not supported by Informatica are marked "*". To convert them, see online help.
Type ↑
Source
Target
Lookup
Stored Procedure
SQL Transformat...
Total Supported
Total Not Suppor...
Total
FlatFile 10 84 2 0 0 96 0 96
Hive 85 12 1 0 0 98 0 98
JDBC 19 19 3 0 0 41 0 41

The following image shows a sample dashboard of a Model repository that contains Data Quality assets:



The dashboard displays the following details of a repository:

Assessment result

Provides a graphical representation of the latest assessment task result of a repository. You can view the following assessment details:

- Breakdown of the assets available in the repository based on asset type and conversion potential in the Assessment results chart.
- Total number of mappings that are used in workflows and standalone mappings in the repository and their conversion potential.
- Count of mappings based on the execution engine used by them.

Converted assets

Displays a graphical comparison of converted and unconverted assets of the repository. You can view the following conversion details:

- Comparison between converted and not converted assets based on the asset types.
- Comparison between the number of mappings within workflows and standalone mappings based on their conversion status.

Top 5 Manual Flags

Displays the top five manual flags for each asset type based on the latest assessment result of the repository.

Top 5 Partial Flags

Displays the top five partial flags for each asset type based on the latest assessment result of the repository.

Connection types

Displays the details of supported and unsupported repoint connections of a repository in a tabular format. You can download the connection details in the CSV file format.

Configurations page

You can manage an existing configuration by performing different actions on the configuration, such as modifying the configuration, creating a copy of an existing configuration, or renaming a configuration.

The **Configurations** page lists the repoint, connection map, and conversion properties configurations. Click the actions menu on a configuration and select the appropriate action to manage the configuration.

You can perform the following actions on a configuration:

View

Click **View** to view the configuration details.

Edit

Click **Edit** to modify the configuration description and properties for the configuration.

Copy

Click **Copy** to copy the configuration to another domain and repository with a different name.

Rename

Click **Rename** to change the name of the configuration.

Set as default

Click **Set as default** to set the configuration as the default configuration. For each configuration type, you can set one configuration as default. When you select a configuration in assessment or conversion tasks, the configuration is marked as default.


Delete

Click **Delete** to delete a configuration. You can delete a configuration only if it is not associated with any assessment or conversion task.

All Tasks page


Click **Explore** from the left navigation menu and select **All Tasks** from the drop-down list. The list of tasks that you created appears.

The following image shows a sample **All Tasks** page:



Each task displays the name, last update time, description, and location where the converted workflows are stored in Cloud Data Integration. You can use the actions menu to run a conversion job, edit the job details, or delete the job. Click a task name to view the details fo the task.

Use the filter option to filter the tasks based on the task type as shown in the following image:



Sizing recommendations

To manage concurrent execution of multiple assessment and conversion jobs, Informatica recommends that you group the Secure Agents. When you group the Secure Agents, the task distribution is balanced between the Secure Agents, allowing each agent to process one assessment job and two conversion jobs simultaneously.

To enable parallel execution of two assessment tasks, ensure that you have at least two Secure Agents in the Secure Agent Group.

To ensure efficient execution of the assessment and conversion jobs and to prevent any memory-related performance issues, configure the memory of the PC2CDIModernizationApp agent application based on the

size of the repository and PC XML. The following table provides the memory recommendations for the PC2CDIModernizationApp agent application for different configurations:

Repository Size	PC XML ZIP Size	RAM Size (-Xmx)
200 MB	N/A	1 GB (-Xmx)
1 GB	N/A	1 GB (-Xmx)
4 GB	N/A	4 GB (-Xmx)
9 GB	N/A	5 GB (-Xmx)
200 MB	600 MB	2 GB (-Xmx)
1 GB	600 MB	2 GB (-Xmx)
4 GB	600 MB	5 GB (-Xmx)
9 GB	600 MB	6 GB (-Xmx)

Note: The size suggested for the PC XML ZIP file is an approximate value. For example, if you have 20 XML files of 30 MB each, the approximate size of the ZIP file is 600 MB.

For information on configuring the memory for PC2CDIModernizationApp, see "Configuring memory for Secure Agent" on page 36.

Configuring memory for Secure Agent

You can configure the memory for the PC2CDIModernizationApp agent application from the Informatica Administrator service.

1. Access the Administrator service.
2. On the left navigation menu, click **Runtime Environments**.
3. On the **Runtime Environments** page, click the name of the Secure Agent that you want to configure.
4. In the upper-right corner, click **Edit**.
5. In the **System Configuration Details** area, select the **PC2CDIModernizationApp** service.
6. In the row that contains the JRE_OPTS property, click the **Edit Agent Configuration** icon.
7. Enter the new memory value based on the recommendations available in the "Sizing recommendations" on page 35 topic.
8. If you want to configure the maximum size of the file chunk to be uploaded to cloud, specify the size in MB in the FILE_CHUNK_SIZE property.

   Default is 30.

   Note: The maximum supported size for file chunk is 30MB. If you specify a value greater than 30, the value in the FILE_CHUNK_SIZE property is set to the default value.
9. If you want to configure the maximum buffer size, specify the size in MB in the UPLOAD_BUFFER_SIZE property.

   Default is 5.

   Note: The maximum supported buffer size for is 5MB. If you specify a value greater than 5, the value in the UPLOAD_BUFFER_SIZE property is set to the default value.

10. Click **Save**.

    The memory for the PC2CDIModernizationApp agent application is configured.

CHAPTER 2

Repository Assessment

Assess a PowerCenter or Model repository to review the asset details within the repository along with their conversion feasibility to the cloud environment.

Before initiating the conversion of PowerCenter, Data Engineering Integration, or Data Quality assets to the cloud, it is crucial to determine the feasibility of converting the assets within a PowerCenter or Model repository. You can find out the conversion feasibility by assessing the PowerCenter or Model repository. When you assess a repository, CDI-PC creates a backup of the repository, restores the backup in IDMC, and then runs the assessment. The assessment groups the assets into the following categories based on their conversion criteria:

- Automated. The conversion service can convert these assets automatically. The converted assets do not need any manual intervention in Cloud Data Integration after the conversion process.
- Partial. The conversion service can convert these assets to the cloud, however, you might need to do some manual tweaks on the converted Cloud Data Integration assets.
- Manual. Assets classified as manual conversion might require redesign of the assets because there is no direct support available for these assets in cloud. These assets cannot be migrated and needs to be created manually created on Data Integration.

The assessment process also generates a comprehensive report detailing the reasons behind assets being categorized as partial or manual.

Before you begin

Before you assess a repository, perform the following steps.

1. Create a directory which is accessible from the domain machine and the secure agent. The user who started the Informatica Domain and Secure Agent must have read, write, and execute permissions on this shared directory location. Create the following folders within the shared directory location:

   `<SharedDirectoryLocation>\<DomainDisplayName>\<RepositoryName>\Templates`

   For example, if the name of the CDI-PC repository that you are going to assess is `Test_Repo` and the display name of the domain is `Test_Domain`, create the folders in the following format:
   `<SharedDirectoryLocation>\Test_Domain\Test_Repo\Templates`
2. Collect the parameter files from your PowerCenter, Data Engineering Integration, or Data Quality environment and store them in the ZIP format in the folder created in step 1.

   Parameter files are the configuration files that are used for running workflows and sessions present in a repository. Parameter files are optional for assessment.

Note: If your version is April 2024 or newer, the file name for the assessment of PowerCenter repositories should be `PC_Parameter.zip`. For versions older than April 2024, the file name should be `PC_PARAMETER_ZIP.zip`. For the assessment of Model repositories, the file name should be `MRS_Parameter.zip`.

3. Create a Repoint configuration. For information on creating a Repoint configuration, see "Creating a repoint configuration" on page 39.
4. Assign the Admin role to the user running the assessment. For any assistance on assigning the Admin role, contact the administrator.

Creating a repoint configuration

Create a repoint configuration where you can define various connection endpoints to which you want to repoint the assets. You can use this configuration in assessment tasks to evaluate the feasibility of repointing the assets to another endpoint.

The following video shows you how to create a repoint configuration:



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.
2. Click **Configuration**, and then click **Create**.

   The **New Configuration** page appears.
3. From the **Configuration Type** list, select **Repoint Configuration**.
4. Enter a name and description for the configuration.
5. From the **Domain** list, select the domain where you want to use this configuration.
6. From the **Repository Type** list, select the type of repository where you want to use this configuration, and then click **Next**.
7. In the **Select Endpoints and Transformations** page, click **+**.

   You can add multiple endpoints and transformations.
8. Select a PowerCenter or Data Engineering Integration connection type and a cloud connection type to which you want to repoint the migrated assets.
9. In the **Transformation** column, select the transformations where you want to use this repoint.

   You can use the following transformations for a repoint:

   - Source
   - Target
   - Lookup Transformation
   - SQL Transformation
   - Stored Procedure Transformation
10. Click **Save Configuration**.

    You can use this configuration when you assess a repository in the specified domain.

Creating an assessment task

Evaluate the conversion feasibility of the PowerCenter, Data Engineering Integration, and Data Quality assets to the cloud environment.

You can create assessment tasks to assess PowerCenter or Model repositories within CDI-PC or import the assessment results of already assessed repositories from another environment.


Assessing a repository

Create an assessment task to evaluate the conversion feasibility of the PowerCenter, Data Engineering Integration, or Data Quality assets to the cloud environment.

Before you assess a repository, perform the following steps:

- Store the parameter file in ZIP format in the shared directory you created. Ensure that the parameter file contains only text content. If the parameter file includes executables or binary files, file validation fails and prevents the assessment task from running.
- If you want to repoint PowerCenter or Data Engineering Integration assets to a different endpoint after migrating to the cloud, create a repoint configuration to specify the repoint parameters. For information about creating a repoint configuration, see the "Creating a repoint configuration" on page 39 topic.

The following video shows you how to create an assessment task:



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.
2. Click **Assessment Task**, and then click **Create**.

   The **New Assessment Task** page appears.
3. In **Task Operation**, select **Assess repository from Cloud Data Integration for PowerCenter** to assess a PowerCenter or Model repository.
4. Enter the required information as shown in the following table:

Property	Description
Name of the task	Name of the assessment task.
Task Location	Location in Data Integration to save the assessment tasks.
Runtime Environment	The name of the runtime environment where you want to run the assessment job.
Description	(Optional) Description of the assessment job.
Domain	The domain that contains the repository to be assessed.

Property	Description
Repository Type	The type of repository to be assessed. Select one of the following repository types: - **PowerCenter**. To assess PowerCenter assets. - **Model**. To assess Data Engineering Integration or Data Quality assets.
Repository	Repository to be assessed.
Are the parameter files placed in the shared folder?	Confirm that you have copied the parameter files to the following location: `<shared_folder>\<domain_name>\<repository_name>\Templates`
Shared Folder Location	Base location of the shared folder where you copied the parameter files. For example, if you have copied the configuration files to the `<SharedDirectoryLocation>\<DomainDisplayName>\<RepositoryName>\Templates` folder, the base location is `<SharedDirectoryLocation>\`. The file path format that you provide must be compatible with the operating system of the repository service node.

5. (Optional) To repoint the PowerCenter, Data Engineering Integration, or Data Quality assets to a different endpoint after migrating to the cloud, select the repoint configuration.
   a. Confirm that you want to migrate the assets to a different end point.
   b. Select the repoint configuration that you want to use for this assessment.
   c. Click **Validate**.

      CDI-PC validates if the required input files are available in the shared directory location.

      On successful validation, the **Start Assessment** button is enabled.
6. Click **Start Assessment**.

   An assessment job is created and the assessment process starts.

   Based on the repository size, it might take several minutes to few hours for the assessment process to complete. You can monitor the status of the assessment job in the **My Jobs** page.

   Additionally, CDI-PC sends an email notification after the assessment job completes.

Importing assessment results

Import assessment results of PowerCenter and Model repositories from another environment.

Before you import, ensure that the following requirements are met:

- The name of the assessment results file is `assessment_metadata.zip`.
- The `assessment_metadata.zip` is located in the following directory, `<SharedDirectoryLocation>\<DomainDisplayName>\<RepositoryName>\ImportFiles\`.
- The `assessment_metadata.zip` file is not older than 15 days.

1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.
2. Click **Assessment Task**, and then click **Create**.

   The **New Assessment Task** page appears.
3. In **Task Operation**, select **Import assessment results** to import the assessment results of a PowerCenter or Model repository that has already been assessed in another environment.

4. Enter the required information as shown in the following table:

Property	Description
Name of the task	Name of the assessment task.
Task Location	Location in Data Integration to save the assessment tasks.
Runtime Environment	The name of the runtime environment where you want to run the assessment job.
Description	(Optional) Description of the assessment job.
Domain	The domain that contains the repository to be assessed. Ensure that you select the same domain as mentioned in the `assessment_metadata.zip`.
Repository Type	The type of repository to be assessed. Select one of the following repository types: - **PowerCenter**. To assess PowerCenter assets. - **Model**. To assess Data Engineering Integration or Data Quality assets.
Repository	Repository to be assessed. Ensure that you select the same repository as mentioned in the `assessment_metadata.zip`.
Shared Folder	Base location of the shared folder where you copied the assessment results ZIP file. For example, if you have copied the file to the `<SharedDirectoryLocation>\<DomainDisplayName>\<RepositoryName>\ImportFiles\` folder, the base location is `<SharedDirectoryLocation>\`. The file path format that you provide must be compatible with the operating system of the repository service node.

5. Click **Validate**.

   CDI-PC validates if the assessment results file is available in the shared directory location.

   On successful validation, the **Start Assessment** button is enabled.

6. Click **Start Assessment**.

   An assessment job is created and the assessment process starts. You can monitor the status of the assessment job in the **My Jobs** page.

   Additionally, CDI-PC sends an email notification after the assessment job completes.

Re-assessing a repository

You can re-assess an already assessed repository directly from the **Explore** page.

When you re-assess a PowerCenter or Model repository, the conversion status of successfully converted assets and the assessment details from previous runs remain unchanged. If you have converted some assets before re-assessing a repository, CDI-PC retains the conversion status and the latest assessment result of the repository shows the conversion status of the converted assets as successful.
Note: CDI-PC does not retain the conversion status of failed conversion tasks.

When you create an assessment task to re-assess a repository, the reassessment job runs with the same task name as the previous assessment task, but with an incremental run ID. For example, if you re-assess a repository with a previous assessment task named *AssessmentTask-A*, the re-assessment job runs with the

task name *AssessmentTask-A* and the run ID *AssessmentTask-A_1*. You can compare the results of the assessment runs by downloading the assessment reports from the **My Jobs** page.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **Repositories**.

   A list of repositories available in the domains registered with CDI-PC appears.
3. Identify the repository that you want to assess.
4. Click **Assess Repository**.

   Alternatively, to re-assess a previously assessed repository, click **Assess again** from the actions menu.

   The **Edit Assessment Task** page appears.
5. Enter the required information as shown in the following table:

Property	Description
Name of the task	(Optional) Name of the assessment task.
Assessment Task Location	Location in Data Integration to save the assessment tasks.
Runtime Environment	The name of the runtime environment where you want to run the assessment job.
Description	(Optional) Description of the assessment job.
Domain	The domain that contains the repository to be assessed.
Repository Type	The type of repository to be assessed. Select one of the following repository types: - **PowerCenter**. To assess PowerCenter assets. - **Model**. To assess Data Engineering Integration or Data Quality assets.
Repository	Repository to be assessed.
Are the parameter files placed in the shared folder?	Check box to confirm that you have copied the parameter files to the following location: `<shared_folder>/<domain_name>/<repository_name>/Templates`
Shared Folder Location	Base location of the shared folder where you copied the parameter files. For example, if you have copied the configuration files to the `<SharedDirectoryLocation>\<DomainDisplayName>\<RepositoryName>\Templates` folder, the base location is `<SharedDirectoryLocation>\`.

6. (Optional) To repoint the PowerCenter, Data Engineering Integration, or Data Quality assets to a different endpoint after migrating to the cloud, select the repoint configuration.

   Note: If a repository is assessed without repointing the assets, create a new assessment task to repoint and re-assess the repository.

   a. Confirm that you want to migrate the assets to a different end point.

   b. Select the repoint configuration that you want to use for this assessment.

   c. Click **Validate**.

      CDI-PC validates if the required input files are available in the shared directory location.

      On successful validation, the **Start Assessment** button is enabled.
7. Click **Start Assessment**.

An assessment job with a new job ID is created and the assessment starts.You can monitor the status of the assessment job in the **My Jobs** page. Additionally, CDI-PC sends an email notification after the assessment job completes. You can compare the latest assessment results with the previous assessment by reviewing the job details of the previous run on the **My Jobs** page.

Accessing assessment results

Review the assessment result to understand the conversion potential of the assets and the underlying parameters contributing to the result.

After the assessment is successfully completed, you can access the assessment results on the user interface. These results provide a visual representation of the assets categorized by their potential for conversion. Assets that CDI-PC can convert automatically are indicated by the color Green, partially convertible assets are marked in Yellow, and assets requiring manual conversion are marked in Grey.

For the workflows and mappings that are marked as Partial or Manual, you can view the details of the assessment result on the user interface. Additionally, you can download an assessment report that includes detailed information on the assessment results. To learn more about the Assessment report, see the "Assessment report" on page 48 topic.

In addition to the assessment report, the assessment job also generates additional output files that you can use as inputs in the conversion process. If you have chosen to analyze mapping patterns, the assessment job generates mapping analysis reports. For more information on the output files, see the "Assessment output files" on page 44 topic.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **Repositories**.

   A list of repositories appears. If the assessment is successfully completed on a repository, you can see the asset categorization in a graphical view.
3. Click a repository name to view the folders inside the repository along with the assessment result for each folder.
4. For the workflows and mappings that are marked as **Partial** or **Manual**, click the corresponding **More details** link in the **Assessment Results** column.

   A dialog box appears, containing information on the flags that are preventing automatic conversion of the workflow.
5. Review the report to understand the reasons preventing the automatic conversion of an asset.
6. Alternatively, to download the assessment report, click **Download Reports**.

   A ZIP file is downloaded containing the assessment report. The assessment report is available in MS Excel format.
   For more information about the assessment report, see "Assessment report" on page 48.

Assessment output files

When you download the reports for an assessment job, CDI-PC downloads a ZIP file containing assessment reports, log files, and configuration templates. Some of these files are used as inputs in the conversion process.

The following table contains the list of assessment output files for a PowerCenter repository:

File Name	User Action	Content
<Repository_Name>_ASSESSMENT_SUMMARY	Review	Review the assessment summary file to view detailed information about the assessment result. For more information on the assessment report, see the "Assessment report" on page 48 topic.
Command_List.xlsx	Review	Review the `Command_List.xlsx` file to verify the commands used in the workflows.
File_List.xlsx	Review	Review the `File_List.xlsx` file to verify the list of flat files used in the workflows with their source and target directories.
Parameter_Files.xlsx	Review	Review the `Parameter_Files.xlsx` file to verify the details of the workflow and session parameter files, such as file name, location, and task type.
Sql_List.csv	Review	Review the `Sql_List.csv` file to view the list of SQL queries used in the transformations.
Xml_Pre_Processing_Configuration.xlsx	Use as input for conversion	Configure the `Xml_Pre_Processing_Configuration.xlsx` file to specify additional attributes for the conversion process, such as names for duplicate worklets, session level attributes, and connection subtype. For more information on configuring the XML Pre-processor file, see the *Configuring the XML Pre-processor file* topic.
Connection_Details.xlsx	Review	Review the `Connection_Details.xlsx` file to verify the list of parameterized PowerCenter connections available in the repository and their resolved values for each transformation. To migrate your assets to a different endpoint, you can create a Connection Map configuration to map the PowerCenter connections to specific cloud connections. For information on creating a Connection Map configuration, see the *Creating a Connection Map configuration* topic.

File Name	User Action	Content
Conversion_Configuration.properties	Review	Review the `Conversion_Configuration.properties` file to verify the conversion properties and their default values. You can create a Conversion Properties configuration to override these default values. For information on creating a Conversion Properties configuration, see the *Creating a Conversion Properties configuration* topic.
MULTI_SESSION_PC2C_FILE.xlsx	Use as input for conversion	Configure the `MULTI_SESSION_PC2C_FILE.xlsx` file to specify multi-session mappings where sessions are present across different workflows. For more information on configuring the XML Pre-processor file, see the *Configuring the XML Pre-processor file* topic.
<Repository_Name>_SQL_ELT_Summary	Review	Review the SQL ELT pattern summary to get a list of mapping and maplets in the repository that follow SQL ELT rules and are being repointed to Snowflake.
MasterSql.xlsx	Review	Review the master SQL conversion file to get a list of folders in the repository that contain the SQL queries.
ConvertSql<file_number>.xlsx	Use as input for conversion	Configure the `ConvertSql.xlsx` files to specify the converted SQL queries. For more information on configuring the SQL conversion files, see *Configuring the SQL conversion files*.
Connection_Summary_Report.xlsx	Review	Review the connection summary report to get a list of all supported and unsupported connections available in the repository.
MANUAL_FLAGS.csv	Review	Review the `MANUAL_FLAGS.csv` file to get a list of all manual flags and the number of assets impacted by the flags in the repository.
PARTIAL_FLAGS.csv	Review	Review the `PARTIAL_FLAGS.csv` file to get a list of all partial flags and the number of assets impacted by the flags in the repository.

File Name	User Action	Content
<Transformation type> Transformation.csv	Review	Review the `Lookup Transformation.csv`, `SourceQualifier Transformation.csv`, `SQL Transformation.csv`, `StoredProcedure Transformation.csv`, and `Target Transformation.csv` files in the TXConnectionInfo folder to get connection details of each transformation type.
BulkUpdateConnectionTemplate.xlsx	Use as input to create or update connections	Review the `BulkUpdateConnectionTemplate.xlsx` file and update the connection details. Use this file in a bulk update task to create or update connections. For more information, see *Updating assets metadata*.

The following table contains the list of assessment output files for a Model repository:

File Name	User Action	Content
<Repository_Name>_ASSESSMENT_SUMMARY	Review	Review the assessment summary file to view detailed information about the assessment result. For more information on the assessment report, see the "Assessment report" on page 48 topic.
Connection_Details.xlsx	Review	Review the `Connection_Details.xlsx` file to verify the list of Data Engineering Integration connections available in the repository.
Connection_Summary_Report.xlsx	Review	Review the connection summary report to get a list of all supported and unsupported connections available in the repository.
MANUAL_FLAGS.csv	Review	Review the `MANUAL_FLAGS.csv` file to get a list of all manual flags and the number of assets impacted by the flags in the repository.

File Name	User Action	Content
PARTIAL_FLAGS.csv	Review	Review the `PARTIAL_FLAGS.csv` file to get a list of all partial flags and the number of assets impacted by the flags in the repository.
MRS_Parameter_Generated.zip	Use as input for conversion	Contains parameter and parameter set details as CSV files. The CSV files are used in the conversion tasks to convert the assets to the cloud environment. Configure the parameter set files to update the parameter values of the assets.

Assessment report

The assessment report contains the detailed information about the assessment result for a repository. You can download the report from the **Repository** page.
The assessment report for a PowerCenter repository is generated in the XLSX format and contains the following sheets:

Sheet Name	Contents
Overall Summary	Contains the repository details, domain details, asset count, conversion rate, and additional details, such as the number of mapping shortcuts and reused maplet instaces in the repository.
Asset Summary	Contains a list of flags and the number of assets impacted by the flags. The sheet also contains the assessment result of the assets and provides suggestions to resolve the flags.
Connection_Summary	Contains the repoint configuration details and the list of connections used in the assessed repository with their count.
Workflows	Contains the list of workflows in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a workflow.
Sessions	Contains the list of workflow and worklet sessions in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of the workflow and worklet sessions.
Mappings	Contains the list of mappings in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a mapping.
Mapplets	Contains the list of mapplets in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a mapplet.
Worklets	Contains the list of worklets in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a worklet.
Complexity Report	Contains a list of asset types in the repository and the asset count based on the difficulty levels to convert the assets.

The assessment report for a Model repository that contains Data Engineering Integration assets is generated in the XLSX format and contains the following sheets:

Sheet Name	Contents
Summary	Contains the repository details, domain details, asset count, conversion rate, and additional details, such as the number of mapping shortcuts and reused maplet instances in the repository.
Asset Summary	Contains a list of flags and the number of assets impacted by the flags. The sheet also contains the assessment result of the assets and provides suggestions to resolve the flags.
Connection_Summary	Contains the repoint configuration details and the list of connections used in the assessed repository with their count.
Workflows	Contains the list of workflows in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a workflow.
Mappings	Contains the list of mappings in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a mapping.
Mapplets	Contains the list of mapplets in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a mapplet.
Applications	Contains the list of applications in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a worklet.
Projects	Contains the list of projects in the repository.

The assessment report for a Model repository that contains Data Quality assets is generated in the XLSX format and contains the following sheets:

Sheet Name	Contents
Summary	Contains the repository details, domain details, total number of projects, total number of failed projects, conversion rate, and asset count based on their conversion potential.
Asset Summary	Contains a list of flags and the number of assets impacted by the flags. The sheet also contains the assessment result of the assets and provides suggestions to resolve the flags.
Connection Summary	Contains the repoint configuration details and the list of connections used in the assessed repository with their count.
Workflows	Contains the list of workflows in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a workflow.
Mappings	Contains the list of mappings in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a mapping.
Mapplets	Contains the list of mapplets in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a mapplet.
Applications	Contains the list of applications in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of an application.
Projects	Contains the list of projects in the repository.

Sheet Name	Contents
Failed Projects	Contains the list of failed projects in the repository. This sheet also contains the status of the project and the associated error message.
Profile	Contains the list of profiles in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a profile.
Scorecard	Contains the list of scorecards in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a scorecard.
Rules	Contains the list of rules in the repository. This sheet also contains the list of flags responsible for manual or partial conversion of a rule.

CHAPTER 3

Asset Conversion

You can convert your PowerCenter and Data Engineering Integration assets to the corresponding assets in Cloud Data Integration. Conversion is the process of migrating the PowerCenter and Data Engineering Integration assets to the cloud environment.

After you complete the assessment for a repository, you can start the conversion process for the assets within the repository. The conversion process converts PowerCenter mappings, mapplets, sessions, and workflows to Cloud Data Integration mappings, mapplets, mapping tasks, and taskflows. The conversion process uses a set of configurations to convert the assets and stores them in the specified location in Cloud Data Integration repository. Currently, you can convert Data Engineering Integration mapping and workflow assets.

Before you begin

Before you convert PowerCenter or Data Engineering Integration assets, complete the following steps:

1. Complete the assessment of the repository. For more information on assessment, see the *Repository Assessment* section.
2. Assign the required asset permissions to create or run a conversion task. For more information on the asset permissions, see the "Asset permissions for conversion task" on page 8 topic.
3. To convert PowerCenter assets, configure the `Xml_Pre_Processing_Configuration.xlsx` file to pre-process the PC XML before converting or repointing. For more information on configuring this file, see the "Configuring the XML Pre-processor file" on page 52 topic.
4. Create a Connection Map configuration to map the old connection types and connection names to new connection types and connection names. For more information on creating this configuration, see the "Creating a connection map configuration" on page 53 topic.
5. Create a Conversion Properties configuration to override the default conversion behavior. For more information on creating this configuration, see the "Creating a conversion properties configuration" on page 79 topic.

Configuring the XML Pre-processor file

Configure this file to specify additional attributes for the conversion process of PowerCenter assets, such as names for duplicate worklets, and session level attributes.

1. Open the `Xml_Pre_Processing_Configuration.xlsx` file from the following location:

   `<SharedFolder>/<DomainDisplayName>/<RepositoryName>/Templates/Xml_Pre_Processing_Configuration.xlsx`

2. Configure the required parameters.

   The following table lists the sheets in the `Xml_Pre_Processing_Configuration.xlsx` along with the description for each sheet:

Sheet Name	Description
DUPLICATE_WORKFLOW_WORKLET	Contains a list of duplicate workflow and worklet combinations available in the repository. Use the DUPLICATE_WORKFLOW_WORKLET sheet to specify new names for the duplicate workflow and worklet combinations.
CHANGE_TARGET_DB_TYPE	Use the CHANGE_TARGET_DB_TYPE sheet to change the target database type during asset conversion.
UPDATE_CONNECTION_SUBTYPE	Use the UPDATE_CONNECTION_SUBTYPE sheet to specify the connection sub types for a connection.
DUPLICATE_WORKLET_NAME	Contains a list of duplicate worklets available in the repository. Use the DUPLICATE_WORKLET_NAME sheet to specify a new name for a duplicate worklet.
DUPLICATE_EVENT_WAIT_TIME	Contains a list of duplicate event wait tasks. Use the DUPLICATE_EVENT_WAIT_TIME sheet to specify new event names for the duplicate events.
STANDARDIZE_RULE_INFO	Contains a list of rules to use with business data.
ADD_SESSION_LEVEL_ATTRIBUTES	Use the ADD_SESSION_LEVEL_ATTRIBUTES sheet to update the session level properties.
DUPLICATE_SESSION_INSTANCE_NAME	Contains a list of duplicate session instance names available in the repository. Use the DUPLICATE_SESSION_INSTANCE_NAME sheet to specify new names for the duplicate session instance names.

3. Save the file.

   The conversion process uses this file update specified attributes.

SQL conversion

Review the SQL conversion configuration files that are generated after assessing a PowerCenter repository.

The SQL conversion configuration files retrieve SQL details from the assessment of PowerCenter repositories. You can specify the converted SQL queries for the target endpoint and use the files to generate converted SQL queries. For example, to repoint an Oracle query to a Snowflake query, specify the converted

SQL query for Snowflake in the configuration files and use the files to create a conversion properties configuration. Use the conversion properties configuration to create a parameter file conversion task, and then run the task to generate the converted queries.

You can find the SQL conversion configuration files in the SqlQueries folder of the downloaded assessment ZIP file. The SqlQueries folder contains the following types of files:

MasterSql

This file contains a list of folders in the repository that contain the SQL queries. The folders are organized into separate ConvertSql files, with each file containing the SQL details of 10 folders. The **Link** column contains direct links for easy access to the respective ConvertSql files.

ConvertSql<file_number>

This file contains the existing SQL queries in the folders. To convert an SQL query, specify the converted query in the **CONVERTED_SQL** column.

Configuring the SQL conversion files

Configure the SQL conversion configuration files to generate converted SQL queries for the target endpoint.

1. Open the assessment output ZIP file and extract the content.
2. Go to the **TEMPLATES** > **SqlQueries** folder and open the `MasterSql.xlsx` file.
3. Select the folder that contains the SQL queries and click the link to open the ConvertSql file.
4. Enter the converted query for the target endpoint in the CONVERTED_SQL column.
5. Save the file.

Use the ConvertSql file to create a properties conversion configuration. Conversion tasks use the configuration to generate converted queries for the target endpoints.

Note: You must enter an advanced property to use the ConvertSql files in the properties conversion configuration. For more information, contact Informatica Global Customer Support.

Creating a connection map configuration

Create a Connection Map configuration to map the PowerCenter connections to IDMC connections.

The Connection Map configuration is associated with a domain and a repository. This configuration contains connection types and connection names used in the assessed repository. If you want to repoint the assets to a new endpoint, map these connections to relevant IDMC connections.

The following video shows you how to create a connection map configuration:



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.
2. Click **Configuration**, and then click **Create**.

   The **New Configuration** page appears.
3. From the **Configuration Type** list, select **Connection Map**.

4. Enter the required information as shown in the following table:

Property	Description
Configuration Name	Name of the configuration.
Description	(Optional) Description of the configuration.
Domain	The domain where you want to use this configuration. The list of repositories within the selected domain appears in the **Repository** field.
Repository Type	The type of repository where you want to use this configuration.
Repository	The repository where you want to use this configuration. **Important:** The selected repository must be assessed to create the configuration.

5. Click **Next**.

   On the **Set Properties** tab, the **Connection Map Configuration** section displays the list of connections used in the repository. You can filter the connections based on a connection type.

6. In the **Cloud Connection Type** and **Cloud Connection Name** columns, select the IDMC connection type and connection name of the endpoint to which you want to repoint the assets.

7. In the **Transformation** column, select the transformations where you want to use this repoint.

   You can use the following transformations for a repoint:

   - Source
   - Target
   - Lookup Transformation
   - SQL Transformation
   - Stored Procedure Transformation

8. If you want to configure additional properties for the repoint, click **Set Properties** in the **Advanced Properties** column.

9. Click **Save Configuration**.

   The configuration is saved. You can use this configuration in conversion tasks.

Advanced properties

If you are repointing your assets to another endpoint, you can configure additional properties in the Connection Map configuration.

Based on the IDMC connection that you choose for repoint, you can configure the properties specific to that connection.

Amazon Redshift advanced properties

The following tables lists the Amazon Redshift properties that you can configure for a **Connection Map configuration**:

Object properties

The following table describes the Amazon Redshift connection properties:

Connection property	Description
Schema	The Amazon Redshift schema name to be used when creating the object. Th schema name is similar to the schema name specified in the `SCHEMAMAP.properties` file. Default is `schema_changeit`.

Source advanced properties

The following table describes the Amazon Redshift source advanced properties:

Property name	Description
Schema Name	Overrides the default schema name.
S3 Bucket Name	Amazon S3 bucket name for staging the data. You can also specify the bucket name with the folder path. If you provide an Amazon S3 bucket name that is in a different region than the Amazon Redshift cluster, you must configure the REGION attribute in the Unload command options.
Read Mode	Specifies the read mode to read data from the Amazon Redshift source. You can specify one of the following read modes: - *Direct*: Reads data directly from the Amazon Redshift source without staging the data in Amazon S3. - *Staging*: Reads data from the Amazon Redshift source by staging the data in the S3 bucket. Default is *Staging*.
Fetch Size	Determines the number of rows to read in one resultant set from Amazon Redshift. Applies only when you select the **Direct** read mode. Default is *10000*.
Enable Compression	Compresses the staging files into the Amazon S3 staging directory. The task performance improves when the Secure Agent compresses the staging files. Default is enabled.
Staging Directory Location	Location of the local staging directory. When you run a task in the Secure Agent runtime environment, specify a directory path that is available on the corresponding Secure Agent machine in the runtime environment. For example, `C:\Temp`. Ensure that you have the write permissions to the directory.

Property name	Description
Unload Options	Unload command options. Enter the options to the Unload command to extract data from Amazon Redshift and create staging files on Amazon S3. You can enter the following unload options: - DELIMITER - ESCAPE - PARALLEL - NULL - AWS_IAM_ROLE - REGION - ADDQUOTES For example: `DELIMITER = \036;ESCAPE = OFF;NULL=text;PARALLEL = ON;AWS_IAM_ROLE=arn;aws;iam;;<account ID>;role/<role-name>;REGION = ap-south-1` For the AWS_IAM_ROLE option, provide the Amazon Resource Name (ARN) of an Amazon Redshift Role. Also, specify a directory on the machine that hosts the Secure Agent.
Temporary Credential Duration	The time duration during which an IAM user can use the dynamically generated temporarily credentials to access the AWS resource. Enter the time duration in seconds. Default is 900 seconds. If you require more than 900 seconds, you can set the time duration up to a maximum of 12 hours in the AWS console and then enter the same time duration in this property.
Treat NULL Value as NULL	Retains the null values when you read data from Amazon Redshift.
Encryption Type	Encrypts the data in the Amazon S3 staging directory. You can specify the following encryption types: - None - SSE-S3 - SSE-KMS - CSE-SMK Default is None.
Download S3 Files In Multiple Parts	Downloads large Amazon S3 objects in multiple parts. When the file size of an Amazon S3 object is greater than 8 MB, you can choose to download the object in multiple parts in parallel. Default is 5 MB.
Multipart Download Threshold Size	The maximum threshold size to download an Amazon S3 object in multiple parts. Default is 5 MB.

Target advanced properties

The following table describes the Amazon Redshift target advanced properties:

Property	Description
S3 Bucket Name	Amazon S3 bucket name for writing the files to Amazon Redshift target. You can also specify the bucket name with the folder path. If you provide an Amazon S3 bucket name that is in a different region than the Amazon Redshift cluster, you must configure the **REGION** attribute in the *Copy Options* property.
Enable Compression	Compresses the staging files before writing the files to Amazon Redshift. The task performance improves when the Secure Agent compresses the staged files. Default is enabled.
Staging Directory Location	Location of the local staging directory. When you run a task in Secure Agent runtime environment specify a directory path that is available on the corresponding Secure Agent machine in the runtime environment. For example, `C:\Temp`. Ensure that you have the write permissions on the directory.
Batch Size	Minimum number of rows in a batch. Enter a number greater than 0. Default is 2000000.
Max Errors per Upload Batch for INSERT	Number of error rows that causes an upload insert batch to fail. Enter a positive integer. Default is 1. If the number of errors is equal to or greater than the property value, the Secure Agent writes the entire batch to the error file.
Require Null Value For Char and Varchar	Replaces the string value with NULL when you write data to Amazon Redshift columns of Char and Varchar data types. Default is an empty string. **Note:** When you run a mapping to write null values to a table that contains a single column of the Int, Bigint, numeric, real, or double data type, the mapping fails. You must provide a value other than the default value in the **Require Null Value For Char And Varchar** property.
WaitTime In Seconds For S3 File Consistency	Number of seconds to wait for the Secure Agent to make the staged files consistent with the list of files available on Amazon S3. Default is 0.

Property	Description
Copy Options	Copy command options. Enter the options to the Copy command to write data from Amazon S3 to the Amazon Redshift target when the default delimiter comma (,) or double-quote (") is used in the data. Provide the Amazon Redshift Role Amazon Resource Name (ARN). You can add the following options: - DELIMITER - ACCEPTINVCHARS - QUOTE - COMPUPDATE - AWS_IAM_ROLE - REGION For example: `DELIMITER = \036;ACCEPTINVCHARS = #;QUOTE = \037 COMPUPDATE = ON;AWS_IAM_ROLE=arn:aws:iam::<account ID>:role/<role-name>;REGION = ap-south-1` Specify a directory on the machine that hosts the Secure Agent. **Note:** If you do not add the options to the Copy command manually, the Secure Agent uses the default values.
S3 Server Side Encryption	Indicates that Amazon S3 encrypts data during upload. Provide a customer master key ID in the connection property to enable this property. Default is not selected.
S3 Client Side Encryption	Indicates that the Secure Agent encrypts data using a private key. Provide a master symmetric key ID in the connection property to enable this property. If you enable both server-side and client-side encryptions, the Secure Agent ignores the server-side encryption.
Analyze Target Table	Runs an ANALYZE command on the target table. The query planner on Amazon Redshift updates the statistical metadata to build and choose optimal plans to improve the efficiency of queries.
Vacuum Target Table	Recovers disk space and sorts the row in a specified table or all tables in the database. You can select the following recovery options: - None - Full - Sort Only - Delete Only - Reindex Default is None.
Prefix to retain staging files on S3	Retains staging files on Amazon S3. Provide both a directory prefix and a file prefix separated by a slash (/) or only a file prefix to retain staging files on Amazon S3. For example, `backup_dir/backup_file` or `backup_file`.
Success File Directory	Directory for the Amazon Redshift success file. Specify a directory on the machine that hosts the Secure Agent.
Error File Directory	Directory for the Amazon Redshift error file. Specify a directory on the machine that hosts the Secure Agent.

Property	Description
Transfer Manager Thread Pool Size	Number of threads to write data in parallel. Default is 10.
Preserve record order on write	Retains the order of the records when you read data from a CDC source and write data to an Amazon Redshift target. Use this property when you create a mapping to capture the changed record from a CDC source. This property enables you to avoid inconsistencies between the CDC source and target.
Minimum Upload Part Size	Minimum size of the Amazon Redshift object to upload an object. Default is 5 MB.
Number of files per batch	Calculates the number of the staging files per batch. If you do not provide the number of files, Amazon Redshift V2 Connector calculates the number of the staging files. When you connect to Amazon Redshift serverless and do not provide the number of files, 20 files per batch is considered as the default value.
Schema Name	Overrides the default schema name.
Recovery Schema Name	Schema that contains recovery information stored in the `infa_recovery_table` table on the target system to resume the extraction of the changed data from the last checkpoint.
Temporary Credential Duration	The time duration during which an IAM user can use the dynamically generated temporarily credentials to access the AWS resource. Enter the time duration in seconds. Default is 900 seconds. If you require more than 900 seconds, you can set the time duration maximum up to 12 hours in the AWS console and then enter the same time duration in this property.

Lookup advanced properties

The following table describes the Amazon Redshift lookup transformation advanced properties:

Property	Description
Read Mode	Specifies the read mode to read data from the Amazon Redshift source. You can specify one of the following read modes: - *Direct*: Reads data directly from the Amazon Redshift source without staging the data in Amazon S3. - *Staging*: Reads data from the Amazon Redshift source by staging the data in the S3 bucket. Default is *Staging*.
Fetch Size	Determines the number of rows to read in one resultant set from Amazon Redshift. Applies only when you select the **Direct** read mode. Default is *10000*.
S3 Bucket Name	Amazon S3 bucket name for staging the data. You can also specify the bucket name with the folder path. If you provide an Amazon S3 bucket name that is in a different region than the Amazon Redshift cluster, you must configure the **REGION** attribute in the Unload command options.

Property	Description
Enable Compression	Compresses the staging files into the Amazon S3 staging directory. The task performance improves when the Secure Agent compresses the staging files. Default is selected.
Staging Directory Location	Location of the local staging directory. When you run a task in Secure Agent runtime environment, specify a directory path that is available on the corresponding Secure Agent machine in the runtime environment. Specify the directory path in the following manner: `<staging directory>` For example, `C:\Temp`. Ensure that you have the write permissions on the directory.
Unload Options	Unload command options. Add options to the Unload command to extract data from Amazon Redshift and create staging files on Amazon S3. Provide an Amazon Redshift Role Amazon Resource Name (ARN). You can add the following options: - DELIMITER - ESCAPE - PARALLEL - NULL - AWS_IAM_ROLE - REGION - ADDQUOTES For example: DELIMITER = \036;ESCAPE = OFF;NULL=text;PARALLEL = ON;AWS_IAM_ROLE=arn;aws;iam;;<account ID>;role/<role-name>;REGION = ap-south-1 Specify a directory on the machine that hosts the Secure Agent. **Note:** If you do not add the options to the Unload command manually, the Secure Agent uses the default values.
Treat NULL Value as NULL	Retains the null values when you read data from Amazon Redshift.
Encryption Type	Encrypts the data in the Amazon S3 staging directory. You can select the following encryption types: - None - SSE-S3 - SSE-KMS - CSE-SMK Default is None.
Download S3 Files in Multiple Parts	Downloads large Amazon S3 objects in multiple parts. When the file size of an Amazon S3 object is greater than 8 MB, you can choose to download the object in multiple parts in parallel. Default is 5 MB.
Multipart Download Threshold Size	The maximum threshold size to download an Amazon S3 object in multiple parts. Default is 5 MB.

Property	Description
Schema Name	Overrides the default schema name. **Note:** You cannot configure a custom query when you use the schema name.
Temporary Credential Duration	The time duration during which an IAM user can use the dynamically generated temporarily credentials to access the AWS resource. Enter the time duration in seconds. Default is 900 seconds. If you require more than 900 seconds, you can set the time duration up to a maximum of 12 hours in the AWS console and then enter the same time duration in this property.

Databricks Delta advanced properties

The following tables lists the Databricks Delta properties that you can configure for a **Connection Map configuration**:

Object properties

The following table describes the Databricks Delta connection properties:

Connection property	Description
Schema	The Databricks Delta schema name to be used when creating the object. Th schema name is similar to the schema name specified in the `SCHEMAMAP.properties` file. Default is `schema_changeit`.

Source advanced properties

The following table describes the Databricks Delta source advanced properties:

Property name	Description
Schema Name	Overrides the schema specified in the connection. Default is `$$dbd_schema`.
Staging Location	Relative directory path to store the staging files. If the Databricks cluster is deployed on AWS, use the path relative to the Amazon S3 staging bucket. If the Databricks cluster is deployed on Azure, use the path relative to the Azure Data Lake Store Gen2 staging filesystem name. Default is `$$dbd_staging_loc`.
Database Name	Overrides the database name provided in connection and the database name provided during metadata import. **Note:** To read from multiple objects ensure that you have specified the database name in the connection properties.
Job Timeout	Maximum time in seconds that is taken by the Spark job to complete processing. If the job is not completed within the time specified, the Databricks cluster terminates the job and the mapping fails. If the job timeout is not specified, the mapping shows success or failure based on the job completion.

Property name	Description
Job Status Poll Interval	Poll interval in seconds at which the Secure Agent checks the status of the job completion. Default is 30 seconds.
DB REST API Timeout	The Maximum time in seconds for which the Secure Agent retries the REST API calls to Databricks when there is an error due to network connection or if the REST endpoint returns `5xx HTTP` error code. Default is 10 minutes.
DB REST API Retry Interval	The time Interval in seconds at which the Secure Agent must retry the REST API call, when there is an error due to network connection or when the REST endpoint returns `5xx HTTP` error code. This value does not apply to the Job status REST API. Use job status poll interval value for the Job status REST API. Default is 30 seconds.

Target advanced properties

The following table describes the Databricks Delta target advanced properties:

Property Name	Description
Schema Name	Overrides the schema specified in the connection. Default is `$$dbd_schema`.
Staging Location	Relative directory path to store the staging files. If the Databricks cluster is deployed on AWS, use the path relative to the Amazon S3 staging bucket. If the Databricks cluster is deployed on Azure, use the path relative to the Azure Data Lake Store Gen2 staging filesystem name. Default is `$$dbd_staging_loc`.
Target Database Name	Overrides the database name provided in the connection and the database selected in the metadata browser for existing targets.
Write Disposition	Overwrites or adds data to the existing data in a table. You can select from the following options: - Append. Appends data to the existing data in the table even if the table is empty. - Truncate. Overwrites the existing data in the table. Only applies to Insert operation and non-empty sources. - Truncate Always. Overwrites the existing data in the table. Applies to insert, update, upsert, and delete target operations for empty and non-empty sources.
DTM Staging File Size	The size of the flat file that Data Integration creates locally in a temporary folder to stage the data before writing to Databrick. Default is 50 MB.
Job Timeout	Maximum time in seconds that is taken by the Spark job to complete processing. If the job is not completed within the time specified, the job terminates and the mapping fails. If the job timeout is not specified, the mapping shows success or failure based on the job completion.
Job Status Poll Interval	Poll interval in seconds at which the Secure Agent checks the status of the job completion. Default is 30 seconds.

Property Name	Description
DB REST API Timeout	The Maximum time in seconds for which the Secure Agent retries the REST API calls to Databricks when there is an error due to network connection or if the REST endpoint returns `5xx HTTP` error code. Default is 10 minutes.
DB REST API Retry	The time Interval in seconds at which the Secure Agent must retry the REST API call, when there is an error due to network connection or when the REST endpoint returns `5xx HTTP` error code. This value does not apply to the Job status REST API. Use job status poll interval value for the Job status REST API. Default is 30 seconds.

Lookup advanced properties

The following table describes the Databricks Delta lookup transformation advanced properties:

Property Name	Description
Schema Name	Overrides the schema specified in the connection. Default is `$$dbd_schema`.
Staging Location	Relative directory path to store the staging files. If the Databricks cluster is deployed on AWS, use the path relative to the Amazon S3 staging bucket. If the Databricks cluster is deployed on Azure, use the path relative to the Azure Data Lake Store Gen2 staging filesystem name. Default is `$$dbd_staging_loc`.
Database Name	Overrides the database specified in the connection.
Job Timeout	Maximum time in seconds that is taken by the Spark job to complete processing. If the job is not completed within the time specified, the Databricks cluster terminates the job and the mapping fails. If the job timeout is not specified, the mapping shows success or failure based on the job completion.
Job Status Poll Interval	Poll interval in seconds at which the Secure Agent checks the status of the job completion. Default is 30 seconds.
DB REST API Timeout	The Maximum time in seconds for which the Secure Agent retries the REST API calls to Databricks when there is an error due to network connection or if the REST endpoint returns `5xx HTTP` error code. Default is 10 minutes.
DB REST API Retry Interval	The time Interval in seconds at which the Secure Agent must retry the REST API call, when there is an error due to network connection or when the REST endpoint returns `5xx HTTP` error code. This value does not apply to the Job status REST API. Use job status poll interval value for the Job status REST API. Default is 30 seconds.

Google BigQuery advanced properties

The following tables lists the Google BigQuery properties that you can configure for a **Connection Map configuration**:

Object properties

The following table describes the Google BigQuery connection properties:

Connection property	Description
Source Dataset ID	Name of the dataset that contains the source table and target table that you want to connect to. Default is `datasetID_changeit`. **Note:** Google BigQuery supports the datasets that reside only in the US region.

Source advanced properties

The following table describes the Google BigQuery source advanced properties:

Property name	Description
Source Dataset ID	Overrides the Google BigQuery dataset name that you specified in the connection. Default is `$$sf_database`.
Source Staging Dataset	Overrides the Google BigQuery staging dataset name that you specified in the connection and the Source Dataset ID source advanced property.
Number of Rows to Read	Specifies the number of rows to read from the Google BigQuery source table.
Job Poll Interval In Seconds	The number of seconds after which Google BigQuery Connector polls the status of the read job operation. Default is 10.
Read Mode	Specifies the read mode to read data from the Google BigQuery source. You can select one the following read modes: - Direct. In direct mode, Google BigQuery Connector reads data directly from the Google BigQuery source table. When you use hybrid and complex connection mode, you cannot use direct mode to read data from the Google BigQuery source. - Staging. In staging mode, Google BigQuery Connector exports data from the Google BigQuery source into Google Cloud Storage. After the export is complete, Google BigQuery Connector downloads the data from Google Cloud Storage into the local stage file and then reads data from the local stage file. Default is Staging mode.
Use EXPORT DATA Statement to stage	Uses the EXPORT DATA statement to export data from Google BigQuery to Google Cloud Storage. If the query contains an ORDER BY clause, the specified order is maintained when you export the data. This property applies to staging mode. Default is false.

Property name	Description
Number of Threads for Downloading Staging Files	Specifies the number of files that Google BigQuery Connector downloads at a time to enable parallel download. This property applies to staging mode. Default is 1.
Local Stage File Directory	Specifies the directory on your local machine where Google BigQuery Connector stores the Google BigQuery source data temporarily before it reads the data. This property applies to staging mode. Default is `$PMTempDir`.
Staging File Name	Name of the staging file where data from the Google BigQuery source table is exported to Google Cloud Storage. This property applies to staging mode.
Persist Extract Staging File After Download	Indicates whether Google BigQuery V2 Connector must persist the staging file after it reads data from the staging file. By default, Google BigQuery V2 Connector deletes the staging file.
Persist Destination Table	Indicates whether Google BigQuery V2 Connector must persist the query results table after it reads data from the query results table. By default, Google BigQuery V2 Connector deletes the query results table.
Data format of the staging file	Specifies the data format of the staging file. You can select one of the following data formats: - JSON (Newline Delimited). Supports flat and record data with nested and repeated fields. - CSV. Supports flat data. In a .csv file, columns of the Timestamp data type are represented as floating point numbers that cause the milliseconds value to differ. Default is `JSON`.
Enable Staging File Compression	Indicates whether to compress the size of the staging file in Google Cloud Storage before Google BigQuery Connector reads data from the staging file. You can enable staging file compression to reduce cost and transfer time. This property applies to staging mode. Default is false.
Retry Options	Comma-separated list to specify the following retry options: - Retry Count. The number of retry attempts to read data from Google BigQuery. - Retry Interval. The time in seconds to wait between each retry attempt. - Retry Exceptions. The list of exceptions separated by pipe (|) character for which the retries are made. Default is `$$gbq_retry_options`.

Property name	Description

Use Legacy SQL for SQL Override	Indicates that the SQL Override query is specified in legacy SQL.
	Use the following format to specify a legacy SQL query for the **SQL Override Query** property:
	`SELECT <Col1, Col2, Col3> FROM [projectID:datasetID.tableName]`
	Clear this option to define a standard SQL override query.
	Use the following format to specify a standard SQL query for the **SQL Override Query** property:
	`SELECT * FROM` `` `projectID.datasetID.tableName` ``
	Default is false.

pre SQL Configuration	Specify a pre SQL configuration.
	For example,
	`DestinationTable:PRESQL_SRC,DestinationDataset:EMPLOYEE,`
	`FlattenResults:False,WriteDisposition:WRITE_TRUNCATE,UseLegacySql:False`

post SQL Configuration	Specify a post SQL configuration.
	For example,
	`DestinationTable:POSTSQL_SRC,DestinationDataset:EMPLOYEE,`
	`FlattenResults:True,WriteDisposition:WRITE_TRUNCATE,UseLegacySql:False`

Label	You can assign a label for the transformation to organize and filter the associated jobs in the Google Cloud Platform Log Explorer.
Billing Project ID	The project ID for the Google Cloud project that is linked to an active Google Cloud Billing account where the Secure Agent runs query and extract jobs. If you omit the project ID here, the Secure Agent runs query and extract jobs in the Google Cloud project corresponding to the **Project ID** value specified in the Google BigQuery V2 connection.
Number of Spark Partitions	Specifies the maximum number of partitions that the Spark engine splits the data into. Default is 1.

Target advanced properties

The following table describes the Google BigQuery target advanced properties:

Property name	Description
Target Dataset ID	Overrides the Google BigQuery dataset name that you specified in the connection. Default is `$$gbq_datasetID`.
Write Mode	Specifies the mode to write data to the Google BigQuery target. You can select one of the following modes: - Bulk. Google BigQuery V2 Connector first writes the data to a staging file in Google Cloud Storage. When the staging file contains all the data, Google BigQuery V2 Connector loads the data from the staging file to the BigQuery target. Google BigQuery V2 Connector then deletes the staging file unless you configure the task to persist the staging file. - Streaming. Google BigQuery V2 Connector directly writes data to the BigQuery target. Google BigQuery V2 Connector writes the data into the target row by row. - CDC. Applies only when you capture changed data from a CDC source. In CDC mode, Google BigQuery V2 Connector captures changed data from any CDC source and writes the changed data to a Google BigQuery target table. Default is Bulk mode.
Data format of the staging file	Specifies the data format of the staging file. You can select one of the following data formats: - Avro - JSON (Newline Delimited). Supports flat and record data with nested and repeated fields. - Parquet - CSV. Supports flat data. In a .csv file, columns of the Timestamp data type are represented as floating point numbers that cause the milliseconds value to differ. Only JSON format is applicable for mappings in advanced mode. This property applies to bulk and CDC mode. Avro and parquet format is not applicable when you perform a data driven operation. Default is `JSON`.
Enable Staging File Compression	Select this option to compress the size of the staging file before Google BigQuery writes the data to the Google Cloud Storage and decompress the staging file before it loads the data to the Google BigQuery target. You can enable staging file compression to reduce cost and transfer time. Default is `false`.
Local Stage File Directory	Specifies the directory on your local machine where Google BigQuery V2 Connector stores the files temporarily before writing the data to the staging file in Google Cloud Storage. This property applies to bulk mode. Default is `$PMTempDir`.
Use Default Column Values	Applicable when the selected data format for the staging file is CSV when the mapping contains unconnected ports. Includes the default column values for the unconnected port from the staging file to create the target. This is applicable when you have defined the default constraint value in the Google BigQuery source column. When you do not enable this option, the agent creates a target only with the connected ports. The agent populates null or empty strings for unconnected ports. Default is `true`.

Property name	Description
Enable Merge	Implements the Merge query to perform an update, upsert, delete or data driven operation on a Google BigQuery target table. If you select the **Enable Data Driven** property, you must select this option. Default is disabled.
Target Staging Dataset	Optional. Overrides the Google BigQuery staging dataset name that you specified in the connection and the Target Dataset ID target advanced property.
Create Disposition	Specifies whether Google BigQuery V2 Connector must create the target table if it does not exist. You can select one of the following values: - Create if needed. If the table does not exist, Google BigQuery V2 Connector creates the table. - Create never. If the table does not exist, Google BigQuery V2 Connector does not create the table and displays an error message. Create disposition is applicable only when you perform an insert operation on a Google BigQuery target.
Write Disposition	Specifies how Google BigQuery V2 Connector must write data in bulk mode if the target table already exists. You can select one of the following values: - Write append. If the target table exists, Google BigQuery V2 Connector appends the data to the existing data in the table. - Write truncate. If the target table exists, Google BigQuery V2 Connector overwrites the existing data in the table. - Write empty. If the target table exists and contains data, Google BigQuery V2 Connector displays an error and does not write the data to the target. Google BigQuery V2 Connector writes the data to the target only if the target table does not contain any data. Write disposition is applicable for bulk mode. Write disposition is applicable only when you perform an insert operation on a Google BigQuery target.
Streaming Template Table Suffix	Specify the suffix to add to the individual target tables that Google BigQuery V2 Connector creates based on the template target table. This property applies to streaming mode. If you select the Enable Merge option, Google BigQuery V2 Connector ignores this property. Streaming mode is not applicable when you perform a data driven operation.
Rows per Streaming Request	Specifies the number of rows that Google BigQuery V2 Connector streams to the BigQuery target for each request. Default is 500 rows. The maximum row size that Google BigQuery V2 Connector can stream to the Google BigQuery target for each request is 10 MB. This property applies to streaming mode. Streaming mode is not applicable when you perform a data driven operation.
Staging File Name	Name of the staging file that Google BigQuery V2 Connector creates in the Google Cloud Storage before it loads the data to the Google BigQuery target. This property applies to bulk mode.

Property name	Description
Persist Staging File After Loading	Indicates whether Google BigQuery V2 Connector must persist the staging file in the Google Cloud Storage after it writes the data to the Google BigQuery target. You can persist the staging file if you want to archive the data for future reference. By default, Google BigQuery V2 Connector deletes the staging file in Google Cloud Storage. This property applies to bulk mode.
Job Poll Interval In Seconds	The number of seconds after which Google BigQuery V2 Connector polls the status of the write job operation. Default is 10.
Number of Threads for Uploading Staging File	The number of files that Google BigQuery V2 Connector must create to upload the staging file in bulk mode.
Allow Quoted Newlines	Indicates whether Google BigQuery V2 Connector must allow the quoted data sections with newline character in a .csv file.
Field Delimiter	Indicates whether Google BigQuery V2 Connector must allow field separators for the fields in a .csv file.
Allow Jagged Rows	Indicates whether Google BigQuery V2 Connector must accept the rows without trailing columns in a .csv file.
Suppress post SQL on Error	Indicates whether the Secure Agent must abort the post-SQL query execution in case the task fails to write data to the Google BigQuery target table due to errors. Default is disabled.

pre SQL Configuration	Specify a pre-SQL configuration.
	For example,
	`DestinationTable:PRESQL_TGT2,`
	`DestinationDataset:EMPLOYEE,`
	`FlattenResults:False,`
	`WriteDisposition:WRITE_TRUNCATE,`
	`UseLegacySql:False`

post SQL Configuration	Specify a post-SQL configuration.
	For example,
	`DestinationTable:POSTSQL_SRC,`
	`DestinationDataset:EMPLOYEE,`
	`FlattenResults:True,`
	`UseLegacySQL:False`

Quote Char	Specifies the quote character to skip when you write data to Google BigQuery. When you write data to Google BigQuery and the source table contains the specified quote character, the task fails. Change the quote character value to a value that does not exist in the source table. Default is double quotes.

Property name	Description
Allow Duplicate Inserts	Indicates that the Secure Agent can insert duplicate rows into the Google BigQuery target. Applicable only when you perform a data driven operation and DD_INSERT is specified in the data driven condition. Default is not selected.
Disable Duplicate Update Rows	Determines if multiple incoming rows attempt to update the same target row, the Secure Agent must process only one of the incoming rows and ignore the rest of the incoming rows. Select this option to configure the mapping to process only one of the incoming rows and ignore the rest of the incoming rows. Default is disabled.
Label	You can assign a label for the transformation to organize and filter the associated jobs in the Google Cloud Platform Log Explorer.
Billing Project ID	The project ID for the Google Cloud project that is linked to an active Google Cloud Billing account where the Secure Agent runs query and load jobs. If you omit the project ID here, the Secure Agent runs query and load jobs in the Google Cloud project corresponding to the **Project ID** value specified in the Google BigQuery V2 connection.
Forward Rejected Rows	Applicable only when you configure DD_REJECT constant in the data driven condition to reject all the rows. Otherwise, this property is not applicable for Google BigQuery V2 Connector.

Lookup advanced properties

The following table describes the Google BigQuery lookup transformation advanced properties:

Property name	Description
Source Dataset ID	Overrides the Google BigQuery dataset name that you specified in the connection. Default is `$$gbq_datasetID`.
Source Staging Dataset	Overrides the Google BigQuery staging dataset name that you specified in the Lookup transformation.
Job Poll Interval In Seconds	The number of seconds after which Google BigQuery V2 Connector polls the status of the read job operation. Default is `10`.
Read Mode	Specifies the read mode to read data from the Google BigQuery source. You can select one the following read modes: - Direct. In direct mode, Google BigQuery V2 Connector reads data directly from the Google BigQuery source table. When you use hybrid and complex connection mode, you cannot use direct mode to read data from the Google BigQuery source. - Staging. In staging mode, Google BigQuery V2 Connector exports data from the Google BigQuery source into Google Cloud Storage. After the export is complete, Google BigQuery V2 Connector downloads the data from Google Cloud Storage into the local stage file and then reads data from the local stage file. Default is `Staging` mode.

Property name	Description
Use EXPORT DATA Statement to stage	Uses the EXPORT DATA statement to export data from Google BigQuery to Google Cloud Storage. If the query contains an ORDER BY clause, the specified order is maintained when you export the data. This property applies to staging mode. Default is `true`.
Number of Threads for Downloading Staging Files	Specifies the number of files that Google BigQuery Connector downloads at a time to enable parallel download. This property applies to staging mode. Default is `1`.
Local Stage File Directory	Specifies the directory on your local machine where Google BigQuery V2 Connector stores the Google BigQuery source data temporarily before it reads the data. This property applies to staging mode. Default is `$PMTempDir`.
Data format of the staging file	Specifies the data format of the staging file. You can select one of the following data formats: - Avro - JSON (Newline Delimited). Supports flat and record data with nested and repeated fields. - Parquet - CSV. Supports flat data. In a .csv file, columns of the Timestamp data type are represented as floating point numbers that cause the milliseconds value to differ. Only JSON format is applicable for mappings in advanced mode. This property applies to bulk and CDC mode. Avro and parquet format is not applicable when you perform a data driven operation. Default is `JSON`.
Enable Staging File Compression	Indicates whether to compress the size of the staging file in Google Cloud Storage before Google BigQuery V2 Connector reads data from the staging file. You can enable staging file compression to reduce cost and transfer time. This property applies to staging mode. Default is `false`.
Retry Options	Comma-separated list to specify the following retry options: - Retry Count. The number of retry attempts to read data from Google BigQuery. - Retry Interval. The time in seconds to wait between each retry attempt. - Retry Exceptions. The list of exceptions separated by pipe (|) character for which the retries are made. Default is `$$gbq_retry_options`.

Use Legacy SQL for SQL Override	Indicates that the SQL Override query is specified in legacy SQL.
	Use the following format to specify a legacy SQL query for the SQL Override Query property:
	`SELECT <Col1, Col2, Col3> FROM [projectID:datasetID.tableName]`
	Clear this option to define a standard SQL override query.
	Use the following format to specify a standard SQL query for the SQL Override Query property:
	`SELECT * FROM 'projectID.datasetID.tableName'`

Property name	Description
Number of Rows to Read	Specifies the number of rows to read from the Google BigQuery source table.
Staging File Name	Name of the staging file where data from the Google BigQuery source table is exported to Google Cloud Storage. This property applies to staging mode.
Persist Extract Staging File After Download	Indicates whether Google BigQuery V2 Connector must persist the staging file in the Google Cloud Storage after it writes the data to the Google BigQuery target. You can persist the staging file if you want to archive the data for future reference. By default, Google BigQuery V2 Connector deletes the staging file in Google Cloud Storage. This property applies to bulk mode.
Persist Destination Table	Indicates whether Google BigQuery V2 Connector must persist the query results table after it reads data from the query results table. By default, Google BigQuery V2 Connector deletes the query results table.

pre SQL Configuration	Specify a pre SQL configuration.
	For example,
	`DestinationTable:PRESQL_SRC,DestinationDataset:EMPLOYEE,`
	`FlattenResults:False,WriteDisposition:WRITE_TRUNCATE,UseLegacySql:False`

post SQL Configuration	Specify a post SQL configuration.
	For example,
	`DestinationTable:POSTSQL_SRC,DestinationDataset:EMPLOYEE,`
	`FlattenResults:True,WriteDisposition:WRITE_TRUNCATE,UseLegacySql:False`

Label	You can assign a label for the transformation to organize and filter the associated jobs in the Google Cloud Platform Log Explorer.
Billing Project ID	The project ID for the Google Cloud project that is linked to an active Google Cloud Billing account where the Secure Agent runs query and extract jobs. If you omit the project ID here, the Secure Agent runs query and extract jobs in the Google Cloud project corresponding to the **Project ID** value specified in the Google BigQuery V2 connection.
Number of Spark Partitions	Specifies the maximum number of partitions that the Spark engine splits the data into. Default is 1.

Microsoft Azure Synapse SQL advanced properties

The following tables lists the Microsoft Azure Synapse SQL properties that you can configure for a **Connection Map configuration**:

Object properties

The following table describes the Microsoft Azure Synapse SQL connection properties:

Connection property	Description
Schema	The Microsoft Azure Synapse SQL schema name to be used when creating the object. Th schema name is similar to the schema name specified in the `SCHEMAMAP.properties` file. Default is `schema_changeit`.

Source advanced properties

The following table describes the Microsoft Azure Synapse SQL source advanced properties:

Property	Description
Azure Blob Container Name	The name of the container in Microsoft Azure Blob Storage. The container name must not contain special characters. Default is `$$blob_container_name`.
ADLS FileSystem Name	Required if you select ADLS Gen2 storage in the connection properties. The name of the file system in Microsoft Azure Data Lake Storage Gen2. The file system name must not contain special characters. You can also specify the path of the directory under the file system. Use only a forward slash to specify the directory path. Default is `$$adls_folder_name`.
Schema Name Override	Overrides the schema specified in the connection. Default is `$$syn_schema`.
Staging File Format	Type of file format to use when you stage the files in Azure storage. Select one of the following formats: - Delimited Text - Parquet
Field Delimiter	Character used to separate fields in the file. Default is `0x1e`. You can specify 'TAB' or 0-256 single-char printable and non-printable ASCII characters. Non-printable characters must be specified in hexadecimal. **Note:** Multi-char ASCII characters except TAB are not applicable. You cannot use the following non-printable characters: `00x0`, `0x0`, `0x0A` , `0x1B`, `0x0D`, and `0x1F`
Number of Concurrent Connections to Blob Store	Number of concurrent connections to extract data from the Microsoft Azure Blob Storage. When reading a large-size blob, you can spawn multiple threads to process data. Configure **Blob Part Size** to partition a large-size blob into smaller parts. Default is 4. Maximum is 10.

Property	Description
Blob Part Size	Partitions a blob into smaller parts each of specified part size. When reading a large-size blob, consider partitioning the blob into smaller parts and configure concurrent connections to spawn required number of threads to process data in parallel. Default is 8 MB.
On Pre-Post SQL Error	Determines the behavior when a task that includes pre-SQL or post-SQL commands encounters errors. Select one of the following options: - Continue. The task continues regardless of errors. - Stop. The task stops when errors occur while executing pre-SQL or post-SQL commands.
Quote Character	Specifies the quote character to skip when you read data from Microsoft Azure Synapse SQL. The quote character that you specify must not exist in the source table. If it exists, enter a different quote character value. Default is `0x1f`.
Interim Directory	Optional. Path to the staging directory in the Secure Agent machine. Specify the staging directory where you want to stage the files when you read data from Microsoft Azure SQL Data Warehouse. Ensure that the directory has sufficient space and you have read permissions to the directory. Default staging directory is `/tmp`. You cannot specify an interim directory when you use the Hosted Agent.

Target advanced properties

The following table describes the Microsoft Azure Synapse SQL target advanced properties:

Advanced Property	Description
Azure Blob Container Name	The name of the container in Microsoft Azure Blob Storage. The container name must not contain special characters. Default is `$$blob_container_name`.
ADLS FileSystem Name	Required if you select ADLS Gen2 storage in the connection properties. The name of the file system in Microsoft Azure Data Lake Storage Gen2. The file system name must not contain special characters. You can also specify the path of the directory under the file system. Use only a forward slash to specify the directory path. Default is `$$adls_folder_name`.
Copy Method	The method to load data from the staging location to Microsoft Azure Synapse SQL. Select one of the following options: - Polybase - Copy Command Default is Polybase.

Advanced Property	Description
Copy Command Options	Options for the copy command in key=value format. Specify each option on a new line.
Schema Name Override	Overrides the schema specified in the connection. Default is `$$syn_schema`.
Staging File Format	Type of file format to use when you stage the files in Azure storage. Select one of the following formats: - Delimited Text - Parquet
Field Delimiter	Character used to separate fields in the file. Default is `0x1e`. You can specify 'TAB' or 0-256 single-char printable and non-printable ASCII characters. Non-printable characters must be specified in hexadecimal. **Note:** Multi-char ASCII characters except TAB are not applicable. You cannot use the following non-printable characters: `00x0`, `0x0`, `0x0A` , `0x1B`, `0x0D`, and `0x1F`
Number of Concurrent Connections to Blob Storage	Number of concurrent connections to extract data from the Microsoft Azure Blob Storage. When reading a large-size blob, you can spawn multiple threads to process data. Default is 4. Maximum is 10.
On Pre-Post SQL Error	Determines the behavior when a task that includes pre-SQL or post-SQL commands encounters errors. You can select any of the following options: - Continue. The task continues regardless of errors. - Stop. The task stops when errors occur while executing pre-SQL or post-SQL commands.
Batch Size	Minimum number of rows in a batch. Enter a number greater than 0. Default is 2000000.
Reject Threshold	Number of errors within a batch that causes a batch to fail. Enter a positive integer. If the number of errors is equal to or greater than the property value, the Secure Agent rejects the entire batch to the error file and marks the session failed. **Note:** When you do not set the reject threshold, the mapping fails when an error is encountered.
Quote Character	Specifies the quote character to skip when you write data to Microsoft Azure Synapse SQL. The quote character that you specify must not exist in the source table. If it exists, enter a different quote character value.
Compression Format	Compresses the staging files in the `.Gzip` format. Default is None.
Interim Directory	Optional. Path to the staging directory in the Secure Agent machine. Specify the staging directory where you want to stage the files when you write data to Microsoft Azure Synapse SQL. Ensure that the directory has sufficient space and you have write permissions to the directory. Default staging directory is `/tmp`. You cannot specify an interim directory when you use the Hosted Agent.

Lookup advanced properties

The following table describes the Microsoft Azure Synapse SQL lookup transformation advanced properties:

Property name	Description
Schema Name Override	Overrides the schema specified in the connection. Default is `$$syn_schema`.
Azure Blob Container Name	The name of the container in Microsoft Azure Blob Storage. The container name must not contain special characters. Default is `$$blob_container_name`.
ADLS FileSystem Name	Required if you select ADLS Gen2 storage in the connection properties. The name of the file system in Microsoft Azure Data Lake Storage Gen2. The file system name must not contain special characters. You can also specify the path of the directory under the file system. Use only a forward slash to specify the directory path. Default is `$$adls_folder_name`.
Staging File Format	Type of file format to use when you stage the files in Azure storage. Select one of the following formats: - Delimited Text - Parquet
Field Delimiter	Character used to separate fields in the file. Default is `0x1e`. You can specify 'TAB' or 0-256 single-char printable and non-printable ASCII characters. Non-printable characters must be specified in hexadecimal. **Note:** Multi-char ASCII characters except TAB are not applicable. You cannot use the following non-printable characters: `00x0`, `0x0`, `0x0A` , `0x1B`, `0x0D`, and `0x1F`
Number of concurrent connections to Blob Store	Number of concurrent connections to extract data from the Microsoft Azure Blob Storage. When reading a large-size blob, you can spawn multiple threads to process data. Configure **Blob Part Size** to partition a large-size blob into smaller parts. Default is 4. Maximum is 10.
Blob Part Size	Partitions a blob into smaller parts each of specified part size. When reading a large-size blob, consider partitioning the blob into smaller parts and configure concurrent connections to spawn required number of threads to process data in parallel. Default is 8 MB.
On Pre-Post SQL Error	Determines the behavior when a task that includes pre-SQL or post-SQL commands encounters errors. You can select any of the following options: - Continue. The task continues regardless of errors. - Stop. The task stops when errors occur while executing pre-SQL or post-SQL commands.
Quote Character	The Secure Agent skips the specified character when you read data from Microsoft Azure SQL Data Warehouse. Default is `0x1f`.
Interim Directory	Optional. Path to the staging directory in the Secure Agent machine. Specify the staging directory where you want to stage the files when you read data from Microsoft Azure SQL Data Warehouse. Ensure that the directory has sufficient space and you have write permissions to the directory. Default staging directory is `/tmp`. You cannot specify an interim directory when you use the Hosted Agent.

PostgreSQL advanced properties

The following tables lists the PostgreSQL properties that you can configure for a **Connection Map configuration**:

Object properties

The following table describes the PostgreSQL connection properties:

Connection property	Description
Schema	The PostgreSQL schema name to be used when creating the object. Th schema name is similar to the schema name specified in the `SCHEMAMAP.properties` file. Default is `schema_changeit`.

Source advanced properties

The following table describes the PostgreSQL source advanced properties:

Property name	Description
Schema Name	Overrides the schema name of the source object. Default is `$$pg_schema`.

Target advanced properties

The following table describes the PostgreSQL target advanced properties:

Property name	Description
Schema Name	Overrides the schema name of the target object. Default is `$$pg_schema`.

Lookup advanced properties

The following table describes the PostgreSQL lookup transformation advanced properties:

Property name	Description
Schema Name	Overrides the schema name of the lookup object. Default is `$$pg_schema`.

Snowflake advanced properties

The following tables lists the Snowflake properties that you can configure for a **Connection Map configuration**:

Object properties

The following table describes the Snowflake connection properties:

Connection property	Description
Database	The Snowflake database name to be used when creating the object. The database name similar to the database name specified in the `DATABASEMAP.properties` file. Default is `dbname_changeit`.
Schema	The Snowflake schema name to be used when creating the object. Th schema name is similar to the schema name specified in the `SCHEMAMAP.properties` file. Default is `schema_changeit`.

Note: Specify the parameters in the following format: `<database name>/<schema name>` You must specify both the database and schema name. If you specify only the database name, source objects do not appear in the Select Source Object window. If you specify only the schema name, an `Invalid Schema` exception occurs while reading data.

Source advanced properties

The following table describes the Snowflake source advanced properties:

Property name	Description
Database	Overrides the database specified in the connection. Default is `$$sf_database`.
Schema	Overrides the schema specified in the connection. Default is `$$sf_schema`.
Warehouse	Overrides the Snowflake warehouse name specified in the connection.
Role	Overrides the Snowflake role assigned to user you specified in the connection.

Target advanced properties

The following table describes the Snowflake target advanced properties:

Property Name	Description
Database	Overrides the database that you used to import the object. Default is `$$sf_database`.
Schema	Overrides the schema that you used to import the object. Default is `$$sf_schema`.

Property Name	Description
Warehouse	Overrides the Snowflake name specified in the connection. The warehouse name in the mapping overrides the warehouse name you specify in the connection.
Role	Overrides the Snowflake role assigned to the user specified in the connection.
Batch Row Size	The number of rows written to a single file in the agent location. When the number of rows written to the file reaches the value specified, the agent flushes the data queue and starts processing the write commands.
Number of local staging files	The number of files that represents a single batch of data. The default number of files considered is 64. After the agent uploads the specified number of local staging files to the Snowflake user stage, Snowflake unloads the data to the target table.
Additional Write Runtime Parameters	The additional runtime parameters that you can use when you write to Snowflake. You can enter multiple write runtime parameters, separated by ampersand (&).
Rejected File Path	The filename and path of the file on the agent machine where you want to write the rejected records. For example, `\rejectedfiles\reject7`
Forward Rejected Rows	Determines whether the transformation passes rejected rows to the next transformation or drops rejected rows. By default, the agent forwards rejected rows to the next transformation.

Lookup advanced properties

The following table describes the Snowflake lookup transformation advanced properties:

Property Name	Description
Database	Overrides the database specified in the connection. Default is `$$sf_database`.
Schema	Overrides the schema specified in the connection. Default is `$$sf_schema`.
Warehouse	Overrides the Snowflake warehouse name specified in the connection.
Role	Overrides the Snowflake role assigned to user you specified in the connection.

Creating a conversion properties configuration

Create a Conversion Properties configuration if you want to override the default conversion behavior of PowerCenter assets.

The Conversion Properties configuration contains the basic and advanced conversion properties. You can configure these properties to override the default conversion behavior of PowerCenter and Data Engineering Integration assets.

The following video shows you how to create a conversion properties configuration:



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.
2. Click **Configuration**, and then click **Create**.

   The **New Configuration** page appears.
3. From the **Configuration Type** list, select **Conversion Properties**.
4. Enter the required information as shown in the following table:

Property	Description
Configuration Name	Name of the configuration.
Description	(Optional) Description of the configuration.
Domain	The domain where you want to use this configuration.

5. Click **Next**.

   The **Basic Properties** tab appears.
6. Configure the required properties.

   The following table contains the list of basic properties that you can configure:

Property	Default value	Description
Preprocessor File Location	-	Location of the XML Pre-processor file that contains additional attributes for the conversion process, such as names for duplicate worklets, session level attributes, and connection sub types. For information about configuring this file, see the "Configuring the XML Pre-processor file" on page 52 topic.
Skip Session Log File Name	True	Determines whether you want to skip the conversion of the SessionLogFileName property based on the value specified in the `PC.xml` file.
Append Run ID to Session Log File Name	False	Determines whether you want to append the SessionLogFileName property to the run ID. If you enable the property, it takes precedence over the `Skip Session Log File Name` property.
Treat Null as Zero	False	Determines whether you want to set the default value as 0 for all numeric aggregators.
Enable High Precision	False	Determines whether you want to enable high precision for decimal data types.

Property	Default value	Description
Retain Direct Connections	False	Determines whether you want to convert the transformations that have a direct connection in PowerCenter to a direct connection in IDMC.
Reuse Dependent Assets	True	Reuse existing dependent assets while publishing converted assets instead of overwriting the assets. **Note:** Global assets, such as User-Defined Functions (UDFs), are always reused irrespective of the Reuse Dependent Assets property value.

7. (Optional) To configure additional properties, click **Next**.

   The **Advanced Properties** tab appears.

8. Click **+** and configure the advanced properties as required.

   Contact Informatica Global Customer Support for the list of supported advanced properties.

   Note: Informatica recommends that you consult the Informatica Global Customer Support team before you configure the advanced properties.

9. Click **Save Configuration**.

   You can use this configuration in conversion tasks.

Creating a parameter file conversion task

Create a parameter file conversion task to convert PowerCenter parameter files to Cloud Data Integration parameter files.

Before you create a parameter file conversion task, make sure that all the necessary permissions are assigned to your role. For information on assigning the required permissions, see the *Asset Permissions* topic.

The following video shows you how to create a parameter file conversion task:



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.

2. Click **Parameter File Conversion Task**, and then click **Create**.

   The **New Parameter File Conversion Task** page appears.
   Parameter file conversion tasks are not associated with a repository or domain.

3. Enter the required information as shown in the following table:

Property	Description
Task Name	Name of the parameter file conversion task.
Description	(Optional) Description of the conversion task.
Task Location	Click **Browse**, and select the project or folder location where you want to create the parameter file conversion task.
Project Name	The Data Integration project name that you want to append to the CDI parameter file. The parameter scopes inside a CDI parameter file start with a project name. The selected project name will be appended to the parameter scopes inside the CDI parameter file.
Runtime Environment	The name of the runtime environment where you want to run the task.
PowerCenter Parameter File Location	Location of the PowerCenter parameter file that you want to convert. Make sure that the location is accessible from the Secure Agent. The location must contain the file name and extension (.ZIP). Make sure that the Secure Agent user has read, write, and execute access to this location and the ZIP file contains the PowerCenter parameter files.
Conversion Input File Location	Location of the conversion input file. The conversion input file template is available in the following location: `downloads/package-PC2CDIModernizationApp.<latest_version>/package/templates/ParameterFileConversionInput.xlsx` Configure this file to map the PowerCenter parameter and connection names to the Data Integration parameter and connection names. Save the template in a shared directory which is accessible from the Secure Agent.

4. Click **Validate Locations**.

   On successful validation, you can save the task.

5. Do one of the following:

   - Click **Save and Close** to save the parameter file conversion task.
   - Click **Save and Run** to save the parameter file conversion task and run it immediately.

   The parameter file conversion task is created. You can view the list of conversion tasks in the **Explore** > **All Tasks** page. Use the **Type** filter to filter and view all the available conversion tasks.

   Note: A parameter file is a list of parameters and variables and their associated values. These values define properties for PowerCenter mappings, mapplets, sessions, and workflows. The conversion task applies these values when you run a mapping that uses the parameter file.

Creating an asset conversion task

Create an asset conversion task to convert the assets of a PowerCenter or Model repository to Data Integration.

Creating an asset conversion task for PowerCenter assets

Create an asset conversion task to convert the assets of a PowerCenter repository to Data Integration.

The following video shows you how to create an asset conversion task for PowerCenter assets:



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.

2. Click **Asset Conversion Task**, and then click **Create**.

   The **Conversion Task** page appears.
   Alternatively, click the action menu of the repository to create or run a conversion task, and click **Convert Assets**.

   Note: You can only convert the workflows whose assessment result is Automated or Partial. For the workflows whose assessment result is Manual, you need to convert them manually.

3. Enter the required information as shown in the following table:

Property	Description
Name of the task	Name of the asset conversion task.
Conversion Task Location	Click **Browse** and select the project or folder where you want to create the conversion task asset definition. **Note:** Make sure that you have write access to the specified location.
Runtime Environment	The runtime environment that you want to use for creating the default connections during the conversion process.
Description	(Optional) Description of the conversion task.
Domain	The domain that contains the repository to be converted. From the **Domain** list, select the domain where you want to use this configuration.
Repository	Repository to be converted. Select the repository where you want to use this configuration. **Note:** Make sure that the selected repository is assessed.
Conversion Properties Configuration	Conversion properties configuration that you want to use for the task. If you want to override the default conversion behavior of PowerCenter assets, select the required conversion properties configuration.
Connection Map Configuration	Connection map configuration that you want to use for the task. If you want to repoint the PowerCenter assets to another endpoint, select the required connection map configuration. You can also provide connection map and the parameter files in the ZIP format. If a connection exists in the parameter ZIP file, the existing connection will be reused.

4. Click **Next**.

   The **Select Folder** tab displays the list of folders available in the selected repository.

5. Click the folder name that contains the assets you want to convert, and click **Next**.

   The **Select Workflows** tab displays the list of workflows available inside the folder.

6. Click **Next**.

   The list of workflows that are added to the conversion task appears.

7. Verify the workflows.

   If required, you can select and remove a workflow.

8. Do one of the following:

   - Click **Save and Close** to save the conversion task.
   - Click **Save and Run** to save the conversion task and run it immediately.

   The conversion task is created. You can view the list of conversion tasks in the **Explore** > **All Tasks** page. Use the **Type** filter to filter and view all the available conversion tasks.

Creating an asset conversion task for Data Engineering Integration assets

Create an asset conversion task to convert the mapping and workflow assets of a Model repository to Data Integration.

Ensure that the Model repository of the assets that you want to convert is assessed.

You can only convert the mapping and workflow assets whose assessment result is Automated or Partial. For the assets whose assessment result is Manual, you must convert them manually.



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.

2. Click **Asset Conversion Task**, and then click **Create**.

   The **Conversion Task** page appears.
   Alternatively, click the action menu of the repository to create or run a conversion task, and click **Convert Assets**.

3. Enter the required information as shown in the following table:

Property	Description
Task Name	Name of the asset conversion task.
Conversion Task Location	Click **Browse** and select the project or folder where you want to create the conversion task asset definition. **Note:** Make sure that you have write access to the specified location.

Property	Description
Runtime Environment	The runtime environment that you want to use for creating the default connections during the conversion process.
Description	(Optional) Description of the conversion task.
Domain	The domain that contains the repository to be converted. From the **Domain** list, select the domain where you want to use this configuration.
Repository Type	The type of repository.
Repository	Repository to be converted. Select the repository where you want to use this configuration.
Conversion Properties Configuration	Conversion properties configuration that you want to use for the task. If you want to override the default conversion behavior of Data Engineering Integration assets, select the required conversion properties configuration.
Connection Map Configuration	Connection map configuration that you want to use for the task. If you want to repoint the Data Engineering Integration assets to another endpoint, select the required connection map configuration.

4. Click **Next**.

   The **Select Project** tab displays the list of projects available in the selected repository.
5. Click the project name that contains the assets you want to convert, and click **Next**.

   The **Select Assets** tab displays the list of assets available in the project.
6. Select a maximum of 20 assets to convert.
7. Click **Next**.

   The list of assets that are added to the conversion task appears.
8. Review the assets and do one of the following:
   - Click **Save and Close** to save the conversion task.
   - Click **Save and Run** to save the conversion task and run it immediately.

   The conversion task is created. You can view the list of conversion tasks in the **Explore** > **All Tasks** page. Use the **Type** filter to filter and view all the available conversion tasks.

Modifying a conversion task

Modify a task if you want to remove the assets that you added for conversion, change the configurations, or change the runtime environment where you want to run the conversion job.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **All Tasks**.

   A list of all the assessment, parameter file conversion, and asset conversion tasks appears.
3. Click the task that you want to edit.

   The **Task Details** page appears.

4. Click the edit icon to edit the task.
5. Do one of the following:
   - Click **Save and Close** to save the conversion task.
   - Click **Save and Run** to save the conversion task and run it immediately.

   The conversion task is saved. You can view the list of conversion tasks in the **Explore** > **All Tasks** page. Use the **Type** filter to filter and view all the available conversion tasks.

Running a conversion task

Run a conversion task to start the conversion process.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **All Tasks**.

   A list of all the assessment, parameter file conversion, and asset conversion tasks appears.
3. Click the **Actions** menu of the row of the conversion task and click **Run**.

   The conversion task starts running. You can track the progress of the job in the **My Jobs** page.
4. If you want to view the conversion task details before running, perform the following steps:
   a. Click the conversion task that you want to run.

      The conversion task details appear.
   b. Verify the task details, and then click **Run**.

      The conversion task starts running. You can track the progress of the job in the **My Jobs** page.

   Additionally, CDI-PC sends an email notification after the conversion job completes.

Deleting a conversion task

You can delete a conversion task if it is no longer required.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **All Tasks**.

   A list of all the assessment, parameter file conversion, and asset conversion tasks appears.
3. Click the **Actions** menu of the row of the conversion task and click **Delete**.

   A warning message appears.
4. Click **Yes, delete** to confirm the deletion.

   The conversion task is deleted.
5. If you want to view the conversion task details before deleting, perform the following steps:
   a. Click the conversion task that you want to delete.

      The conversion task details appear.
   b. Verify the task details, and then click the delete icon.

      A warning message appears.

c. Click **Yes, delete** to confirm the deletion.

   The conversion task is deleted.

CHAPTER 4

Bulk Metadata Update

Update the metadata of multiple assets in a single operation.

After you convert and migrate the PowerCenter or Data Engineering Integration assets to Data Integration, you can update the metadata of the assets to ensure that the assets function seamlessly in the cloud environment. You can create bulk update tasks to update the metadata of mapping and taskflow asset types.

To update or create connections, update the `BulkUpdateConnectionTemplate.xlsx` file that is included in the assessment results ZIP and use the file in a bulk update task.

The bulk update process also generates a comprehensive report that includes a list of assets that are submitted for update and the metadata update status.

Mapping asset metadata

The following table describes the metadata types and the corresponding details you can update using a bulk update task:

Metadata Type	Details
Field details	Field name, native type, precision, scale, platform type, default value, and expression.
Advanced properties	Value of mapping properties.
Connection details	Object name, multiple matches, filter, truncate, lookup condition, and data driven condition.
In-out parameters	Description, data type, precision, scale, expression variable, default value, retention policy, and aggregation type.
Mapping SQL queries	SQL queries of the assets.

Taskflow asset metadata

The following table describes the task types and the corresponding details you can update using a bulk update task:

Task Type	Details
Assignment task	Field, type, and value.
Command task	Type and value.
Data task	Preference to suspend taskflow execution when a warning, error, or failure is encountered or when the data task is not run.

Task Type	Details
Decision task	Field, condition, and value.
Email task	Input type and value of the subject, content, body, to, and cc parameters.

Mapping task asset metadata

The following table describes the metadata types and the corresponding details you can update using a bulk update task:

Metadata Type	Details
General properties	Description, Verbose, Schedule ID, Mapping Id, Pre-Processing Commands, Post-Processing Commands, Error Emails, Success Emails, Warning Emails, Max Logs, Enable Cross Schema Pushdown, Allow The Mapping Task To Be Executed Simultaneously, Auto Tuned Applied, Auto Tuned Applied Type, $Source Connection Value, $Target Connection Value, Additional Concurrent Pipelines For Lookup Cache Creation, Allow Pushdown For User Incompatible Connections, Create Temporary Sequence, Create Temporary View, Cache LOOKUP() Function, Commit Interval, Commit On End Of File, Commit Type, Constraint Based Load Ordering, Custom Properties, DTM Buffer Size, Data Column Delimiter, Date Time Format String, Default Buffer Block Size, Error Log File Name, Error Log Type, Incremental Aggregation, Java Classpath, Line Sequential Buffer Length, Log Row Data, Log Source Row Data, Maximum Memory Allowed For Auto Memory Attributes, Maximum Percentage Of Total Memory Allowed For Auto Memory Attributes, On Pre-Post SQL Error, On Pre-session Command Task Error, On Stored Procedure Error, Override Tracing, Pre 85 Timestamp Compatibility, Pushdown Optimization, Rollback Transactions On Errors, Session Log File Name, Session Log File Directory, Session Sort Order, Session Retry On Deadlock, Stop On Errors, Treat Source Rows As, Write Backward Compatible Session Log File, Allow Pushdown Across Databases, Enable High Precision, Error Log File Directory, Output File Directory, Pre-build Lookup Cache, Recovery Strategy, Reinitialize Aggregate Cache, Parameter File Name, Parameter File Dir, Param File Type, Param File Connection Id, Agent Id, Runtime Environment, Short Description, and Source File Directory.
Source transformation advanced properties	Value of the advanced properties of the source transformations.
Target transformation advanced properties	Value of the advanced properties of the target transformations.
Lookup transformation advanced properties	Value of the advanced properties of the lookup transformations.
Sequence advanced properties	Current value of sequences.
In-out parameters	Retention policy and current value of in-out parameters.

Before you begin

The steps you must complete before bulk updating assets metadata.

Before you create a bulk update task, complete the following steps:

1. Complete the conversion of the assets. For more information, see Chapter 3, “Asset Conversion” on page 51.
2. Assign the required asset permissions to create and run a bulk update task. For more information on the asset permissions, see “Asset permissions for bulk update task” on page 10.

Updating assets metadata

Create bulk update tasks to update the metadata of the assets you have converted and migrated to the cloud environment.

Updating the metadata of assets is a two-step process that includes exporting the existing metadata of the converted assets, and then importing new metadata to update the assets. To update the metadata of assets, perform the following steps:

1. Export the existing metadata of the converted assets. Create a bulk update task to perform an export metadata operation. For more information, see “Exporting assets metadata” on page 90.
2. Import new metadata to update the assets. Create a bulk update task to upload new metadata and update the assets. For more information, see “Updating assets metadata” on page 91.

Exporting assets metadata

Export the existing metadata of the assets as an Excel template file.

Before you create a bulk update task, ensure that your role has all the necessary permissions. For information on assigning the required permissions, see *Asset Permissions*.

Create a bulk update task to export the metadata of the assets you have converted and migrated to the cloud platform.



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.
2. Click **Bulk Update Task**, and then click **Create**.

   The **New Bulk Update Task** page appears.

3. The following table describes the properties that you need to configure:

Property	Description
Bulk Update Operation	Type of bulk update operation you want to perform. Select **Export Metadata** to export the metadata of the assets.
Asset Type	Type of assets you want to update.
Task Name	Name of the bulk update task.
Description	(Optional) Description of the bulk update task.
Task Location	Click **Browse**, and select the project or folder location where you want to create the bulk update task.
Project/Folder	Project or folder that contains the assets for bulk update. Select a project and up to 5 folders in the project. To choose a different project or folder, uncheck the selected values.
Operation	The type of metadata you want to export and update the assets. For more information, see the *Bulk update overview* topic.

4. Click **Next**.

   Review the task details before you save and run the task.

5. Do one of the following:
   - Click **Save and Close** to save the bulk update task.
   - Click **Save and Run** to save and run the bulk update task.

   The bulk update task is created. You can view the list of bulk update tasks in the **Explore** > **All Tasks** page. Use the **Type** filter to filter and view all the available bulk update tasks.

Updating assets metadata

Create a bulk update task to update the metadata of the assets you have converted and migrated to the cloud platform.

Before you create a bulk update task, ensure that your role has all the necessary permissions. For information on assigning the required permissions, see *Asset Permissions*.

To create or update connections, ensure that you have updated the `BulkUpdateConnectionTemplate.xlsx` file with the connection details.



1. On the left navigation menu, click **New**.

   The **New Asset** dialog box appears.
2. Click **Bulk Update Task**, and then click **Create**.

   The **New Bulk Update Task** page appears.
3. The following table describes the properties that you need to configure:

Property	Description
Bulk Update Operation	Type of bulk update operation you want to perform. Select **Update Metadata** to update the metadata of the assets.
Task Name	Name of the bulk update task.
Description	Optional. Description of the bulk update task.
Task Location	Click **Browse**, and select the project or folder location where you want to create the bulk update task.
Template File Location	Location of the template file that contains the metadata to update the assets. Select one of the following location types: - **Update from local file system** to upload the template file from your local system. Click **Validate**, and verify if the template file is valid. To create or update connections, upload the `BulkUpdateConnectionTemplate.xlsx` file that you have configured. - **Update from shared location** to provide the shared location path of the template file and the runtime environment. Click **Validate**, and verify if the shared location path is valid.

4. Click **Next**.

   Review the task details before you save and run the task.
5. Do one of the following actions:
   - Click **Save and Close** to save the bulk update task.
   - Click **Save and Run** to save and run the bulk update task.

You can view the list of bulk update tasks in the **Explore** > **All Tasks** page. Use the **Type** filter to filter and view all the available bulk update tasks.

Modifying a bulk update task

You can modify the details of a saved bulk update task to update the task name and description.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **All Tasks**.

   A list of all the assessment, parameter file conversion, worklow conversion, and bulk update tasks appears.
3. Click the bulk update task that you want to edit.

   The **Task Details** page appears.
4. Click the edit icon and modify the task details, such as the task name and description.
5. Do one of the following actions:
   - Click **Save and Close** to save the bulk update task.
   - Click **Save and Run** to save the bulk update task and run it.

Running a bulk update task

Run a bulk update task to start updating assets.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **All Tasks**.

   A list of all the assessment, parameter file conversion, worklow conversion, and bulk update tasks appears.
3. Click the **Actions** menu of the bulk update task row, and click **Run**.

   The bulk update task starts running. You can track the progress of the job in the **My Jobs** page.
4. Click the bulk update task that you want to run.

   The bulk update task details appear.
5. Verify the task details, and then click **Run**.

CDI-PC sends an email notification after the conversion job completes.

Deleting a bulk update task

You can delete a bulk update task if the task is no longer required.

1. On the left navigation menu, click **Explore**.
2. From the explore drop-down list, select **All Tasks**.

   A list of all the assessment, parameter file conversion, worklow conversion, and bulk update tasks appears.
3. Click the **Actions** menu of the row of the bulk update task, and click **Delete**.

   A warning message appears.
4. Click **Yes, delete** to confirm and delete the task.

CHAPTER 5

Jobs

You can monitor the status of the assessment, conversion, and parameter file conversion jobs from the **My Jobs** page.

When you assess a repository, run a conversion task, or run a parameter file conversion task, a job is created. You can track the progress of these jobs from the **My Jobs** page. You can view the job details, download reports, and log files. Use these reports to verify the job results and troubleshoot any issues. Additionally, you can stop a running job or restart a completed job, if required.

Monitoring an assessment job

When you assess a repository, an assessment job is created. You can track the status of the job in the **My Jobs** page. After the job completes, you can view the job summary, download the files generated as part of the job, and access the task properties.

1. On the left navigation menu, click **My Jobs**.

   A list of jobs appear with their current status.

   Note: The job name for an assessment job is auto-generated in the following format: `<DomainName>_<RepositoryName>_AssessmentTask`
2. Use the search option to find the job that you want to monitor.
3. Optionally, you can use the filter option to filter the jobs by type and status.
4. Click the job name that you want to monitor.

   The job detail page appears, displaying the summary and properties of the job.
5. Click the **Task Name** link.

   The **Task Details** page appears, displaying the following information:

   - Task name, description, and type
   - Shared location where the input files are placed
   - Runtime environment on which the job was run
   - Conversion use case selected for the assessment
   - Domain and Repository names

Monitoring a conversion job

When you run a conversion task, a conversion job is created. You can track the status of the job in the **My Jobs** page.

1. On the left navigation menu, click **My Jobs**.

   A list of jobs appear.
2. Use the search option to find for the conversion job that you want to monitor.
3. Optionally, you can use the filter option to filter the jobs by type and status.

   The type of conversion job is Conversion Task.
4. Click the conversion job name that you want to monitor.

   The job detail page appears, displaying the properties of the job and the list of assets with their conversion statuses.

   Note: You can view the job details only for completed and failed jobs.
5. Select an asset on the left pane.

   The right pane displays the asset details within the workflow.
6. Click the **Task Name** link.

   The **Task Details** page appears, displaying the following information:

   - Task name, description, and type
   - Project and folder location
   - Runtime environment on which the job was run
   - Repository name containing the assets for conversion
   - List of assets processed by the conversion job
   - Connection map and conversion properties configurations

Monitoring a parameter file conversion job

When you run a parameter file conversion task, a parameter file conversion job is created. You can track the status of the job in the **My Jobs** page. After the job completes, you can view the job summary, download the reports, and access the task properties.

1. On the left navigation menu, click **My Jobs**.

   A list of jobs appear with their current status.
2. Use the search option to find the job that you want to monitor.
3. Optionally, you can use the filter option to filter the jobs by type and status.
4. Click the job name that you want to monitor.

   The job detail page appears that displays the summary and properties of the job.
5. Click the **Task Name** link.

   The **Task Details** page appears that displays the following information:

   - Task name, description, and location

- Location of the PowerCenter parameter file and conversion input file
- Runtime environment on which the job was run
- Project name

Monitoring a bulk update job

When you run a bulk update task, a bulk update job is created. You can track the status of the job in the **My Jobs** page.

1. On the left navigation menu, click **My Jobs**.

   A list of jobs appear.
2. Use the search option to find the bulk update job that you want to monitor.
3. Optionally, you can use the filter option to filter the jobs by type and status.

   The type for bulk update jobs is Bulk Update Task.
4. Click the bulk update job name that you want to monitor.

   The job detail page appears that displays the summary and properties of the job.
5. On the left pane, select a workflow.

   The right pane displays the asset details within the workflow.
6. Click the **Task Name** link.

   The **Task Details** page appears displaying the following information:

   - Bulk update operation and asset type
   - Task name and description of the task
   - Location of the task
   - Project and folder containing the assets
   - Type of operation for the export metadata tasks
   - Template file location and the Excel file to be updated for the update metadata tasks

Downloading job output files

After a job completes, you can download the reports, log files, templates, and other related files generated as part of the job.

1. On the left navigation menu, click **My Jobs**.

   A list of jobs appear.
2. Click the job name for which you want to download the reports.

   The job detail page appears, displaying the summary and properties of the job.
3. Click **Download All**.

   A zip file is downloaded containing the files generated as part of the job.

An assessment job contains the following files:

- Assessment reports
- Log files
- Template files for conversion

A conversion job contains the following files:

- Conversion reports
- Input files
- Log files
- Templates

A parameter file conversion job contains the following files:

- PowerCenter parameter file
- Data Integration parameter files
- Logs and reports

CHAPTER 6

Configurations

In CDI-PC, a configuration is a set of configured parameters that you can use in multiple tasks to customize the assessment and conversion behavior.

Based on the configuration type, you can use the configuration in assessment or conversion tasks.

You can create the following configurations:

- **Repoint Configuration**: If you want to repoint the assets to another endpoint, you need to create a repoint configuration. You can configure the PowerCenter connection type and the corresponding IDMC connection type to which you want to repoint the assets. You can use this configuration in assessment tasks to evaluate the feasibility of repointing the assets to another endpoint. For information on creating a repoint configuration, see the *Creating a Repoint Configuration* topic.
- **Connection Map**: Based on the assessment result, you can create a connection map configuration to map the PowerCenter connections to corresponding IDMC connections. You can use this configuration in conversion tasks. Based on the configuration, CDI-PC repoints the PowerCenter assets to the configured connection in IDMC. For information on creating a connection map configuration, see the *Creating a Connection Map configuration* topic.
- **Conversion Properties**: If you want to override the default conversion behavior, you need to create a conversion properties configuration. You can use this configuration in conversion tasks. For information on creating the conversion properties configuration, see the *Creating a Conversion Properties configuration* topic.

Managing a configuration

You can manage an existing configuration by performing different actions on the configuration, such as modifying the configuration, creating a copy of an existing configuration, or renaming a configuration.

The **Configurations** page lists the repoint, connection map, and conversion properties configurations. Click the actions menu on a configuration and select the appropriate action to manage the configuration.

You can perform the following actions on a configuration:

View

Click **View** to view the configuration details.

Edit

Click **Edit** to modify the configuration description and properties for the configuration.

Copy

Click **Copy** to copy the configuration to another domain and repository with a different name.

Rename

Click **Rename** to change the name of the configuration.

Set as default

Click **Set as default** to set the configuration as the default configuration. For each configuration type, you can set one configuration as default. When you select a configuration in assessment or conversion tasks, the configuration is marked as default.

Delete

Click **Delete** to delete a configuration. You can delete a configuration only if it is not associated with any assessment or conversion task.

Accessing configurations associated with domains and repositories

You can access the configurations associated with a domain or repository from the **Explore** page.

Each configuration that you create is associated with either a domain or a combination of a domain and repository. The **Configurations** page displays the list of all the configurations. You can filter the configurations by domain or repository. Alternatively, you can access to the domain or repository from the **Explore** page, and then access the configurations associated with a domain or repository.

1. On the left navigation menu, click **Explore**.
2. From the **Explore** list, select **Domain** or **Repository**.
3. From the actions menu of the domain or repository, click **View Configurations**.

INDEX

A

assess repository 42, 98

C

connection map configuration 54
conversion job monitoring 95

J

job monitoring 94
jobs 94

M

modify a conversion project 22, 85

P

parameter file conversion job monitoring 95