Informatica

Informatica® Cloud Data Integration

DB2 Loader Connector

Informatica Cloud Data Integration DB2 Loader Connector
April 2026

© Copyright Informatica LLC 2023, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at https://www.informatica.com/legal/patents.html.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-04-10

Table of Contents

Preface 4

Informatica Resources 4

- Informatica Documentation 4
- IDMC web site 4
- IDMC Communities 4
- IDMC Marketplace 4
- Data Integration connector documentation 5
- Informatica Knowledge Base 5
- IDMC Trust Center 5
- Informatica Global Customer Support 5

Chapter 1: Introduction to DB2 Loader Connector 6

DB2 Loader Connector assets 6

Chapter 2: Connections for DB2 Loader 7

Prerequisites 7

- Install the DB2 Loader JDBC driver and DB2 client 7

Connect to DB2 Loader 8

- Before you begin 8
- Connection details 8

Chapter 3: Mappings and mapping tasks with DB2 Loader Connector 12

Before you begin 12

- Verify database authorities and privileges 12

DB2 Loader targets in mappings 12

Rules and guidelines for DB2 Loader objects 15

Chapter 4: Data type reference 16

DB2 Loader and transformation data types 16

Index 18

Preface

Use DB2 Loader Connector to learn how to write to DB2 database by using Data Integration. Learn to create a DB2 Loader connection, develop, and run mappings and mapping tasks in Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security policies and real-time system availability.

You can access the trust center at https://www.informatica.com/trust-center.html.

Subscribe to the IDMC Trust Center to receive upgrade, maintenance, and incident notifications. The Informatica Intelligent Data Management Cloud Status page displays the production status of all the Informatica cloud products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single component or all IDMC components. Subscribing to all components is the best way to be certain you never miss an update.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introduction to DB2 Loader Connector

You can use DB2 Loader Connector to connect to DB2 from Data Integration. Use the DB2 Loader connection to securely write data to a DB2 database.

You can use DB2 Loader objects as targets in mappings and mapping tasks. When you use these objects in mappings, you must configure properties specific to DB2.

You can use DB2 Loader Connector to insert records to DB2 databases.

DB2 Loader Connector assets

Create assets in Data Integration to integrate data using DB2 Loader Connector.

When you use DB2 Loader Connector, you can include the following Data Integration assets:

- Mapping
- Mapping task

For more information about configuring assets and transformations, see *Mappings*, *Transformations*, and *Tasks* in the Data Integration documentation.

CHAPTER 2

Connections for DB2 Loader

Create a DB2 Loader connection to securely write data to DB2. You can use a DB2 Loader connection to specify targets in mappings and mapping tasks.

Prerequisites

Before you create a DB2 Loader connection to write to DB2, be sure to complete the prerequisites.

Install the DB2 Loader JDBC driver and DB2 client

To write data to DB2 databases, you need to install the DB2 Loader JDBC driver and DB2 client on the Secure Agent machine.

- Install the DB2 Loader JDBC driver on the Secure Agent machine.
  To install the driver, perform the following steps:
  1. To get the DB2 Loader JDBC driver, contact Informatica Global Customer Support.
  2. Create the `informatica.db2loader` folder manually in the following directory based on whether the Secure Agent machine is a Windows or a Linux machine:

Secure Agent machine	Directory
Linux	`<Secure Agent installation directory>/ext/connectors/thirdparty/informatica.db2loader`
Windows	`<Secure Agent installation directory>\ext\connectors\thirdparty\informatica.db2loader`

  3. Copy the DB2 Loader JDBC driver to the `informatica.db2loader` folder.

- Install the DB2 LUW client on the Secure Agent machine.
  To install the DB2 LUW client, perform the following steps:
  1. Download and install the DB2 LUW client and instance from the IBM website.

2. Set the following environmental variables based on whether the Secure Agent machine is a Windows or a Linux machine:

Secure Agent machine	Environmental variable
Linux	- setenv DB2INSTANCE <DB2 instance directory> - setenv DB2CLP DB20FADE - setenv PATH <DB2 client directory>/bin - setenv LD_LIBRARY_PATH <DB2 client directory>/lib64
Windows	setenv DB2CLP DB20FADE

After you install the DB2 Loader JDBC driver and set the environmental variables, you need to restart the Secure Agent.

Connect to DB2 Loader

Let's configure the DB2 Loader connection properties to connect to a DB2 database.

Before you begin

Before you get started, you'll need to install the DB2 Loader JDBC driver and DB2 client on the Secure Agent machine to establish a DB2 Loader connection.

Check out "Prerequisites" on page 7 to learn more about the configuration prerequisites.

Connection details

The following table describes the basic connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.

Property	Description
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select which credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent.
Host Name	The name of the machine that hosts the DB2 database server.
Database Name	The name of the DB2 database.
Port Number	The port number that connects to the DB2 database server. Default is 50000.
Schema Name	The schema name in the DB2 database server to fetch the metadata. This property doesn't apply when you configure a DB2 Loader connection.
User Name	The user name to connect to the DB2 account.
Password	The password to connect to the DB2 account.
Connection String	The alias name to connect to the DB2 database.

Advanced settings

The following table describes the advanced connection properties:

Property	Description
Encryption Method	Encrypts data exchanged between the Secure Agent and the database server. Select one of the following encryption methods from the list: - No Encryption. Establishes a connection without using SSL. Data is not encrypted. - SSL. Establishes a connection using SSL. Data is encrypted using SSL. Default is No Encryption.
Validate Server Certificate	Determines whether the Secure Agent validates the certificate that is sent by the database server. This property appears only if you select the encryption method as **SSL**. Select one of the following options from the list: - False. The Secure Agent does not validate the certificate. - True. The Secure Agent validates the certificate. Default is False.

Property	Description
Truststore	The path and file name of the truststore file that contains the SSL certificate to connect to DB2. This property appears only if you select the encryption method as **SSL** and validate server certificate as **True**. Specify both the directory and file name in the following format: `/root/<folder name>/<truststore file name>.p12`
Truststore Password	The password to access the truststore file that contains the SSL certificate. This property appears only if you select the encryption method as **SSL** and validate server certificate as **True**.
Host Name in Certificate	The name of the machine that hosts the secure database. This property appears only if you select the encryption method as **SSL** and validate server certificate as **True**. The Secure Agent validates the host name specified in this property with the host name in the SSL certificate.
Authentication Method	The authentication method that the driver uses to establish a connection. Select one of the following authentication methods from the list: - Clear Text. Sends the user ID and password in clear text to the DB2 server for authentication. - Encrypted Password. Sends the user ID in clear text and encrypted password to the DB2 server for authentication. Default is Clear Text.
Is Staged	Method to load data. Select **Is Staged** to load data to a flat file staging area before loading to the database. Default is disabled.
Recoverable	Sets the DB2 tablespace in backup pending state. Before you enable the **Recoverable** option and run a mapping, you need to fully back up the database to perform any other operation on the tablespace. Default is enabled.
DB2 Server Location	The DB2 database server location. Select one of the following locations from the list: - Remote. The DB2 database server resides on another machine. - Local. The DB2 database server resides on the Secure Agent machine. Default is Remote.
External Loader Executable	The DB2 external loader executable file name. The Secure Agent uses the DB2 external loader executable file of the IBM data server client 9.5 version and later. Default is db2load.

Property	Description
Operation Mode	The operation for DB2 external loader to perform. Select one of the following operation modes to determine how the DB2 external loader writes data to the target table based on the mode that you selected in the DB2 external loader: - Insert. Loads data to the table. - Replace. Deletes existing data from the table, and then adds data to the table. - Restart. Restarts a previously interrupted load operation. - Terminate. Terminates a previously interrupted load operation and rolls back the operation to the starting point, even if consistency points are passed. Default is Insert.
Additional Metadata Connection Properties	Additional metadata connection properties that you want to pass to the driver. If you specify more than one property, separate each key-value pair with a semicolon. For example, <parameter name1>=<value1> ; <parameter name2>=<value2>

CHAPTER 3

Mappings and mapping tasks with DB2 Loader Connector

Use the Data Integration Mapping Designer to create a mapping. When you create a mapping, configure a target to represent a DB2 Loader object.

Describe the flow of data from the source to the target along with the required transformations before the agent writes data to the DB2 target. When you create a mapping task, select the configured mapping that you want to use. Use the Mapping Task wizard to create a mapping task. Validate and run the mapping to write to a target. The mapping task processes data based on the data flow logic you define in the mapping.

Before you begin

Before you configure and run a mapping, complete the required prerequisites.

Verify database authorities and privileges

To run a mapping that writes data to a DB2 Loader target table, you need to have the required database authorities and privileges on the DB2 database.

Before you write to the DB2 database, verify that you have the following database authorities and privileges:

- SYSADM authority or DBADM authority to fetch the metadata at design time.
- LOAD authority on the database to load the data at runtime. One of the following database privileges when the load utility is invoked in insert, terminate, or restart operation:
  - Insert privilege on the table
  - Insert and delete privileges on the table

For more information about these database authorities and privileges, see the IBM DB2 documentation.

DB2 Loader targets in mappings

To write data to a DB2 database, configure a DB2 Loader object as the target in a mapping.

Specify the name and description of the DB2 target. Configure the target and advanced properties for the target object.

The following table describes the target properties that you can configure for a DB2 Loader target:

Property	Description
Connection	Name of the target connection. You can select an existing connection, create a new connection, or define parameter values for the target connection property. To overwrite the target connection properties at runtime, select the **Allow parameter to be overridden at run time** option.
Target Type	Type of the DB2 Loader target object. Select one the following target types: - Single - Parameter
Object	Name of the DB2 Loader target object. You can select an existing object from the list.
Parameter	A parameter file where you define values that you want to update without having to edit the task. Select an existing parameter for the target object or click **New Parameter** to define a new parameter for the target object. The **Parameter** property appears only if you select parameter as the target type. If you want to overwrite the target object at runtime, select the **Allow parameter to be overridden at run time** option. When the task runs, the agent uses the parameters from the file that you specify in the advanced session properties.
Operation	Type of the target operation. You can perform only the insert operation on a DB2 Loader target.

The following table describes the advanced target properties that you can configure for a DB2 Loader target:

Property	Description
Truncate Target	Truncates the target table before inserting new rows. Default is disabled.
Append if exists	Appends the output data to the target files and reject files. Default is disabled.
Create Target Directory	Creates a directory to store the output files. Default is disabled. Do not change the default value.
Header Options	The header row in the DB2 Loader target table. Select one of the following header options from the list: - No Header. Does not create a header row in the target table. - Output Field Names. Creates a header row in the target table with the output field names. - Use header command output. Not applicable. Default is No Header.

Property	Description
Output File Directory	The directory that stores the output files. Specify the directory where you want to store the output files. Ensure that the specified directory is accessible from the Secure Agent machine. Default is `$PMTargetFileDir`. **Note:** Do not use double spaces in the directory name of the output file.
Output File Name	Creates the output file in the output file directory with the name you specify. Specify the output file name. Default is `Output1.out`. If you use the default file name, the mapping appends a unique identifier to it and generates the output file. If you specify an output file name, the mapping generates the output file using the specified file name.
Reject File Directory	The directory that stores the rejected files. Specify the directory where you want to store the rejected files. Default is `$PMBadFileDir`.
Reject File Name	Creates the rejected file in the reject file directory with the name you specify. Specify the reject file name. Default is `Output1.bad`. If you use the default file name, the mapping appends a unique identifier to it and generates the reject file. If you specify a reject file name, the mapping generates the reject file using the specified file name.
File Delimiter	The delimiter to use to separate columns of data in a delimited flat file. Default is comma (,). Do not change the default value.
Table Name Prefix	Prefix that the Secure Agent adds to the target table name. Enter a schema name to add as a prefix to the table name that you load to the target. When you add a prefix in this field, the target table name appears in the control file in the following format: `<table name prefix>.table name`
Target Table Name	The target table name that you want to override in a mapping.
Code Page	The code page that the Secure Agent uses to write data to a delimited flat file. Select one of the following code pages from the list: - MS Windows Latin 1 (ANSI), superset of Latin 1 - Unicode Transformation Format, multibyte Default is MS Windows Latin 1 (ANSI), superset of Latin 1.

Property	Description
Optional Quotes	Quote characters that define the boundaries of data in a delimited flat file. Select one of the following quotes from the list: - None - Single - Double Default is None.
Forward Rejected Rows	Determines whether the transformation passes rejected rows to the next transformation or drops rejected rows. By default, the mapping task forwards rejected rows to the next transformation. If you select the Forward Rejected Rows option, the Secure Agent flags the rows for reject and writes them to the reject file. If you do not select the Forward Rejected Rows option, the Secure Agent drops the rejected rows and writes them to the session log file. The Secure Agent does not write the rejected rows to the reject file.

Rules and guidelines for DB2 Loader objects

Consider the following rules and guidelines for DB2 Loader objects used as targets in mappings and mapping tasks:

General guidelines

- When you write to a DB2 Loader target table and some rows are rejected due to constraint violation errors, the session log shows incorrect number of rows that are written to the target.
- To load data from a delimited flat file, ensure that the precision of each target table column matches the corresponding source column precision to write all data.

Data types

When you load blank spaces to a DB2 Loader target, the blank spaces are loaded as null values in the Char data type field.

Partitioning

You can't load data to a DB2 target in a mapping enabled for the source partitioning.

Data preview

You can't preview data of a DB2 Loader target object.

CHAPTER 4

Data type reference

Data Integration uses the following data types in mappings and mapping tasks with DB2:

DB2 native data types

DB2 data types appear in the **Target Fields** tab of the Target transformation when you choose to edit metadata for the fields.

Transformation data types

Set of data types that appear in the transformations. They are internal data types based on ANSI SQL-92 generic data types, which the Secure Agent uses to move data across platforms. Transformation data types appear in all transformations in a mapping.

When Data Integration writes to a target, it converts the transformation data types to the comparable native data types.

DB2 Loader and transformation data types

Use only the supported DB2 data types in a mapping to write to DB2.

The following table lists the DB2 data types that Data Integration supports and the corresponding transformation data types:

DB2 data type	Range and Description	Transformation data type	Range and Description
Bigint	-9,223,372,036,854,775,808 to 9,223,372,036,854,775,807	Bigint	-9,223,372,036,854,775,808 to 9,223,372,036,854,775,807 Precision 19, scale 0
Char	1 to 254 characters	String	1 to 104,857,600 characters
Date	0001 to 9999 A.D. Precision 19; scale 0 (precision to the day)	Date/Time	Jan 1, 0001 A.D. to Dec 31, 9999 A.D. (precision to the nanosecond)
Decimal	Precision 1 to 31, scale 0 to 31	Decimal	Precision 1 to 28, scale 0 to 28
Double	Precision 15	Double	Precision 15
Float	Precision 1 to 15	Double	Precision 15

DB2 data type	Range and Description	Transformation data type	Range and Description
Graphic	1 to 128 characters	String	1 to 104,857,600 characters
Integer	-2,147,483,648 to 2,147,483,647	Integer	-2,147,483,648 to 2,147,483,647 Precision 10, scale 0
Numeric	Precision 1 to 31, scale 0 to 31	Decimal	Precision 1 to 28, scale 0 to 28
Real	Precision 7, scale 0	Real	Precision 7, scale 0
Smallint	-32,768 to 32,767	Small Integer	Precision 5, scale 0
Time	24-hour time period Precision 19, scale 0 (precision to the second)	Date/Time	Jan 1, 0001 A.D. to Dec 31, 9999 A.D. (precision to the nanosecond)
Timestamp	26 bytes Precision 26, scale 6 (precision to the microsecond)	Date/Time	Jan 1, 0001 A.D. to Dec 31, 9999 A.D. (precision to the nanosecond)
Varchar	Up to 4,000 characters	String	1 to 104,857,600 characters
Vargraphic	1 to 16352 characters	String	1 to 104,857,600 characters

INDEX

C

Cloud Application Integration community
  URL 4
Cloud Developer community
  URL 4
connections
  DB2 Loader 8

D

Data Integration community
  URL 4
data type reference
  overview 16
data types
  DB2 16
DB2 Loader
  assets 6
  connection properties 8
DB2 Loader Connector
  mapping 12
  overview 6
  rules and guidelines 15
DB2 targets
  mappings 12

I

Informatica Global Customer Support
  contact information 5
Informatica Intelligent Data Management Cloud
  web site 4

M

maintenance outages 5

S

status
  IDMC 5
system status 5

T

trust site
  description 5

U

upgrade notifications 5

W

web site 4