Informatica®

Informatica® Cloud Data Integration

JMS Connector

Informatica Cloud Data Integration JMS Connector
April 2026

© Copyright Informatica LLC 2025, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at https://www.informatica.com/legal/patents.html.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-04-10

Table of Contents

Preface 4

Informatica Resources 4

- Informatica Documentation 4
- IDMC web site 4
- IDMC Communities 4
- IDMC Marketplace 4
- Data Integration connector documentation 5
- Informatica Knowledge Base 5
- IDMC Trust Center 5
- Informatica Global Customer Support 5

Chapter 1: Introduction to JMS Connector 6

JMS Connector assets 6

Chapter 2: Connections for JMS 7

Prerequisites 7

Connect to JMS 7

- Before you begin 7
- Connection details 8

Chapter 3: Mappings for JMS 10

JMS sources in mappings 10

- Configure a mapping to read data from JMS in real-time 11

JMS targets in mappings 12

Configure message recovery strategy for a JMS mapping 13

Maintain transactional consistency for JMS targets 13

JMS transacted mode 14

Rules and guidelines for JMS mappings 14

Chapter 4: Data type reference 15

JMS and transformation data types 15

Index 16

Preface

Use JMS Connector to learn how to read from and write to JMS by using Data Integration. Learn to create a JMS connection, run mappings and tasks in Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the IDMC web site at http://www.informatica.com/cloud. This site contains information about Informatica Cloud integration services.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security policies and real-time system availability.

You can access the trust center at https://www.informatica.com/trust-center.html.

Subscribe to the IDMC Trust Center to receive upgrade, maintenance, and incident notifications. The Informatica Intelligent Cloud Services Status page displays the production status of all the Informatica cloud products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single component or all IDMC components. Subscribing to all components is the best way to be certain you never miss an update.

To subscribe, on the Informatica Intelligent Cloud Services Status page, click **SUBSCRIBE TO UPDATES**. You can choose to receive notifications sent as emails, SMS text messages, webhooks, RSS feeds, or any combination of the four.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introduction to JMS Connector

You can use JMS Connector to extract data from JMS sources and write to JMS targets.

You can read and write JMS messages to Java Message Service (JMS) destinations, which can be queues or topics. JMS messages are either text messages or binary messages. You can connect to Apache Active MQ or RabbitMQ to read data from or write data to JMS.

JMS Connector conforms to JMS specification version 1.1.0. However, you can also use a JMS provider that implements JMS version 2.0.

JMS Connector assets

Create assets in Data Integration to integrate data using JMS Connector.

When you use JMS Connector, you can include the following Data Integration assets:

- Mappings
- Mapping task

For more information about configuring assets and transformations, see *Mappings*, *Transformations*, and *Tasks* in the Data Integration documentation.

CHAPTER 2

Connections for JMS

Create a JMS connection to securely read data from or write data to JMS.

You can use a JMS connection to specify sources and targets in mappings and mapping tasks.

Prerequisites

Before you configure the connection properties, make sure to copy the JMS provider-specific third-party client libraries to the following location and restart the Secure Agent after copying the client libraries:
`<Informatica Secure Agent installation directory>/ext/connectors/thirdparty/infa.jms`

Create the folder structure if it does not already exist.

For more information about the required third-party client libraries, see the JMS provider documentation.

Connect to JMS

Let's configure the JMS connection properties to connect to JMS.

Before you begin

Before you get started, you need to keep the details of the JNDI naming provider, JNDI context factory, and credentials for JMS connection handy.

Check out "Prerequisites" on page 7 to learn about the requirements before you configure a connection.

Connection details

The following table describes the basic connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select which credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent or elastic runtime environment. For more information about how to configure and use the runtime environments, see *Runtime Environments* in the Administrator help.

Connection URL	The URL of the JNDI naming provider.
	For Apache Active MQ, specify the URL in the following format:
	`- protocol://hostname:port`
	For example, tcp://INVW201:61616
	For RabbitMQ, place the .bindings file in the Secure Agent machine and specify the URL in the following format based on your operating system:
	`- file:/<absolute path of the folder containing the bindings file>`
	Contact your system administrator to get the .bindings file.

JNDI Username	The user name to connect to the JNDI context factory.
JNDI Password	The password to connect to the JNDI context factory.
JNDI Context Factory	A fully qualified class name that allows you to connect to the JNDI service. For example, the class name of the Initial Context Factory for Apache Active MQ is `org.apache.activemq.jndi.ActiveMQInitialContextFactory` For example, the class name of the Initial Context Factory for RabbitMQ is `com.sun.jndi.fscontext.RefFSContextFactory` For more information, see the documentation of the JMS provider.
JNDI Package Prefixes	A colon-separated list of package name prefixes provided to the JNDI context factory to identify and load the appropriate context factory classes. For example, `java.naming.factory.url.pkgs=org.apache.activemq.jndi` For more information about the values, see the documentation of the JMS provider.

Property	Description
JMS Connection Factory	The name of the JNDI object used by a JMS client to create a connection. For example, `jms/QCF` or `jmsSalesSystem`.
Connection Username	The user name to authenticate the JMS provider to connect to the JMS connection factory.
Connection Password	The password to authenticate the JMS provider to connect to the JMS connection factory.

CHAPTER 3

Mappings for JMS

Use the Data Integration Mapping Designer to create a mapping. When you create a mapping, configure a source or target to represent a JMS destination.

Describe the flow of data from the source to the target along with the required transformations before the agent writes data to the JMS target. When you create a mapping task, select the configured mapping that you want to use. Use the Mapping Task wizard to create a mapping task. Validate and run the mapping to read data from sources and write to a target. The mapping task processes data based on the data flow logic you define in the mapping.

JMS sources in mappings

To read data from JMS, configure a JMS object as the Source transformation in a mapping.

Specify the name and description of the JMS source. Configure the source and advanced properties for the source object.

The following table describes the source properties that you can configure for a JMS source:

Property	Description
Connection	Name of the source connection. You can select an existing connection, create a new connection, or define parameter values for the source connection property. If you want to overwrite the source connection properties at runtime, select the **Allow parameter to be overridden at run time** option. Specify the parameter file directory and name in the advanced session properties.
Source Type	Type of the source object. Select one of the following source types: - Single Object - Parameter Default is Single Object.

Property	Description
Object	Name of the JMS source object type. Select a JMS queue or topic from the list. Specify the name of the JMS queue or topic in the JMS Destination advanced source property.
Parameter	A placeholder to dynamically assign values at run time for the source object without the requirement to edit the task. Select an existing parameter for the source object or click **New Parameter** to define a new parameter for the source object. The **Parameter** property appears only if you select parameter as the source type. If you want to overwrite the parameter at runtime, select the **Allow parameter to be overridden at run time** option.

The following table describes the advanced source properties that you can configure for a JMS source:

Property	Description
Stop Session	Stops session if multiple retries yield no new data and some data is already received. If you clear this check box, JMS Connector continues polling the JMS provider for new data.
JMS Source Destination	The name of the JMS queue or topic on the JMS provider from where you receive JMS messages.
Client ID	The client identifier used to identify and set up a JMS connection.
Durable Subscription Name	Applicable only to JMS topics. The unique string identifier for a durable subscriber that allows the subscriber to receive messages from a JMS topic even if the subscriber is inactive. To create a durable subscriber, you need to configure both the client ID and durable subscription name.
JMS Message Selector	Filters messages from a topic or queue based on the criteria defined in the message header fields or properties.
Tracing Level	Determines the amount of detail that appears in the log file. Select one of the following options: - Terse - Normal - Verbose Initialization - Verbose Data Default is Normal.

Configure a mapping to read data from JMS in real-time

You can configure a mapping to read data from a JMS topic in real-time.

To read data from a JMS topic in real-time, perform the following tasks:

1. In the JMS advanced source properties, clear the **Stop Session** check box.
2. Enable message recovery in the **Advanced Session Properties** section on the **Runtime Options** tab of the mapping task.
   For more information about how to configure the message recovery, see "Configure message recovery strategy for a JMS mapping" on page 13.

JMS targets in mappings

Add a Target transformation to write data to a target. When you add a Target transformation to a mapping, you define the target connection, target objects, and target properties related to the JMS connection type.

The following table describes the JMS target properties that you can configure in a Target transformation:

Property	Description
Connection	Name of the target connection.
Target Type	Target type. Select one of the following target types: - Single Object - Parameter
Object	Name of the JMS target object type. Select a JMS queue or topic.
Operation	Target operation. You can use only the insert operation.

The following table describes the advanced properties:

Property	Description
JMS Target Destination	The name of the JMS queue or topic on the JMS provider to which you write JMS messages. If you don't specify a JMS destination in the Source transformation, the mapping creates the JMS destination at runtime based on the selected target object.
Message Type	The type of JMS messages that you can write to the JMS destination.
Delivery Mode	Determines how the messages are handled in the event of a JMS provider failure. Select **Persistent** to store the messages until it is delivered and select **Non-Persistent** to store messages temporarily depending on how the JMS provider implements message handling.
Time To Live	The time duration in milliseconds for which the messages are available for consumption. Default value is 0, indicating that the messages do not expire and remain available until consumed.
Forward Rejected Rows	Determines whether the transformation passes rejected rows to the next transformation or drops rejected rows. By default, the Secure Agent forwards rejected rows to the next transformation.

For more information about configuring transformations, see *Transformations* in the Data Integration documentation.

Configure message recovery strategy for a JMS mapping

When you enable message recovery for a JMS mapping task, the Secure Agent stores source messages or message IDs in a recovery file, recovery table, recovery queue, or recovery topic.

You can configure message recovery for tasks that read from a JMS source. When you configure message recovery for a JMS mapping task, the Secure Agent can recover unprocessed messages from a failed mapping. If the mapping task fails, run the mapping task in recovery mode to recover the messages that the Secure Agent did not process. The Secure Agent is resilient to JMS connection failures when recovery is enabled and when the Secure Agent is reading a JMS message.

Enable message recovery

Complete the following steps to enable message recovery for a JMS mapping task:

1. In the **Advanced Session Properties** on the **Runtime Options** tab of the mapping task, add the following properties:

Session Property Name	Session Property Value
Commit on End of File	No
Commit Type	Source
Recovery Strategy	Resume from last checkpoint

2. Click **Finish**.

The Secure Agent saves the mapping state of operation and maintains target recovery tables. If the mapping aborts, stops, or terminates, the Secure Agent uses the saved recovery information to resume the mapping from the point of interruption.

Maintain transactional consistency for JMS targets

The Secure Agent can maintain transactional consistency when writing data to JMS targets.

When the Secure Agent maintains transactional consistency, it commits messages to JMS targets after all messages in a transaction group are loaded to the targets. A transaction group consists of all messages that the Secure Agent commits when it reaches a commit point.

To ensure transactional consistency, all JMS targets in the same pipeline must belong to the same target connection group. JMS targets that are in the same target connection group receive data from the same transactional source. Two or more JMS targets are in the same target connection group if they have the same value for each of the following connection properties:

- JNDI Context Factory
- Connection URL
- JMS Connection Factory

JMS transacted mode

You can configure JMS sessions to run in a transacted mode.

When you configure JMS sessions to run in a transacted mode, the Secure Agent receives and processes a group of JMS messages as a transaction and acknowledges all the messages by committing the transaction. If a transaction rolls back, the JMS provider returns all the uncommitted messages in that particular transaction to the recovery queue configured for the JMS application connection or the default cache folder $PMCacheDir\.

Rules and guidelines for JMS mappings

Consider the following rules and guidelines when you configure a JMS mapping:

- You can only use certain transformations when you run a JMS mapping. For more information on the transformations that you can use, see the Custom and other active transformations knowledge article.
- To run a data preview job for a mapping, click **Run Preview** on the **Preview** panel in the Mapping Designer.
- You can configure a commit interval in the **Advanced Session Properties** on the **Runtime Options** tab of the mapping task:

Session Property Name	Session Property Value
Commit Interval	10

Ensure that the commit interval is lesser than the DTM buffer size. When you do not configure a commit interval, the mapping uses the default DTM buffer size.

CHAPTER 4

Data type reference

Data Integration uses the following data types in mappings and mapping tasks with JMS:

- **JMS native data types**. JMS native data types appear in the Source and Target transformations when you choose to edit metadata for the fields.
- **Transformation data types**. Set of data types that appear in the transformations. They are internal data types based on ANSI SQL-92 generic data types, which the Secure Agent uses to move data across platforms. Transformation data types appear in all transformations in a mapping.

When Data Integration reads source data, it converts the native data types to the comparable transformation data types before transforming the data. When Data Integration writes to a target, it converts the transformation data types to the comparable native data types.

JMS and transformation data types

The following table lists the JMS data types that Data Integration supports and the corresponding transformation data types:

JMS data type	Transformation data type	Range and description
Bigint	Big Integer	Default precision is 8.
Binary	Binary	Default precision is 65535.
Boolean	Integer	Default precision is 12.
Decimal	Decimal	Default precision is 12, Scale 0.
Double	Double	Default precision is 15.
Integer	Integer	Default precision is 12.
Long	Big Integer	Default precision is 8.
Object	String	Default precision is 65535.
String	String	Default precision is 65535.
Timestamp	Date	Date and time values with precision to the nanosecond.

INDEX

C

Cloud Application Integration community
  URL 4
Cloud Developer community
  URL 4

D

Data Integration community
  URL 4

I

Informatica Global Customer Support
  contact information 5
Informatica Intelligent Cloud Services
  web site 4

M

maintenance outages 5
mapping
  JMS sources 10
mappings
  message recovery 13

S

status
  Informatica Intelligent Cloud Services 5
system status 5

T

trust site
  description 5

U

upgrade notifications 5

W

web site 4