Informatica® Cloud Data Integration

MongoDB Connector

Informatica Cloud Data Integration MongoDB Connector
July 2025

© Copyright Informatica LLC 2018, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at https://www.informatica.com/legal/patents.html.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-05-12

Table of Contents

Preface 4

Informatica Resources 4

- Informatica Documentation 4
- Informatica Intelligent Cloud Services web site 4
- Informatica Intelligent Cloud Services Communities 4
- Informatica Intelligent Cloud Services Marketplace 4
- Data Integration connector documentation 5
- Informatica Knowledge Base 5
- Informatica Intelligent Cloud Services Trust Center 5
- Informatica Global Customer Support 5

Chapter 1: Introduction to MongoDB Connector 6

MongoDB Connector assets 6

Virtual tables 7

- Virtual tables example 7

Chapter 2: MongoDB connections 9

MongoDB connection properties 9

Chapter 3: Mappings and mapping tasks with MongoDB 11

Configure preSQL and postSQL commands for MongoDB sources and targets 11

MongoDB sources in mappings 11

Joining multiple objects 13

MongoDB targets in mappings 14

Reading hierarchical data in mappings 15

Writing hierarchical data in mappings 16

MongoDB lookups in mapping tasks 16

Writing to an empty collection 17

Rules and guidelines for MongoDB Connector 17

Partitioning 18

- Key range partitioning 18

Appendix A: Data type reference 20

MongoDB and transformation data types 20

Index 22

Preface

Use *MongoDB Connector* to learn how to read from or write to MongoDB by using Cloud Data Integration. Learn to create a connection, develop mappings, and run mapping tasks and dynamic mapping tasks in Cloud Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

Informatica Intelligent Cloud Services web site

You can access the Informatica Intelligent Cloud Services web site at http://www.informatica.com/cloud. This site contains information about Informatica Cloud integration services.

Informatica Intelligent Cloud Services Communities

Use the Informatica Intelligent Cloud Services Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the Informatica Intelligent Cloud Services Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

Informatica Intelligent Cloud Services Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

Informatica Intelligent Cloud Services Trust Center

The Informatica Intelligent Cloud Services Trust Center provides information about Informatica security policies and real-time system availability.

You can access the trust center at https://www.informatica.com/trust-center.html.

Subscribe to the Informatica Intelligent Cloud Services Trust Center to receive upgrade, maintenance, and incident notifications. The Informatica Intelligent Cloud Services Status page displays the production status of all the Informatica cloud products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single component or all Informatica Intelligent Cloud Services components. Subscribing to all components is the best way to be certain you never miss an update.

To subscribe, on the Informatica Intelligent Cloud Services Status page, click **SUBSCRIBE TO UPDATES**. You can choose to receive notifications sent as emails, SMS text messages, webhooks, RSS feeds, or any combination of the four.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the Informatica Intelligent Cloud Services Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introduction to MongoDB Connector

You can use MongoDB Connector to connect to a MongoDB database from Data Integration. You can use MongoDB Connector to read data from or write data to collections in a MongoDB Atlas database. You can use a MongoDB document as a source and as a target in mapping tasks and mappings.

When you run a task or mapping, the Secure Agent uses the Simba MongoDB JDBC driver to connect to MongoDB. The Simba MongoDB JDBC driver can create virtual tables to normalize data in MongoDB collections, such as array or object.

You can use MongoDB Connector to integrate and migrate data from diverse data sources to MongoDB.

You can use the connection for the following data integration scenarios:

- Aggregate data from MongoDB and other source systems, transform the data, and write the data to MongoDB.
- Migrate data from a relational database or other data sources to MongoDB. For example, you want to migrate data from a relational database to MongoDB. You can write data from multiple relational database tables with different schemas to the same MongoDB collection. A MongoDB collection contains the data in a MongoDB database.
- Migrate data from MongoDB to a data warehouse for reporting. For example, your organization uses a business intelligence tool that does not support MongoDB. You must migrate the data from MongoDB to a data warehouse so that the business intelligence tool can use the data to generate reports.

MongoDB Connector assets

You can perform insert, update, and delete operations on a MongoDB target.

When you use MongoDB Connector, you can include the following Data Integration assets:

- Mapping
- Mapping task

For more information about configuring assets and transformations, see *Mappings*, *Transformations*, and *Tasks* in the Data Integration documentation.

Virtual tables

The Simba MongoDB JDBC driver creates virtual tables if the column family contains collections such as arrays and objects.

Virtual tables depict the renormalized view of a MongoDB collection. You can use virtual tables as sources and targets in mappings.

The Simba MongoDB JDBC driver creates a virtual table for each collection in the column family. The virtual table for a collection uses the following naming convention by default: `<original column family name>_<original collection name>`

Each virtual table has a foreign key column that references back to the primary key column in the original collection. The key column uses the following naming convention by default: `<original collection name>.<primary key column name>`

The virtual table has an index column that shows the position of the data within the original array. The index column uses the following naming convention by default: `<original column name>_index`

Other columns in the virtual table represent the elements in the array and are named after the array element. If the array is of scalar type, the data column uses the following naming convention by default: `<original column name>_value`

When you use a virtual table in a mapping, you can perform read, insert, and update operations on a virtual table.

Note: You cannot perform upsert or delete operation on a virtual table.

Virtual tables example

The collection CustomerTable contains arrays. You want to create virtual tables from the arrays and import the virtual tables as data objects in Informatica Cloud.

The following table shows the schema of CustomerTable collection:

id	Customer Name	Invoices	Service Level	Contacts	Ratings
1111	John	[{invoice_id=123,item=toaster, price=456,discount=0.2}, {invoice_id=124,item=oven, price=12345, discount=0.3}]	Silver	[{type=primary,name="John Johnson"}, {type=invoicing,name="Jane Johnson"}]	[7,8]
2222	Jane	[{invoice_id=125,item=blender, price=7456,discount=0.5},	Gold	[{type=primary,name="Jane Johnson"}	[5,6]

If you enable virtual table detection, the driver creates the following virtual tables:

CustomerTable

The main table uses the same name as the original table that it represents.

The following table shows the schema of CustomerTable virtual table:

id	Customer Name	Number of Invoices	Service Level	Number of Contacts	Number of Ratings
1111	John	2	Silver	2	2
2222	Jane	1	Gold	1	2

CustomerTable_Invoices

The following table shows the schema of CustomerTable_Invoices virtual table:

CustomerTable.id	Invoices_index	invoice_id	item	price	discount
1111	1	123	toaster	456	0.2
1111	2	124	oven	12345	0.3
2222	1	125	blender	7456	0.5

CustomerTable_Contacts

The following table shows the schema of CustomerTable_Contacts virtual table:

CustomerTable.id	Contacts_index	type	name
1111	1	primary	John Johnson
1111	2	invoicing	Jane Johnson
2222	1	primary	Jane Johnson

CustomerTable_Ratings

The following table shows the schema of CustomerTable_Ratings virtual table:

CustomerTable.id	Ratings_index	Ratings_value
1111	1	7
1111	2	8
2222	1	5
2222	2	6

CHAPTER 2

MongoDB connections

Use a MongoDB connection to access a MongoDB table.

Use a MongoDB connection to read data from or write data to collections in a MongoDB Atlas database. Use a MongoDB connection to import MongoDB documents, preview data, and run mappings. When you create a MongoDB connection, you define the connection attributes that Data Integration uses to connect to the MongoDB database.

For more information about connecting to MongoDB Atlas Database, see Connecting to MongoDB Atlas Database from Cloud Data Integration.

MongoDB connection properties

When you set up a MongoDB connection, configure the connection properties.

Important: MongoDB Connector is deprecated and has been moved to maintenance mode. Informatica intends to drop support in a future release.

The following table describes the MongoDB connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent, Hosted Agent, serverless, or elastic runtime environment. For more information about how to configure and use the runtime environments, see *Runtime Environments* in the Administrator help.
Host Name*	Host name or IP address of the MongoDB server.
Port*	MongoDB server port number. Default is 27017.
User Name*	User name to access the MongoDB server.
Password*	Password corresponding to the user name to access the MongoDB server.

Property	Description
Database Name	Name of the MongoDB database to connect to.
Additional Connection Properties	The JDBC connection parameters required in a MongoDB connection. Enter one or more JDBC connection parameters in the following format: <param1>=<value>&<param2>=<value>&<param3>=<value> Provide the JDBC parameters as ampersand-separated key-value pairs. Configure the following JDBC connection parameters in a MongoDB connection: - AuthSource - BatchSize - connectTimeoutMS - DefaultStringColumnLength - DmlBatchSize - EnableDoubleBuffer - EnableTransaction - LogLevel - LogPath - SamplingLimit - SamplingStepSize - SamplingStrategy For example, DefaultStringColumnLength=512&DmlBatchSize=1000& EnableDoubleBuffer=false&EnableTransaction=true& SamplingLimit=200&SamplingStepSize=2&SamplingStrategy=Backwards
SSL Mode	SSL mode indicates the encryption type to use for the connection. SSL is not applicable when you use the Hosted Agent. You can configure SSL when you use the Secure Agent or the serverless runtime environment. **Note:** Set it to **Required** for connecting to MongoDB Atlas.
SSL Truststore Path	Not applicable for MongoDB Connector.
SSL Truststore Password	Not applicable for MongoDB Connector.
*If you specify the host name, port, user name, and password of the MongoDB server in the connection properties and also in the additional connection properties field, the values in the additional connection properties take precedence.	

For more information about configuring the MongoDB JDBC connection parameters, see the Informatica How-To Library article, "Configuring the Simba MongoDB JDBC Driver Options for MongoDB Connector":

https://docs.informatica.com/integration-cloud/cloud-data-integration-connectors/h2l/configuring-the-simba-mongodb-jdbc-driver-options-for-mongodb-co/abstract.html

CHAPTER 3

Mappings and mapping tasks with MongoDB

Use the Data Integration Mapping Designer to create a mapping. When you create a mapping, you configure a source or a target to represent a MongoDB table or virtual table.

Validate the mapping and describe the flow of data from source to target, along with the required transformations before the Secure Agent reads data from or writes data to the MongoDB target.

Use the Mapping Task wizard to create a mapping task and select the mapping that you configured. The mapping task processes data based on the data flow logic you define in the mapping. Run the mapping task to read data from or write data to a MongoDB table.

Configure preSQL and postSQL commands for MongoDB sources and targets

You can specify **preSQL** and **postSQL** advanced properties for MongoDB sources and targets.

You can perform the following operations by using preSQL and postSQL commands:

- INSERT
- UPDATE
- DELETE

Note: You cannot perform more than one operation with a preSQL or postSQL command.

MongoDB sources in mappings

To read data from MongoDB, configure a MongoDB object as the Source transformation in a mapping.

Specify the name and description of the MongoDB source. Configure the source, query options, and advanced properties for the source object.

The following table describes the source properties that you can configure for a MongoDB source:

Property	Description
Connection	Name of the MongoDB source connection.
Source Type	Type of the MongoDB source objects available. Select one of the following types: - Single Object. Reads from a single object. - Multiple Objects. Reads from multiple objects. Related objects appear based on simple primary key-foreign key relationship. You can use the Advanced Relationship option to define the relationship for objects that you want to join. - Query. Not applicable. - Parameter. Parameterizes the object name. You can configure the source object in a mapping task associated with a mapping that uses this source transformation. You can read data from a single MongoDB source object, multiple objects, or parameterize the object.
Object	Name of the MongoDB source object based on the source type selected.
Filter	Configure a simple filter or an advanced filter to remove rows at the source. You can improve efficiency by filtering early in the data flow. A simple filter includes a field name, operator, and value. Use an advanced filter to define a more complex filter condition, which can include multiple conditions using the AND or OR logical operators.

The following table describes the query options that you can configure in a Source transformation:

Property	Description
Filter	Filter value in a read operation. Click **Configure** to add conditions to filter records and reduce the number of rows that the Secure Agent reads from the source. You can specify the following filter conditions: - **Not parameterized**. Use a basic filter to specify the object, field, operator, and value to select specific records. - **Completely parameterized**. Use a parameter to represent the field mapping. - **Advanced**. Use an advanced filter to define a more complex filter condition on an object. You can configure filter conditions for columns of the following data types: - Date - Double - Float - Integer - String
Sort	Sorts records based on the conditions you specify. Click **Configure** to add conditions to sort records and reduce the number of rows that the Secure Agent reads from the source. You can specify the following sort conditions: - Not parameterized. Select the fields and type of sorting to use. - Parameterized. Use a parameter to specify the sort option.

The following table describes the advanced properties that you can configure for a MongoDB source:

Property	Description
preSQL	SQL statement that you want to run before reading data from the source. For example, if you want to insert records in the database before you read the records from the table, specify the following preSQL statement: `INSERT INTO cloud.employees ("name", "uid") VALUES('James', 2012)`

postSQL	SQL statement that you want to run after reading data from the source.
	For example, if you want to update records in a table after you read the records from a table, specify the following postSQL statement:
	`UPDATE cloud.employees`
	`SET uid = 2011 WHERE uid=2014`

You can set the tracing level in the advanced properties to determine the amount of detail that appears in the logs.

The following table describes the tracing levels that you can configure:

Property	Description
Terse	The Secure Agent logs initialization information, error messages, and notification of rejected data.
Normal	The Secure Agent logs initialization and status information, errors encountered, and skipped rows due to transformation row errors. Summarizes session results, but not at the level of individual rows.
Verbose Initialization	In addition to normal tracing, the Secure Agent logs additional initialization details, names of index and data files used, and detailed transformation statistics.
Verbose Data	In addition to verbose initialization tracing, the Secure Agent logs each row that passes into the mapping. Also notes where the Secure Agent truncates string data to fit the precision of a column and provides detailed transformation statistics. When you configure the tracing level to verbose data, the Secure Agent writes row data for all rows in a block when it processes a transformation.

Joining multiple objects

When you create a Source transformation, you can select multiple MongoDB objects as the source type and then configure an advanced relationship to combine the tables.


Perform the following steps to join multiple objects in a Source transformation:

1. In the Source transformation properties, select the **Source Type** as **Multiple Objects**.
2. From the **Actions** menu, select **Add Source Object**, and then select the source object that you want to add from the displayed list.

3. From the **Related Objects Actions** menu, and select the Advanced Relationship option to define the relationship between the tables.

   Note: The Add Related Objects option is not applicable.

   The following image shows an advanced relationship condition defined between MongoDB tables:



   Note: You can join only two source tables. You must define only the join condition, not the complete join query.

MongoDB targets in mappings

To write data to a MongoDB target, configure a MongoDB object as the Target transformation in a mapping.

Specify the name and description of MongoDB target. Configure the target and advanced properties for the target object.

The following table describes the target properties that you can configure for a MongoDB target:

Property	Description
Connection	Name of the MongoDB connection that is associated with a dataset.
Target Type	Type of the MongoDB target objects available. - Single Object. Reads from a single JDBC object. - Parameter. Parameterizes the object name. You can write data to multiple MongoDB target objects.
Object	Name of the MongoDB target object based on the target type selected.

Property	Description
Operation	You can select one the following operations: - Insert - Update - Delete **Note:** You cannot perform a delete operation on a MongoDB virtual table.
Update columns	Specifies the default primary key column and temporary key columns to update or delete target data. If the MongoDB target does not include a primary key column, and the mapping is configured to perform an update or delete task operation, click **Add** to add the primary key column and temporary key columns. You must select the default primary key column and the temporary key columns. Select the key columns to update data to or delete data from the MongoDB target table. By default, no columns are specified.

The following table describes the advanced properties that you can configure for a MongoDB target:

Property	Description
preSQL	SQL statement that you want to run before writing data to the target. For example, if you want to insert records into the database before you write the records into the table, specify the following preSQL statement: `INSERT INTO cloud.employees ("name", "uid") VALUES('Presq_src', 2012)`

postSQL	SQL statement that you want to run after writing the data into the target.
	For example, if you want to update records in a table after you write the records into the table, specify the following postSQL statement:
	`UPDATE cloud.employees`
	`SET uid = 2011 WHERE uid=2014`

Bulk Mode	Performs bulk upload when you configure an insert, update, or delete operation to write data to a MongoDB target. Select this option to improve the performance of inserting, updating, or deleting data in bulk from MongoDB.
Batch Size	The number of rows that the Secure Agent writes in a single batch to MongoDB. Specify a batch size value that is greater than zero. Applicable if you select the **Bulk Mode** check box. **Note:** To gain better performance it is recommended that the batch size value is less than or equal to 1000.
Forward Rejected Rows	Determines whether the transformation passes rejected rows to the next transformation or drops rejected rows. By default, the agent forwards rejected rows to the next transformation.

Reading hierarchical data in mappings

To preserve the hierarchical structure when you read data from MongoDB and write data to relational targets, you must use a Hierarchy Parser transformation.

The Hierarchy Parser transformation processes JSON input from the source transformation and provides relational output to the target transformation. The Hierarchy Parser transformation converts hierarchical input based on the sample schema of the MongoDB table that you associate with the transformation and the way that you map the data.

Writing hierarchical data in mappings

When you read data from relational sources and write data to a MongoDB target, you must use a Hierarchy Builder transformation.

The Hierarchy Builder transformation processes relational input from the upstream transformation and provides JSON output to the downstream transformation. The Hierarchy Builder transformation produces JSON output based on the sample schema of the MongoDB table that you associate with the transformation and the way that you map the data.

MongoDB lookups in mapping tasks

You can create lookups for objects in a MongoDB connection. You can retrieve data from a MongoDB lookup object based on the specified lookup condition.

When you configure a lookup in MongoDB, you select the lookup connection and lookup object. You also define the behavior when a lookup condition returns more than one match.

You can create the following lookups when you configure field mappings in a mapping task:

- Cached lookup
- Uncached lookup
- Connected lookup
- Unconnected lookup

For more information about the Lookup transformation, see *Transformations* in the Data Integration documentation.

The following table describes the MongoDB lookup object properties that you can configure in a Lookup transformation:

Property	Description
Connection	Name of the lookup connection.
Source Type	Type of the source object. You can select one of the following options: - Single Object - File List - Command - Parameter

Property	Description
Lookup Object	Name of the lookup object for the mapping.
Multiple Matches	Behavior when the lookup condition returns multiple matches. You can select one of the following options: - Return first row - Return last row - Return any row - Return all rows - Report error

You can set the tracing level in the advanced properties to determine the amount of detail that appears in the logs.

The following table describes the tracing levels that you can configure:

Property	Description
Terse	The Secure Agent logs initialization information, error messages, and notification of rejected data.
Normal	The Secure Agent logs initialization and status information, errors encountered, and skipped rows due to transformation row errors. Summarizes session results, but not at the level of individual rows.
Verbose Initialization	In addition to normal tracing, the Secure Agent logs additional initialization details, names of index and data files used, and detailed transformation statistics.
Verbose Data	In addition to verbose initialization tracing, the Secure Agent logs each row that passes into the mapping. Also notes where the Secure Agent truncates string data to fit the precision of a column and provides detailed transformation statistics. When you configure the tracing level to verbose data, the Secure Agent writes row data for all rows in a block when it processes a transformation.

Writing to an empty collection

You can write data to empty MongoDB targets only in JSON mode by mapping the **DocumentAsJSON** field from the source to the target, through which you can write the entire MongoDB source collection to the MongoDB target collection.

Rules and guidelines for MongoDB Connector

Consider the following guidelines when you use a MongoDB connection in a mapping:

- You cannot use MongoDB Connector to read or write MongoDB column or table names that have more than 65 characters.
- You cannot fetch the details of the rejected rows when you write data to a Mongo DB target.

- If you want to configure a filter condition for the date data type in a mapping, you must specify the `EnableUTCTimeZone=true` property in the **Additional Connection Properties** field in the MongoDB connection. If you do no set the property and use the filter condition, the date from the MongoDB collection is converted to the local timezone that might lead to incorrect row selection.
- When you run a mapping with multiple pre-SQL and post-SQL queries in the advanced properties of a MongoDB source or target, the mapping fails.

Partitioning

When you read data from a MongoDB source, you can configure key range partitioning to optimize the mapping performance at run time.

Key range partitioning

You can configure key range partitioning when you use a mapping task to read data from MongoDB sources. With key range partitioning, the Secure Agent distributes rows of source data based on the fields that you define as partition keys. The Secure Agent compares the field value to the range values for each partition and sends rows to the appropriate partitions.

Use key range partitioning for columns that have an even distribution of data values. Otherwise, the partitions might have unequal size. For example, a column might have 10 rows between key values 1 and 1000 and the column might have 999 rows between key values 1001 and 2000. If the mapping includes multiple sources, use the same number of key ranges for each source.

When you define key range partitioning for a column, the Secure Agent reads the rows that are within the specified partition range. For example, if you configure two partitions for a column with the ranges as 10 through 20 and 30 through 40, the Secure Agent does not read the rows 20 through 30 because these rows are not within the specified partition range.

You can configure a partition key for fields of the following data types:

- String
- Integer

Configuring key range partitioning


Perform the following steps to configure key range partitioning for MongoDB sources:

1. In the Source Properties, click the **Partitions** tab.
2. Select the required partition key from the list.

3. Click **Add New Key Range** to define the number of partitions and the key ranges based on which the Secure Agent must partition data.

   Use a blank value for the start range to indicate the minimum value. Use a blank value for the end range to indicate the maximum value.

   The following image displays the **Partitions** tab:



APPENDIX A

Data type reference

Data Integration uses the following data types in mappings, synchronization tasks, and mapping tasks with MongoDB:

MongoDB native data types

MongoDB data types appear in the **Fields** tab for Source and Target transformations when you choose to edit metadata for the fields.

Transformation data types

Set of data types that appear in the transformations. They are internal data types based on ANSI SQL-92 generic data types, which the Secure Agent uses to move data across platforms. Transformation data types appear in all transformations in a mapping.

When Data Integration reads source data, it converts the native data types to the comparable transformation data types before transforming the data. When Data Integration writes to a target, it converts the transformation data types to the comparable native data types.

MongoDB and transformation data types

The following table describes the data types that Data Integration supports for MongoDB sources and targets:

MongoDB Data Types	Transformation Data Types	Range and Description
Array	NA	Simba MongoDB JDBC driver re-normalizes the data in the array into virtual tables.
Boolean	String	Precision of 1
Date	Date/Time	Jan 1, 0001 A.D. to Dec 31, 9999 A.D. (precision to second)
NumberDouble	Double	Precision 15
NumberInt	Integer	Precision 10, scale 0
NumberLong	Decimal	Precision 1 to 28 digits, scale 0 to 28

MongoDB Data Types	Transformation Data Types	Range and Description
Object	NA	Simba MongoDB JDBC driver re-normalizes the data in the object into virtual tables.
ObjectID	String	1 to 104,857,600 characters
String	String	1 to 104,857,600 characters

INDEX

C

Cloud Application Integration community
  URL 4
Cloud Developer community
  URL 4
configuring key range
  partitioning 18

D

Data Integration community
  URL 4

I

Informatica Global Customer Support
  contact information 5
Informatica Intelligent Cloud Services
  web site 4

L

lookup
  database 16
  MongoDB 16
  multiple matches 16
  role 16
  schema 16

M

maintenance outages 5
mapping
  MongoDB sources 11
  MongoDB targets 14
mapping tasks
  overview 11
mappings
  lookup overview 16
  lookup properties 16
MongoDB connection
  rules and guidelines 17
MongoDB connections
  overview 9
  properties 9
MongoDB connector
  supported task and object types 6
MongoDB Connector
  overview 6
MongoDB data types
  mapping to transformation data types 20
  overview 20

P

Partitioning
  key range 18
post SQL commands
  entering 11
pre SQL commands
  entering 11

S

status
  Informatica Intelligent Cloud Services 5
system status 5

T

trust site
  description 5

U

upgrade notifications 5

V

virtual table
  collection 7
  list 7
  map 7
  set 7
virtual tables
  example 7

W

web site 4