Informatica® Cloud Data Integration

Veeva Vault Connector

Informatica Cloud Data Integration Veeva Vault Connector
July 2026

© Copyright Informatica LLC 2025, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at https://www.informatica.com/legal/patents.html.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-07-10

Table of Contents

Preface 4

Informatica Resources 4

- Informatica Documentation 4
- IDMC web site 4
- IDMC Communities 4
- IDMC Marketplace 4
- Data Integration connector documentation 5
- Informatica Knowledge Base 5
- IDMC Trust Center 5
- Informatica Global Customer Support 5

Chapter 1: Introduction to Veeva Vault Connector 6

Veeva Vault Connector assets 6

Chapter 2: Connections for Veeva Vault 7

Prepare for authentication 7

- Basic 7
- Authorization code 7

Connect to Veeva Vault 8

- Before you begin 8
- Connection details 8
- Authentication types 8

Chapter 3: Mappings and mapping tasks with Veeva Vault Connector 12

Before you begin 12

- Setting the staging property for write operation 12

Veeva Vault sources in mappings 13

- Filter options and operators 14
- Multiple source objects 15

Veeva Vault targets in mappings 15

Rules and guidelines for Veeva Vault objects 16

Chapter 4: Data type reference 18

Veeva Vault and transformation data types 18

Chapter 5: Troubleshooting 20

Troubleshooting Veeva Vault Mappings 20

Index 21

Preface

Use Veeva Vault Connector to learn how to read from or write to the Veeva Vault customer relationship management (CRM) application by using Data Integration. Learn to create a Veeva Vault connection, develop and run mappings, and mapping tasks in Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security, compliance, and privacy practices.

You can access the trust center at https://trust.informatica.com/.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introduction to Veeva Vault Connector

You can use Veeva Vault Connector to access the Veeva Vault customer relationship management (CRM) application from Data Integration. Use the Veeva Vault connection to securely read data from or write data to Veeva Vault objects, which represent the data model in Veeva Vault.

Veeva Vault is a cloud-based enterprise platform that manages regulated content and data in life sciences. Veeva Vault Connector communicates with the Vault APIs that enable access to Veeva Vault.

You can create a Veeva Vault connection and use the connection as a source and target in mappings and mapping tasks. When you run mappings or mapping tasks, the Secure Agent reads from and writes to the Veeva Vault CRM application based on the workflow and Veeva Vault connection configuration.

You can also read from multiple Veeva Vault objects and filter data before the data enters the data flow.

Veeva Vault Connector assets

Create assets in Data Integration to integrate data using Veeva Vault Connector.

When you use Veeva Vault Connector, you can include the following Data Integration assets:

- Mapping
- Mapping task

For more information about configuring assets and transformations, see *Mappings*, *Transformations*, and *Tasks* in the Data Integration documentation.

CHAPTER 2

Connections for Veeva Vault

Create a Veeva Vault connection to securely read data from or write data to Veeva Vault objects.

You can use a Veeva Vault connection to specify sources and targets in mappings and mapping tasks.

Prepare for authentication

You can configure basic and authorization code authentication types to access Veeva Vault.

Before you configure the connection properties, you need to keep the authentication details handy based on the authentication type that you want to use.

Basic

To connect to Veeva Vault using basic authentication, you need the Veeva Vault DNS name, API version, account user name, and password.

Get the required details from the Veeva Vault CRM application to which you want to connect.

For more information about basic authentication in Veeva Vault, see User name and password in the Veeva Vault documentation.

Authorization code

To connect to Veeva Vault using the OAuth 2.0 authorization code, you need the Veeva Vault DNS name, API version, authorization URL, access token URL, client ID, scope, OAuth profile ID, and access token.

To get the authorization details, you need to create an authorization integration in Veeva Vault and register the following Informatica redirect URL in Veeva Vault Integration using OAuth 2.0 / OpenID Connect Profiles:

`https://<Informatica cloud hosting facility for your organization>/ma/proxy/oauthcallback`

If the access token expires and the response returns a 401 error code, the Informatica redirect URL, which is outside the customer firewall, tries to connect to the endpoint and retrieves a new access token.

For more information about how to create an authorization integration and get the authorization details, see Configuring OAuth 2.0 / OpenID Connect Profiles in the Veeva Vault documentation.

Connect to Veeva Vault

Let's configure the Veeva Vault connection properties to connect to Veeva Vault.

Before you begin

Before you get started, you'll need to get the relevant configuration details from your Veeva Vault account based on the authentication type that you want to configure.

Check out "Prepare for authentication" on page 7 to learn more about the authentication prerequisites.

Connection details

The following table describes the basic connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select which credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent or elastic runtime environment. For more information about how to configure and use the runtime environments, see *Runtime Environments* in the Administrator help.

Authentication types

You can configure basic and authorization code authentication types to access Veeva Vault.

Select the required authentication method and then configure the authentication-specific parameters.

Basic authentication

Basic authentication is the default type and the minimum requirement for a basic authentication is the Veeva Vault DNS name, API version, account user name, and password.

The following table describes the basic connection properties for basic authentication:

Property	Description

Vault DNS	The DNS name for the Veeva Vault endpoint.
	Enter the DNS name in the following format:
	`https://<Domain address>.veevavault.com`
	For example, if your domain address is <MyDomain>, enter the following DNS name:
	`https://<MyDomains>.veevavault.com`

API Version	The Veeva Vault API version you want to connect to. Enter the Veeva Vault API version 24.3.
User Name	The user name to connect to the Veeva Vault account.
Password	The password to connect to the Veeva Vault account.

Advanced settings

The following table describes the advanced connection properties for basic authentication:

Property	Description
Retry Count	The maximum number of retry attempts made to receive a response from the Veeva Vault endpoint.
Retry Interval	The time in milliseconds to wait before the Veeva Vault connection retries to receive a response.

Additional Properties	The additional parameters that you can configure when connecting to Veeva Vault.
	You can enter multiple additional parameters, each separated by an ampersand with colon (&:), in the following format:
	`<parameter name1>=<value1>&:<parameter name2>=<value2>&:<parameter name3>=<value3>...`
	Default is
	`okhttp.retryStatusCodes=429,500,502,503,504&:okhttp.connectTimeout=30&:okhttp.readTimeout=30&:ok`
	.

Authorization code authentication

The minimum requirement for an authorization code authentication is the Veeva Vault DNS name, API version, authorization URL, access token URL, client ID, scope, OAuth profile ID, and access token.

The following table describes the basic connection properties for authorization code authentication:

Property	Description

Vault DNS	The DNS name for the Veeva Vault endpoint.
	Enter the DNS name in the following format:
	`https://<Domain address>.veevavault.com`
	For example, if your domain address is <MyDomain>, enter the following DNS name:
	`https://<MyDomains>.veevavault.com`

API Version	The Veeva Vault API version you want to connect to. Enter the Veeva Vault API version 24.3.
Authorization URL	The Veeva Vault OAuth 2.0 authorization server that is used to authorize the user request. Enter the authorization URL in the following format: `https://<Host name of the authorization server>/oauth2/v2.0/authorize`
Access Token URL	The Veeva Vault OAuth 2.0 authorization server that is used to exchange the authorization code to get an access token. Enter the access token URL in the following format: `https://<Host name of the authorization server>/oauth2/v2.0/token`
Client ID	The client identifier of your application generated when you configure the application for OAuth.
Scope	The scope of the access request when the Veeva Vault endpoint has defined custom scopes. You can enter multiple scope attributes, each separated by a space, in the following format: `<Scope attribute1> <Scope attribute2> <Scope attribute3>...`
OAuth Profile ID	The unique identifier assigned to your OAuth profile in Veeva Vault.
Access Token	The access token granted by the authorization server to access the Veeva Vault data. Enter the populated access token value that you get from the OAuth endpoint, or click **Generate Access Token** to populate the access token value.

Advanced settings

The following table describes the advanced connection properties for authorization code authentication:

Property	Description
Retry Count	The maximum number of retry attempts made to receive a response from the Veeva Vault endpoint.
Retry Interval	The time in milliseconds to wait before the Veeva Vault connection retries to receive a response.

Additional Properties	The additional parameters that you can configure when connecting to Veeva Vault.
	You can enter multiple additional parameters, each separated by an ampersand with colon (&:), in the following format:
	`<parameter name1>=<value1>&:<parameter name2>=<value2>&:<parameter name3>=<value3>...`
	Default is
	`okhttp.retryStatusCodes=429,500,502,503,504&:okhttp.connectTimeout=30&:okhttp.readTimeout=30&:ok`
	.

CHAPTER 3

Mappings and mapping tasks with Veeva Vault Connector

You can configure a mapping to read from or write to Veeva Vault CRM applications.

You can configure a Source or Target transformation to represent a Veeva Vault object. Add the Source and Target transformations in the mapping canvas and configure the Veeva Vault source and target properties accordingly. Use the Data Integration Mapping Designer to define and configure a mapping for Veeva Vault sources and targets.

Before you begin

Before you configure and run a mapping, verify that you have the required permissions on the Veeva Vault objects that you read from or write to Veeva Vault.

For more information about the required permissions, see Accessing Vault Admin in the Veeva Vault documentation.

Additionally, when you write to Veeva Vault, verify that you have the API and application level permissions.

For more information about the API and application level permissions, see Related permissions in the Veeva Vault documentation.

Setting the staging property for write operation

Before you configure a mapping to write data to Veeva Vault, enable the staging property for the write operation.

To enable the staging property, set the value of the *INFA_DTM_STAGING_ENABLED_CONNECTORS* Tomcat property to the plugin ID of Veeva Vault Connector in the Secure Agent properties.

1. Log in to Informatica® Intelligent Data Management Cloud™ (IDMC).
2. Select **Administrator** > **Runtime Environments**.
3. On the **Runtime Environments** page, select the Secure Agent machine that runs the mapping.
4. Click **Edit**.
5. In the **System Configuration Details** section, select **Data Integration Server** as the service and **Tomcat** as the type.

6. Edit the *INFA_DTM_STAGING_ENABLED_CONNECTORS* property and set its value to *651901*, which is the plugin ID of Veeva Vault Connector.



7. Click **Save**.

Veeva Vault sources in mappings

To read data from Veeva Vault, configure a Veeva Vault object as a source in a mapping.

Specify the name and description of the Veeva Vault source. Configure the source, query options, and advanced properties for the source object.

The following table describes the source properties that you can configure for a Veeva Vault source:

Property	Description
Connection	Name of the source connection. You can select an existing connection, create a new connection, or define parameter values for the source connection property. To overwrite the source connection properties at runtime, select the **Allow parameter to be overridden at run time** option.
Source Type	Type of the source object. Select one of the following source types: - Single Object. Select to specify a single Veeva Vault source object. - Multiple Objects. Select to specify multiple Veeva Vault source objects. - Parameter. Select to specify a parameter where you define values that you want to update without having to edit the mapping. Default is Single Object.
Object	The source object for the task. You can choose objects only from the vobjects data model. Select the source object for a single source. When you select multiple source objects as the source type, you can add multiple source objects and configure a relationship between them.
Parameter	This property appears only if you select parameter as the source type. A placeholder to dynamically assign values at run time for the source object without the requirement to edit the task. Select an existing parameter for the source object or click **New Parameter** to define a new parameter for the source object. To overwrite the parameter at runtime, select the **Allow parameter to be overridden at run time** option.

The following table describes the query options that you can configure for a Veeva Vault source:

Property	Description
Filter	Filters records based on the filter condition in a read operation. You can configure a simple filter or an advanced filter to filter rows from the source. You can improve efficiency by filtering early in the data flow. Click **Configure** to add conditions to filter records from the data that the Secure Agent reads from the source. Select one of the following filter options from the list: - Not Parameterized. Uses a basic filter to specify the object, field, operator, and value to select specific records. - Completely Parameterized. Uses a parameter to represent the filter condition. - Advanced. Uses an advanced filter to define a complex filter condition. Default is Not Parameterized. For more information about filters and operators that you can configure, see "Filter options and operators" on page 14.
Sort	Not applicable.

The following table describes the advanced source properties that you can configure for a Veeva Vault source:

Property	Description
Page Size	Determines the number of rows to read in each request. Specify 0 to read all rows from the source. Default is 0.
Page Offset	Sets the number of rows you can skip from the beginning of the dataset before returning the result. For example, you can set this property to n to skip the first n rows in a source and read from the (n+1) row. Default is 0.
Tracing Level	Determines the amount of detail that appears in the log file. Select one of the following options from the list: - Terse - Normal - Verbose Initialization - Verbose Data Default is Normal.

Filter options and operators

You can configure the Source transformation to filter data before the data enters the data flow. Use either a simple or advanced filter.

To filter data, configure the source query options on the **Source** tab of the Source transformation. Expand the **Query Options** section, and configure the filter condition.

When you configure a filter, you can use the following operators in a filter expression:

- = (Equals)
- <> (Not equals)

- < (Less than)
- < = (Less or equal)
- > (Greater than)
- > = (Greater or equals)
- Is Null
- Is Not Null

Multiple source objects

You can configure the Source transformation to read from multiple Veeva Vault objects.

To read from Veeva Vault related objects in a mapping, select **Multiple Objects** as the **Source Type**.

You can define relationships between the objects by selecting **Add Related Objects** or **Advanced Relationship** from the **Related Objects Actions** menu.

For more information about creating advanced relationships, see "Advanced relationships" in *Transformation* in the Data Integration help.

Veeva Vault targets in mappings

To write data to Veeva Vault, configure a Veeva Vault object as a target in a mapping.

Specify the name and description of the Veeva Vault target. Configure the target and advanced properties for the target object.

The following table describes the target properties that you can configure for a Veeva Vault target:

Property	Description
Connection	Name of the target connection. You can select an existing connection or create a new connection, or define parameter values for the target connection property. To overwrite the target connection properties at run time, select the **Allow parameter to be overridden at run time** option.
Object Type	Type of the target object. Select one of the following object types: - Single Object. Select to specify a single Veeva Vault target object. - Parameter. Select to specify a parameter where you define values that you want to update without having to edit the mapping. Default is Single Object.
Object	The target object for the task. Select the target object for a single target.

Property	Description
Parameter	This property appears only if you select parameter as the object type. A placeholder to dynamically assign values at run time for the target object without the requirement to edit the task. Select an existing parameter for the target object or click **New Parameter** to define a new parameter for the target object. To overwrite the parameter at runtime, select the **Allow parameter to be overridden at run time** option.
Operation	Type of the target operation. Select one of the following operations from the list: - Insert - Update - Upsert (Update or Insert) - Delete - Data Driven. Not applicable Default is Insert.
Update Columns	This property appears only if you select update, upsert, or delete as the operation type. Select the unique key column as the condition field for the update, upsert, or delete operation in a Veeva Vault target.
Data Driven Condition	Not applicable.

The following table describes the advanced target properties that you can configure for a Veeva Vault target:

Property	Description
Staging File Directory	The directory on the Secure Agent machine where target data is temporarily stored before the mapping writes data to Veeva Vault.
Update As Upsert	Upserts data to the target. Select when you choose the operation type as **Upsert (Update or Insert)** and perform both the update and insert operations on the target. Default is disabled.
Forward Rejected Rows	Determines whether the transformation passes rejected rows to the next transformation or drops them. By default, the mapping task forwards rejected rows to the next transformation. If you select the **Forward Rejected Rows** option, the Secure Agent flags the rows as rejected and writes them to the reject file. If you don't select the **Forward Rejected Rows** option, the Secure Agent drops the rejected rows and writes them to the session log file. The Secure Agent does not write the rejected rows to the reject file. Default is enabled.

Rules and guidelines for Veeva Vault objects

Consider the following rules and guidelines for Veeva Vault objects used as sources and targets in mappings and mapping tasks:

General guidelines

Consider the following general guidelines when you configure mappings or mapping tasks:

- You can't display field names by labels when you configure source fields in a mapping or mapping task.
- You can't write column names with the leading or trailing spaces to the Veeva Vault target. The mapping trims these spaces from column names when it writes to the target.

Filter operations

Consider the following rules and guidelines when you filter data from Veeva Vault sources in mappings or mapping tasks:

- When you use a simple source filter with a Veeva Vault source object that contains Boolean or Date data types, ensure that you use the following formats in the filter condition:
  - Boolean: 0 or 1
  - Date: YYYY-MM-DD HH24:MM:SS.US
- To use advanced data filters to filter data from a Veeva Vault source, ensure that the filter condition contains only the field name, operator, and field value. Remove the object name that is added before the field name in the filter condition.
- You can't use the Contains, Starts With, or Ends With operators in a filter operation. Otherwise, the mapping fails.

Multiple source objects

Consider the following rules and guidelines when you read data from multiple Veeva Vault sources in mappings or mapping tasks:

- You can't read data from a related object configured with self-referencing relationships.
- When you configure a mapping to read data from a related object that is defined with multiple relationships, you can select only one relationship instead of all relationships.
- You can't use a simple filter to filter data from a related object when the parent object contains the same field name as specified in the filter condition for the related object. Otherwise, the mapping fails.

Data types

When you write data of the Attachment data type to a flat file from a Veeva Vault object, ensure that you change the Binary transformation data type to the String native data type using an Expression transformation in a mapping. Otherwise, the mapping writes incorrect data to the target.

CHAPTER 4

Data type reference

Data Integration uses the following data types in mappings and mapping tasks with Veeva Vault.

Native data types

Veeva Vault data types appear in the Source and Target transformations when you choose to edit metadata for the fields.

Transformation data types

Set of data types that appear in the transformation. They are internal data types based on ANSI SQL-92 generic data types, which Data Integration uses to move data across platforms. Transformation data types appear in all remaining transformations in mappings, or mapping tasks.

When Data Integration reads source data, it converts the native data types to the comparable transformation data types before transforming data. When Data Integration writes to a target, it converts the transformation data types to the comparable native data types.

Veeva Vault and transformation data types

Use only the compatible Veeva Vault data types in mappings and mapping tasks to read from or write to a Veeva Vault CRM application.

The following table lists the Veeva Vault data types that you can use with Veeva Vault Connector, along with the corresponding transformation data types:

Veeva Vault Data Type	Transformation Data Type
Attachment	Binary
Boolean	String
Component	String
Date	Date
DateTime	Datetime
ID	String
LongText	String

Veeva Vault Data Type	Transformation Data Type
Number	Decimal
Object	String
PickList	String
RichText	String
String	String

CHAPTER 5

Troubleshooting

Use the following section to troubleshoot errors that you might encounter when you use Veeva Vault Connector.

Troubleshooting Veeva Vault Mappings

The mappings fail when you write a large number of data to the target.

When you write a large number of data to the Veeva Vault target, the mappings might fail with the following error:

```
SDKS_38619 Exception occured while uploading the staged file
```

To troubleshoot this issue, increase the heap size by setting the JVM option in the Secure Agent properties.

For more information about how to increase the heap size, see the Increase Java heap size Knowledge article.

INDEX

C

Cloud Application Integration community
  URL 4
Cloud Developer community
  URL 4

D

Data Integration community
  URL 4
data types
  Veeva Vault applications 18

I

Informatica Global Customer Support
  contact information 5
Informatica Intelligent Data Management Cloud
  web site 4

M

maintenance outages 5
mapping
  mapping task 12, 14
  Multiple source objects 15

S

status
  IDMC 5
system status 5

T

trust site
  description 5

U

upgrade notifications 5

V

Veeva Vault
  assets 6
  data types 18
Veeva Vault connections 8
Veeva Vault Connector
  overview 6
Veeva Vault source and target objects
  rules and guidelines 16
Veeva Vault sources
  mapping 13
Veeva Vault targets
  mapping 15

W

web site 4