Informatica® Intelligent Cloud Services
October 2026

Data Integration Connections

Informatica Intelligent Cloud Services Data Integration Connections
October 2026

© Copyright Informatica LLC 2006, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices and AI assistant acknowledgements are included with the product.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-10-16

Table of Contents

Preface 5

Informatica Resources 5

Informatica Documentation 5

IDMC web site 5

IDMC Communities 5

IDMC Marketplace 5

Data Integration connector documentation 6

Informatica Knowledge Base 6

IDMC Trust Center 6

Informatica Global Customer Support 6

Chapter 1: Connectors and connections 7

Add-on connectors 7

Installing an add-on connector 7

Chapter 2: Connection configuration 9

Configuring a connection 10

Connection property format 12

Configuring a connection using sample data 14

Viewing connection dependencies 14

Chapter 3: Connection properties 16

Chapter 4: FTP/SFTP Connections 17

FTP/SFTP Connection Properties 17

Key exchange algorithms and ciphers 18

FTP/SFTP Connection Rules and Guidelines 19

Chapter 5: Large Language Model connection 20

Prepare for authentication 20

Get the API key 20

Configure an API request for a custom model 21

Connect to Large Language Model 22

Before you begin 22

Connection details 22

Chapter 6: REST V3 connection properties 25

Authorization Code Authentication 26

Client Credential Authentication 29

Rules and guidelines for REST V3 connections 31

Chapter 7: SAP BAPI connection **32**

Prerequisites 32

Download and configure the SAP libraries 32

Configure SAP user authorization 33

Connect to SAP BAPI 34

Before you begin 34

Connection details 34

Advanced settings 35

Configure SAP BAPI Connector as a business service 35

Configure the serverless runtime environment 36

Configure the elastic runtime environment 37

Index **39**

Preface

Use *Data Integration Connections* to learn how to configure connections between Data Integration and cloud and on-premises applications, platforms, databases, and flat files. Refer to *Data Integration Connections* for information about the connection properties for all connectors that can be used with Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security policies and real-time system availability.

You can access the trust center at https://www.informatica.com/trust-center.html.

Subscribe to the IDMC Trust Center to receive upgrade, maintenance, and incident notifications. The Informatica Intelligent Data Management Cloud Status page displays the production status of all the Informatica cloud products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single component or all IDMC components. Subscribing to all components is the best way to be certain you never miss an update.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Connectors and connections

Connections provide access to data in cloud and on-premise applications, platforms, databases, and flat files. They specify the location of sources, lookup objects, and targets that are included in a task.

You use connectors to create connections. You can create a connection for any connector that is installed in IDMC. Many connectors are pre-installed. However, you can also use a connector that is not pre-installed by installing an add-on connector created by Informatica or an Informatica partner.

Add-on connectors

Add-on connectors provide connectivity for connection types that are not installed by default in IDMC.

When you install an add-on connector, the connector becomes available as a connection type for the organization and all sub-organizations. Users can create connections of this type and use them in tasks. Some connectors require configuration before you can use them.

If your organization includes sub-organizations, you install add-on connectors in the parent organization. You cannot install add-on connectors in a sub-organization. If a sub-organization should not use a connector that is available to the parent organization, disable the connector license for the sub-organization.

For information about individual connectors, see the help for the appropriate connector.

If you have a request for a connector that is not yet available, or if you would like information about building a connector, contact Informatica Global Customer Support.

Installing an add-on connector

You can install a free trial version of an IDMC add-on connector, or you can buy the connector from Informatica. After you install an add-on connector, it becomes available as a connection type for the organization and all sub-organizations.

Note: If you want to install an add-on connector for use in a sub-organization, install the connector in the parent organization. You cannot install an add-on connector in a sub-organization.

1. In Administrator, select **Add-On Connectors**.
2. Perform either of the following steps:
   - To start a free trial for an IDMC Connector, click **Free Trial** for the connector, and confirm that you want to start the free trial.

- To buy a license for a connector with an expired free trial, click **Contact Us**.

  An Informatica representative will contact you.

After you install the connector, it is displayed on the **Add-On Connectors** page with the message, "Connector Available," and the connection type becomes available to your organization and sub-organizations. The connection type uses the naming convention `<connector name> (<publisher name>)`, for example, "Teradata (Informatica Cloud)."


CHAPTER 2

Connection configuration

When you configure a connection, the connection becomes available for use within the organization. If you use sub-organizations and you want a connection to be available to multiple sub-organizations, create the connection in each sub-organization.

Configure connections on the **Connections** page. The **Connections** page lists all of the connections that have been configured in the organization. You can create a connection on this page. You can also search for an existing connection by name or description, by name only, or by description only.

The following image shows the **Connections** page:



When you configure a connection, you specify the runtime environment for the connection. The runtime environment must contain an agent that is running. You can override the runtime environment in the connection from the mapping or mapping task.

The runtime environment manages the connection between IDMC and the connection endpoint. It helps you perform the following tasks:

- Test the connection to the endpoint.
- Display objects available for the connection and retrieve metadata when you use the connection in an asset. You can preview data in the source, target, or lookup object selected in the asset.
- Run assets that use the connection to read from a source, transform data, or write data to a target.

You can configure a connection to a database, cloud data warehouse, or other endpoint type. When you create a source or target connection to a database or cloud data warehouse, you connect to a table, alias, or view. For example, when you create a Snowflake Data Cloud connection, you connect to a Snowflake table or

view. For more information about creating connections to different types of endpoints, see the help for the appropriate connector.

When you configure connections for sources and targets in a mapping or task, where the connections require you to specify the code page, ensure that the code pages are the same. If the source system and target system in a task use different code pages, the IDMC might load unexpected data to the target.

You can delete any connection that you create as long as the connection is not used by a saved query or task.

Configuring a connection

You can create a connection for connectors that are installed in IDMC. You can create a connection on the **Connections** page in Administrator or when you create a source, target, or lookup object in a mapping or task in Data Integration.

When you configure a connection, you specify properties for the connection. Connection properties enable an agent to connect to data sources.

1. Configure the following connection details:


Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + - Maximum length is 100 characters. Connection names are not case sensitive.
Description	Description of the connection. Maximum length is 255 characters.

2. If your organization use an external secrets manager to store sensitive connection credentials, perform the following steps:
   a. In the Connection Properties area, select **Use Secret Vault**.

b. Enable the slider next to each property that you store in the secrets manager, and then enter the secret name, including the path, in the corresponding field. If the secret is a JSON object, you'll also need to include the secret key.

For example, you configure a relational connection and you store the database password in HashiCorp Vault. The secret name is `secret/data/MyCredentials`, and the secret key is `MyPassword`. To retrieve the password from HashiCorp Vault, select **Use Secret Vault**, enable the slider next to the **Password** field, and enter `secret/data/MyCredentials:MyPassword` in the **Password** field.

The following image shows the connection details:



For more information about formatting the connection property, see "Connection property format" on page 12.

Note: Basic Authentication is offered as an authentication method for some connections. For optimal security, you should choose another method because Basic Authentication is the simplest and least secure authentication method.

3. Select the runtime environment to be used with the connection.

   If you use an external secrets manager, all Secure Agents within the runtime environment must be installed on a local machine or VM and must be able to access the secrets manager. Additionally, the SecretManagerApp service must be running on each agent.

   For more information about runtime environments, see *Runtime Environments* in the Administrator documentation.

4. Configure the connection-specific properties.

   For example, if you configure a flat file connection, enter the directory where the files are stored, the date format for date fields in the files, and the code page of the system that hosts the files.

5. To test the connection, click **Test Connection**.

6. Click **Save**.

Connection property format

To configure a connection property to retrieve its value from a secrets manager, first enable the slider next to the property. Then enter the secret name, including the path, in the corresponding field. If the secret is a JSON object, you'll also need to include the secret key.

The following table shows the value to enter based on the format of the secret:

Format of secret	Format of value to enter


JSON object, for example:
`{`
`"engine": "mysql",`
`"username": "tsmith",`
`"password": "Hello123",`
`"host": "my-database-endpoint.us-west-2.rds.amazonaws.com",`
`"dbname": "myDatabase",`
`"port": "1234"`
`}`
	`<secret name>:<key>`
	If you use AWS Secrets Manager, you can also enter the secret in the following format:*
	`<secret ARN>:<key>`

Simple value, for example: `--name "MyPassword" --value "Hello123"`	`<secret name>` If you use AWS Secrets Manager, you can also enter the full ARN of the secret.*
* If you use AWS Secrets Manager and the account that hosts the Secure Agent differs from the account that hosts the secrets, you must enter the secret using the full ARN.	

Example: Connection property format for AWS Secrets Manager

You want to configure a connection to retrieve a password from AWS Secrets Manager.

The following image shows the secret:



The secret name is `qa/demo/test`, the secret ARN is `arn:aws:secretsmanager:us-east-2:2*********6:secret:qa/demo/test-zUxff*****F`, and the key is `password`.

Enter either of the following values for the **Password** connection property:


- `qa/demo/test:password`
- `arn:aws:secretsmanager:us-east-2:2*********6:secret:qa/demo/test-zUxff*****F:password`

  Note: If the account that hosts the Secure Agent differs from the account that hosts the secrets, you must enter the password in this format.

Example: Connection property format for Azure Key Vault

You want to configure a connection to retrieve a password from Azure Key Vault. The password is stored in a secret named "nestedkey."

The following image shows the secret:



The secret is stored in the following format:

```
{
"name":"Morpheus",
   "job":"Leader",
   "id":"199",
   "dbdetails":{
      "uname": "root",
      "password": "passw0rd"
   }
}
```


Enter the following value for the **Password** connection property:

`nestedkey:dbdetails:password`

Example: Connection property format for HashiCorp Vault

You want to configure a connection to retrieve a password from HashiCorp Vault.

The following image shows the secret:



The secret name is `secret/mysql/webapp` and the key is `password`.

Enter the following value for the **Password** connection property:

`secret/mysql/webapp:password`

Configuring a connection using sample data

You can configure a connection to use sample data. You might want to use sample data when you want to test a mapping without affecting your organization's data.

When you configure a connection to use sample data, you can choose a mock connector from a variety of connector types such as Snowflake, Google BigQuery, and Salesforce. The connection properties are already configured.

1. On the **New Connection** page, select **Sample Data**.
2. Select a mock connector to use for the connection and click **OK**.


Viewing connection dependencies

You can view object dependencies for connections. When you view object dependencies for connections, Administrator lists the runtime environments that the connection uses as well as the assets in each service that use the connection.

To view object dependencies for a connection, on the Connections page, click the **Show Dependencies** icon.

The **Dependencies** page opens with showing the Uses tab by default. To see the assets that use the connection, select the Used By tab.

The following image shows the asset dependencies on the Used By tab for a connection:



To sort the objects that appear on the page, click the sort icon and select the column name for the property you want to sort by.

To filter the objects that appear on the dependencies page, click the **Filter** icon. Use filters to find specific objects. To apply a filter, click **Add Field**, select the property to filter by, and then enter the property value. You can specify multiple filters. For example to find a mapping called "MyMapping," add the Type filter and specify Mapping. Then add the Name filter and enter "MyMapping."

CHAPTER 3

Connection properties

When you configure a connection, you specify the connection properties for the connection. Connection properties enable an agent to connect to data sources.

You can create a connection for connectors that are installed in IDMC.

For more information about the properties that you need to configure to create a connection to a particular endpoint, see the help for the appropriate connector.

CHAPTER 4

FTP/SFTP Connections

File Transfer Protocol (FTP) connections enable you to use FTP to access source and target files. Secure File Transfer Protocol (SFTP) connections use secure protocols, such as SSH, to access source and target files.

When you configure an FTP/SFTP connection, you define the following directories:

Local directory

Directory local to the Secure Agent that contains a copy of the source or target files.

Remote directory

Location of the files you want to use as sources or targets.

IDMC validates the file in the local directory, not the remote directory. When you configure FTP/SFTP connections, ensure that the local directory contains valid copies of all source and target files. When you configure a task with an FTP/SFTP connection, IDMC uses the file structure of the local file to define the source or target for the task. The file structure of the local file must match the source or target file in the remote directory. IDMC also uses the local file to generate data preview. If the data in the local file does not match the data in the source or target file in the remote directory, data preview might display inaccurate results.

When IDMC runs a data integration task with a FTP/SFTP target connection, it creates a target file based on the target defined in the task. As it completes the task, IDMC writes the target file to the remote directory, overwriting the existing file.

FTP/SFTP Connection Properties

The following table describes the FTP/SFTP connection properties:

Connection property	Description
Runtime Environment	Runtime environment that contains the Secure Agent to use to access the files.
User Name	User name used to log in to the FTP server.
Password	Password for the user name used to log in to the FTP server.
Host	Host name or IP address of the FTP/SFTP host.

Connection property	Description
Port	Network port number used to connect to FTP/SFTP connection. Default port is 21 for FTP and 22 for SFTP.
Local Directory	Directory on a local machine that stores the local file. The local machine must also run the Secure Agent used to run the corresponding task. Enter a local directory or use the Browse button to select a local directory.
Remote Directory	Directory on the FTP/SFTP host that stores the remote flat file. Depending on the FTP/SFTP server, you might have limited options to enter directories. For more information, see the FTP/SFTP server documentation.
Date Format	Date format for date fields in the flat file. Default date format is: MM/dd/yyyy HH:mm:ss
Code Page	Code page compatible with the system where the source or target flat file resides. Select one of the following code pages: - MS Windows Latin 1. Select for ISO 8859-1 Western European data. - UTF-8. Select for Unicode data. - Shift-JIS. Select for double-byte character data. - ISO 8859-15 Latin 9 (Western European). - ISO 8859-2 Eastern European. - ISO 8859-3 Southeast European. - ISO 8859-5 Cyrillic. - ISO 8859-9 Latin 5 (Turkish). - IBM EBCDIC International Latin-1. - Japanese EUC (with \ <-> Yen mapping - IBM EBCDIC Japanese - IBM EBCDIC Japanese CP939 - PC Japanese SJIS-78 syntax (IBM-942) - PC Japanese SJIS-90 (IBM-943) - MS Windows Traditional Chinese, superset of Big 5 - Taiwan Big-5 (w/o euro update) - Chinese EUC - ISO 8859-8 Hebrew - PC Hebrew (old) - PC Hebrew (w/o euro update) - EBCDIC Hebrew (updated with new sheqel, control characters)
This is a Secure FTP Connection	Indicates whether the connection is secure or not secure. Select to create an SFTP connection.

Key exchange algorithms and ciphers

You can use the following key exchange algorithms and ciphers for SFTP connections:

Key exchange algorithms

- diffie-hellman-group14-sha1
- diffie-hellman-group-exchange-sha1
- diffie-hellman-group1-sha1

Ciphers

- aes256-ctr
- aes192-ctr
- aes128-ctr
- aes256-cbc (rijndael-cbc@lysator.liu.se)
- aes192-cbc
- aes128-cbc
- 3des-cbc
- blowfish-cbc
- cast128-cbc
- arcfour
- arcfour128
- none

FTP/SFTP Connection Rules and Guidelines

Consider the following rules and guidelines for FTP/SFTP connections:

- IDMC does not lock the target file while writing to the file. To prevent data corruption, verify that only one task writes to a target file at any given time.
- If metadata in the local target file and remote target file are different, IDMC overwrites the metadata of the remote target file with the local target file at run time.
- To find the row count of rows loaded into the local target file, open the job details from the **All Jobs** or **My Jobs** page.
- In Windows, you cannot select FTP/SFTP directory on a mapped drive through the **Browse for Directory** dialog box. You can access a network directory by browsing My Network Places. You can also enter the directory with the following format:

  ```
  \\<server_name>\<directory_path>
  ```

  If the **Browse for Directory** dialog box does not display My Network Places, you might need to configure a network login for the Secure Agent service.
- Error messages for FTP/SFTP connections might only reference FTP or SFTP. Read any error message that references FTP or SFTP as an error message for an FTP/SFTP connection.

CHAPTER 5

Large Language Model connection

Create a Large Language Model connection to connect to Azure OpenAI or a custom model provider.

You can use the chat model from Azure OpenAI or a custom model provider to process and interpret unstructured data within an intelligent structure model. Use the embedding model in Azure OpenAI to generate vector embeddings in a Vector Embedding transformation.

Note: Large Language Model connection is specifically designed to interface with large language models. You can use this connection only within an intelligent structure model and a Vector Embedding transformation. You cannot use this connection to directly read from or write to models in the way other connectors handle databases or files.

Prepare for authentication

Before you configure a Large Language Model connection, you need to keep the authentication details handy based on the model provider.

- To connect to Azure OpenAI, get the API key and endpoint URL of your Azure OpenAI account from the Azure portal.
- To connect to a custom model provider, get the API request details such as parameters, headers, and body for the custom model provider.

Get the API key

You need the API key and endpoint URL to make API calls to the Azure OpenAI chat model or embedding model.

1. Log in to the Azure portal and open the Azure OpenAI service.
2. Click the name of the Azure OpenAI resource that you want to connect to.
3. On the **Overview** page, click **Explore Azure AI Foundry portal**.
4. Under **Shared resources**, click **Deployments**.
5. On the **Model deployments** tab, click the name of the chat or embedding model for which you need the API key and endpoint URL.
6. On the **Details** tab, copy the key and the endpoint URL.

Configure an API request for a custom model

You can connect to a custom model provider through a REST API and use the chat model to process and interpret unstructured data within an intelligent structure model.

When you configure a Large Language Model connection, you can specify the API request details to connect to a custom model provider in the **Configuration** field.

Consider the following examples for an API request for large language models from different model providers:

GrokAI model

```
{
    "headers": {
        "Content-Type": "application/json",
        "Authorization":"Bearer {{API_KEY}}"
    },
    "body": {
        "messages": [
        {
          "role": "system",
          "content": "{{system_message}}"
        },
        {
          "role": "user",
          "content": "{{user_message}}"
        }
      ],
      "model": "grok-4-latest",
      "stream": false,
      "temperature": 0
    }
}
```

Self-hosted Llama model

```
{
    "headers": {
        "Content-Type": "application/json"
    },
    "params": {
        "key": "{{API_KEY}}"
    },
    body:
    {
       "messages":
       [
           {"role": "system", "content": "You are a helpful assistant."},
           {"role": "user", "content": "Say hello!"}
       ]
    }
}
```

Self-hosted Mistral AI model

```
{
    "headers": {
        "Content-Type": "application/json",
        "api-key": "{{API_KEY}}"
    },
    "body": {
        "messages": [
            {
                "role": "user",
                "content": "{{user_message}}"
            }
        ],
        "model": "mistral-small",
        "temperature": 0.7,
```

```
            "max_tokens": 100
        }
    }
```

Connect to Large Language Model

Let's configure a Large Language Model connection to connect to Azure OpenAI. You can use the chat model in Azure OpenAI to process and interpret unstructured data within an intelligent structure model. Use the embedding model to generate vector embeddings in a Vector Embedding transformation.

Note: Large Language Model connection is specifically designed to interface with large language models. You can use this connection only within an intelligent structure model and a Vector Embedding transformation. You cannot use this connection to directly read from or write to models in the way other connectors handle databases or files.

Before you begin

Before you create a Large Language Model connection, you'll need to get the the API key and endpoint URL of your Azure OpenAI account to connect to Azure OpenAI.

To connect to a custom model provider, get the API request details such as parameters, headers, and body for the custom model provider.

Check out Prepare for authenticationon page 20 to learn about the authentication requirements before you configure a connection.

If you want to use the chat model in Azure OpenAI to generate an intelligent structure model, you must enable Python integration to interact with the APIs and pre-process data.

For more information about how to enable Python integration, see *Components* in the Data Integration help.

Connection details

The following table describes the connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.

Property	Description
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select which credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent or elastic runtime environment. Hosted Agent is not applicable.
Model Category	The type of large language model. Select one of the folowing options: - Chat. To use conversation APIs to process and interpret unstructured data within an intelligent structure model. - Embedding. To use text embedding APIs to generate vector embeddings in a Vector Embedding transformation.
Model Provider	The provider of the large language model. Select one of the following options: - Azure OpenAI. To use a chat model or embedding model in Azure OpenAI. - Custom. To use a chat model from a custom model provider.
Authentication	The authentication type to connect to the selected model provider. Select API Key.

Endpoint	The endpoint URL of the large language model API provided by the model provider.
	Example for Chat model:
	`https://<RESOURCE_NAME>/openai/deployments/<DEPLOYMENT_NAME>/chat/completions?api-version=<API_VERSION>`
	Example for Embedding model:
	`https://<RESOURCE_NAME>/openai/deployments/<DEPLOYMENT_NAME>/embeddings?api-version=<API_VERSION>`

Property	Description
API Key	The API key of your account used to authenticate access to the large language model APIs.

Configuration	This property applies only to a chat model.
	The API request details to connect to a custom model provider.
	The following example shows the `params`, `headers`, and `body` components in an API request for Google Gemini:
	`{`
	`"headers": { "Content-Type": "application/json" },`
	`"params": { "key": "{{API_KEY}}" },`
	`"body": {"contents": [`
	`{"parts": [`
	`{`
	`"text": "{{user_message}}"`
	`}`
	`]`
	`}`
	`],`
	`"system_instruction": {`
	`"parts": [`
	`{`
	`"text": "{{system_message}}"`
	`}`
	`]`
	`},`
	`"generationConfig": {`
	`"temperature": 0.7,`
	`"seed": 42`
	`}`
	`}`
	`}`

CHAPTER 6

REST V3 connection properties

When you set up a REST V3 connection, you must configure the connection properties.

When you create a connection, you can specify the following authentication methods:

- None. Does not require an authentication method to connect to the REST endpoint.
- Basic. Requires user ID and password to connect to the REST endpoint.
- OAuth 2.0 authorization code. Requires an authorization server to connect to the REST endpoint. Authorization Code allows authorized access to the endpoint without sharing or storing your credentials.
- OAuth 2.0 client credentials. Requires client ID and client secret to connect to the REST endpoint.

The following table describes the REST V3 connection properties for a basic authentication type connection:

Connection property	Description
Runtime Environment	Name of the runtime environment where you want to run the tasks. Specify a Secure Agent or serverless runtime environment.
Auth Type	The authentication method that the connector must use to connect to the REST endpoint. Select **Basic**. Default is None.
Auth User ID	The user name to log in to the web service application when you select the Basic authentication type.
Auth Password	The password associated with the user name when you select the Basic authentication type.
TrustStore File Path	The absolute path of the truststore file that contains the TLS certificate to establish a one-way or two-way secure connection with the REST API. Ensure that the truststore file is in .jks format. Specify a directory path that is available on each Secure Agent machine in the runtime environment.
TrustStore Password	The password for the truststore file that contains the SSL certificate.
KeyStore File Path	The absolute path of the keystore file that contains the keys and certificates required to establish a two-way secure communication with the REST API. Ensure that the keystore file is in .jks format. Specify a directory path that is available on each Secure Agent machine in the runtime environment.

Connection property	Description
KeyStore Password	The password for the keystore file required for secure communication.
Proxy Type	Type of proxy. You can select one of the following options: - None. Bypasses the proxy server configured at the agent or the connection level. - Custom. Considers proxy configured at the connection level. - Platform. Considers proxy configured at the agent level. Proxy is not applicable when you use the serverless runtime environment.
Proxy Host	The IP address or host name of the proxy server. Required only for the Custom proxy type.
Proxy Port	The port number of the proxy server. Required only for the Custom proxy type.
Proxy User	The user name for the proxy server. Required only for the Custom proxy type.
Proxy Password	The password for the proxy server. Required only for the Custom proxy type.
Connection Timeout	The wait time in seconds to get a response from a REST endpoint. The connection ends after the connection timeout is over. Default is 60 seconds. **Note:** If you define both the REST V3 connection timeout and the endpoint API timeout, the connection ends at the shortest defined timeout.
Retry Attempts	Number of times to retry the connection when 100, 300, 400, and 500 series error codes are returned in the response. Default is 0. Specify 0 to disable the retry attempts. In case of 408 error code, silent retries are attempted. Therefore, the number of retry attempts can be more than the value you specify.
Retry Delay	The wait time in seconds before a retry is attempted. Default is 0.
HTTP version	The HTTP version to connect to the REST endpoint. You can select one of the following options: - HTTP 2 - HTTP 1.1 Default is HTTP 2.

Authorization Code Authentication

To use authorization code authentication, you must first register the following Informatica redirect URL in your application:

`https://<Informatica cloud hosting facility for your organization>/ma/proxy/oauthcallback`

If the access token expires and the error codes `400`, `401`, and `403` are returned in the response, Informatica redirect URL, which is outside the customer firewall, tries to connect to the endpoint and retrieve a new access token.

The following table describes the REST V3 connection properties for an OAuth 2.0 authorization code authentication type connection:

Connection property	Description
Runtime Environment	Name of the runtime environment where you want to run the tasks. Specify a Secure Agent or serverless runtime environment.
Auth Type	The authentication method that the connector must use to connect to the REST endpoint. Select **OAuth 2.0 authorization code**. Default is None.
Authorization Token URL	Authorization server URL configured in your application.
Access Token URL	Access token URL configured in your application.
Client ID	The client identifier issued during the application registration process.
Client Secret	The client secret issued during the application registration process.
Scope	The scope of the access request when the REST endpoint has defined custom scopes. Enter space-separated scope attributes. For example: `root_readonly root_readwrite manage_app_users`
Access Token Parameters	Additional parameters to use with the access token URL. Define parameters in the JSON format. For example: `[{"Name":"resource","Value":"https://<serverName>"}]`
Authorization Code Parameters	Additional parameters to use with the authorization token URL. Define parameters in the JSON format. For example: `[{"Name":"max_age","Value":60},{"Name":"state","Value":"test"}]`
Client Authentication	The client authentication details for authorization. Select an option to send Client ID and Client Secret for authorization either in the request body or in the request header. Default is **Send client credentials in body**.
Generate Access Token	Generates access token and refresh token based on the authentication details provided.
Access Token	The access token granted by the authorization server to access the data using a specific role. Enter the access token value or click **Generate Access Token** to populate the access token value. To pass the generate access token call through a proxy server, you must configure a proxy server at the Secure Agent level. The REST V3 connection-level proxy configuration does not apply to the generate access token call.

Connection property	Description
Refresh Token	Allows the Secure Agent to fetch new access token if the access token is not valid or expires. Enter the refresh token value or click **Generate Access Token** to populate the refresh token value. If the refresh token expires, you must either provide a valid refresh token or click **Generate Access Token** to regenerate a new refresh token.
TrustStore File Path	The absolute path of the truststore file that contains the TLS certificate to establish a one-way or two-way secure connection with the REST API. Ensure that the truststore file is in .jks format. Specify a directory path that is available on each Secure Agent machine in the runtime environment.
TrustStore Password	The password for the truststore file that contains the SSL certificate.
KeyStore File Path	The absolute path of the keystore file that contains the keys and certificates required to establish a two-way secure communication with the REST API. Ensure that the keystore file is in .jks format. Specify a directory path that is available on each Secure Agent machine in the runtime environment.
KeyStore Password	The password for the keystore file required for secure communication.
Proxy Type	Type of proxy. You can select one of the following options: - None. Bypasses the proxy server configured at the agent or the connection level. - Custom. Proxy configured at the connection level is considered. - Platform. Proxy configured at the agent level is considered. Proxy is not applicable when you use the serverless runtime environment.
Proxy Host	The IP address or hostname of the proxy server. Required only for the Custom proxy type.
Proxy Port	The port number of the proxy server. Required only for the Custom proxy type.
Proxy User	The user name for the proxy server. Required only for the Custom proxy type.
Proxy Password	The password for the proxy server. Required only for the Custom proxy type.
Connection Timeout	The wait time in seconds to get a response from a REST endpoint. The connection ends after the connection timeout is over. Default is 60 seconds. **Note:** If you define both the REST V3 connection timeout and the endpoint API timeout, the connection ends at the shortest defined timeout.
Retry Attempts	Number of times to retry the connection when 100, 300, 400, and 500 series error codes are returned in the response. Default is 0. Specify 0 to disable the retry attempts. In case of 408 error code, silent retries are attempted. Therefore, the number of retry attempts can be more than the value you specify.

Connection property	Description
Retry Delay	The wait time in seconds before a retry is attempted. Default is 0.
HTTP version	The HTTP version to connect to the REST endpoint. You can select one of the following options: - HTTP 2 - HTTP 1.1 Default is HTTP 2.

Client Credential Authentication

The following table describes the REST V3 connection properties for OAuth 2.0 client credentials authentication type connection:

Connection property	Description
Runtime Environment	Name of the runtime environment where you want to run the tasks. Specify a Secure Agent or serverless runtime environment.
Auth Type	The authentication method that the connector must use to connect to the REST endpoint. Select **OAuth 2.0 client credentials**. Default is None.
Access Token URL	Access token URL configured in your application.
Client ID	The client identifier issued during the application registration process.
Client Secret	The client secret issued during the application registration process.
Scope	The scope of the access request when the rest endpoint has defined custom scopes. Enter space-separated scope attributes. For example: `root_readonly root_readwrite manage_app_users`
Access Token Parameters	Additional parameters to use with the access token URL. Define parameters in the JSON format. For example: `[{"Name":"resource","Value":"https://<serverName>"}]`
Client Authentication	The client authentication details for authorization. Select an option to send Client ID and Client Secret for authorization either in the request body or in the request header. Default is **Send client credentials in body**.
Generate Access Token	Generates access token based on the authentication details provided.

Connection property	Description
Access Token	The access token granted by the authorization server to access the data using a specific role. Enter the access token value or click **Generate Access Token** to populate the access token value. To pass the generate access token call through a proxy server, you must configure a proxy server at the Secure Agent level. The REST V3 connection-level proxy configuration does not apply to the generate access token call.
TrustStore File Path	The absolute path of the truststore file that contains the TLS certificate to establish a one-way or two-way secure connection with the REST API. Ensure that the truststore file is in .jks format. Specify a directory path that is available on each Secure Agent machine in the runtime environment.
TrustStore Password	The password for the truststore file that contains the SSL certificate.
KeyStore File Path	The absolute path of the keystore file that contains the keys and certificates required to establish a two-way secure communication with the REST API. Ensure that the keystore file is in .jks format. Specify a directory path that is available on each Secure Agent machine in the runtime environment.
KeyStore Password	The password for the keystore file required for secure communication.
Proxy Type	Type of proxy. You can select one of the following options: - None. Bypasses the proxy server configured at the agent or the connection level. - Custom. Considers proxy configured at the connection level. - Platform. Considers proxy configured at the agent level. Proxy is not applicable when you use the serverless runtime environment.
Proxy Host	The IP address or host name of the proxy server. Required only for the Custom proxy type.
Proxy Port	The port number of the proxy server. Required only for the Custom proxy type.
Proxy User	The user name for the proxy server. Required only for the Custom proxy type.
Proxy Password	The password for the proxy server. Required only for the Custom proxy type.
Connection Timeout	The wait time in seconds to get a response from a REST endpoint. The connection ends after the connection timeout is over. Default is 60 seconds. **Note:** If you define both the REST V3 connection timeout and the endpoint API timeout, the connection ends at the shortest defined timeout.

Connection property	Description
Retry Attempts	Number of times to retry the connection when 100, 300, 400, and 500 series error codes are returned in the response. Default is 0. Specify 0 to disable the retry attempts. In case of 408 error code, silent retries are attempted. Therefore, the number of retry attempts can be more than the value you specify.
Retry Delay	The wait time in seconds before a retry is attempted. Default is 0.
HTTP version	The HTTP version to connect to the rest endpoint. You can select one of the following options: - HTTP 2 - HTTP 1.1 Default is HTTP 2.

Rules and guidelines for REST V3 connections

Consider the following rules and guidelines for Rest V3 connections:

- Test the connection to verify if the mandatory parameters are valid.
- You can configure proxy at the agent level or connection level. See the following table to understand the proxy settings that take precedence when you define the System proxy and proxy at the connection level:

System Proxy	REST V3 Connection Attribute			Result
	No Proxy	Platform Proxy	Custom Proxy	
No	Yes	No	No	Does not consider proxy.
No	No	Yes	No	Does not consider proxy.
No	No	No	Yes	Considers Custom proxy.
Yes	Yes	No	No	Does not consider proxy.
Yes	No	Yes	No	Considers Platform proxy.
Yes	No	No	Yes	Considers Custom proxy.

CHAPTER 7

SAP BAPI connection

Create an SAP BAPI connection to access data from SAP through an SAP BAPI function.

You can use an SAP BAPI connection in the Web Services transformation, and then use the Web Services transformation in a mapping or mapping task.

Prerequisites

Before you use an SAP BAPI connection, the SAP administrator needs to perform certain prerequisite tasks to configure the Secure Agent machine and SAP system.

To process SAP BAPI functions, you also need to verify if the required licenses are enabled for the SAP system.

Download and configure the SAP libraries

To access SAP data through an SAP BAPI function, you need to download and configure the SAP JCo libraries on the Secure Agent machine. If you encounter any issues while you download libraries, contact SAP Customer Support.

1. Go to the SAP Support Portal, and then click **Software Downloads**.

   Note: You need to have SAP credentials to access **Software Downloads** from the SAP Support Portal.

2. Download the latest version of the 64-bit SAP JCo libraries based on the operating system of the machine on which the Secure Agent runs.

Operating System	SAP JCo Libraries
Windows	- sapjco3.jar - sapjco3.dll
Linux	- sapjco3.jar - libsapjco3.so

3. Copy the JCo libraries to the following directory:
   `<Informatica Secure Agent installation directory>\apps\Data_Integration_Server\ext\deploy_to_main\bin\rdtm-extra\tpl\sap`

   Create the `deploy_to_main\bin\rdtm-extra\tpl\sap` directory if it does not already exist.

4. Log in to Informatica Intelligent Cloud Services and configure the JAVA_LIBS property for the Secure Agent.
   a. Select **Administrator** > **Runtime Environments**.
   b. Click **Runtime Environments** to access the **Runtime Environments** page.
   c. To the left of the agent name, click **Edit Secure Agent**.
   d. From the **Service** list, select **Data Integration Server**.
   e. From the **Type** list, select **Tomcat JRE**.
   f. Enter the JAVA_LIBS value based on the operating system of the machine on which the Secure Agent runs.

Operating System	Value
Windows	..\bin\rdtm-extra\tpl\sap\sapjco3.jar;..\bin\rdtm\javalib\sap\sap-adapter-common.jar
Linux	../bin/rdtm-extra/tpl/sap/sapjco3.jar:../bin/rdtm/javalib/sap/sap-adapter-common.jar

   Warning: If you copy the value directly from the table, the hyphens (-) in the value might be incorrectly copied. Copy the value to a text editor and make sure that the value you copied is not corrupted.



   g. Click **Save**.
   h. Repeat steps 2 through 4 on every machine where you installed the Secure Agent.
5. Restart the Secure Agent.

Configure SAP user authorization

Configure the SAP user account in the SAP system to enable data exchange through the SAP BAPI functions.

The following table lists the object and authorizations required to configure user permissions to access and process data through the SAP BAPI functions:

Read Object Name	Authorization
S_RFC	SYST, SDTX, SDIFRUNTIME, RFC1, RFC2

For more information about these authorizations and how to use them, see SAP user authorizations.

Connect to SAP BAPI

Let's configure the SAP BAPI connection properties to connect to SAP and process data through the SAP BAPI functions.

Before you begin

Before you get started, you'll need to configure the Secure Agent machine and SAP system to establish an SAP BAPI connection.

Check out "Prerequisites" on page 32 to learn more about these tasks.

Connection details

The following table describes the basic connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select which credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent, serverless, or elastic runtime environment. For more information about how to configure a serverless environment, see "Configure the serverless runtime environment" on page 36. For more information about how to configure a elastic environment, see "Configure the elastic runtime environment" on page 37.
Authentication	The authentication type to access the SAP system and process data through the SAP BAPI functions. Select the **BAPI Connection** authentication type and then configure the authentication-specific parameters.
Username	The user name with the appropriate user authorization to connect to the SAP account.
Password	The password to connect to the SAP account.
Host Name	The host name or IP address of the SAP server to which you want to connect.

Property	Description
Client	The client number of the SAP server. Get the required client number from the SAP system to which you want to connect.
Language	Language code that corresponds to the SAP language. Get the required language code from the SAP system to which you want to connect.
System Number	The system number of the SAP server. Get the required system number from the SAP system to which you want to connect.

Advanced settings

The following table describes the advanced connection properties:

Property	Description
SAP Additional Parameters	Additional SAP properties that the Secure Agent uses to connect to the SAP system as an RFC client. See the following examples where you can use this field to configure additional parameters for the connection: - To create a load balancing connection, define the additional arguments listed in the following sample: `GROUP=interfaces MSHOST=<Message server hostname> R3NAME=<System ID or name of SAP system>` SAP infers the connection type based on the parameters that you specify. For example, if you define the GROUP, MSHOST, and R3NAME parameters, SAP infers the connection type as a load balancing connection. The GROUP parameter defines the group name of the SAP application server. The MSHOST parameter defines the host name of the SAP message server. The R3NAME parameter defines the system ID or name of the SAP system. - To commit data to the SAP system with each BAPI/RFC call, define the `DOCOMMIT=true` parameter. - To create a connection with the Secure Network Communication (SNC) protocol, define the required additional parameters. For more information, see How to configure the SAP Secure Network Communication protocol Informatica How-To Library article. If you specify a property both in the dedicated connection field and in the **SAP Additional Parameters** field, the value specified in the **SAP Additional Parameters** field takes precedence. For more information about SAP parameters, see the SAP documentation.
Jco Trace	Determines whether to track the JCo calls that the SAP system makes. Default is disable. By default, SAP doesn't store information about the JCo calls in a trace file. If you enable JCo trace, you can access the JCo trace file from the following directory: `<Informatica Secure Agent installation directory>\apps\Data_Integration_Server\<latest_version>\ICS\main\bin\rdtm`

Configure SAP BAPI Connector as a business service

Use an SAP BAPI connection in the Web Services transformation in a mapping or mapping task, and then use SAP BAPI Connector as a business service.

For more information, see How to configure SAP BAPI Connector as a business service Informatica How-To Library article.

Configure the serverless runtime environment

You can use a serverless runtime environment hosted on AWS or Azure to connect to the SAP system when you configure an SAP BAPI connection on Linux.

You can't use the serverless runtime environment if you plan to use the SAP Secure Network Communication (SNC) Protocol.

Before you configure an SAP BAPI connection using the serverless runtime environment, perform the following tasks:

- Add the SAP libraries in the Amazon S3 bucket or Azure container in your AWS or Azure account.
- Configure the .yml serverless configuration file.
- Configure the JAVA_LIBS property for the serverless runtime environment on Linux.

Add the SAP libraries in the Amazon S3 bucket or Azure container in your AWS or Azure account

Perform the following steps to configure an SAP BAPI connection in a serverless runtime environment:

1. Create the following structure for the serverless agent configuration in AWS or Azure: `<Supplementary file location>/serverless_agent_config`
2. Add the SAP libraries in the Amazon S3 bucket or Azure container in the following location in your AWS or Azure account: `<Supplementary file location>/serverless_agent_config/sap`

Configure the .yml serverless configuration file

Perform the following steps to configure the .yml serverless configuration file in the serverless runtime environment, and to copy the SAP libraries to the serverless agent directory:

1. Copy the following code snippet to a text editor:

```
version: 1
agent:
  dataIntegrationServer:
    autoDeploy:
      sap:
        jcos:
          - fileCopy:
              sourcePath: sap/jco/<sapjco_libary_filename>
          - fileCopy:
              sourcePath: sap/jco/<sapjco_libary_filename>
```

   where the source path is the directory path of the library files in AWS or Azure.

2. Ensure that the syntax and indentations are valid, and then save the file as `serverlessUserAgentConfig.yml` in the following AWS or Azure location: `<Supplementary file location>/serverless_agent_config`
   When the .yml file runs, the SAP libraries are copied from the AWS or Azure location to the serverless agent directory.

Configure the JAVA_LIBS property for the serverless runtime environment

Perform the following steps in Administrator to configure the JAVA_LIBS and JVMClassPath properties for the serverless runtime environment on Linux:

1. Log in to Informatica Intelligent Cloud Services.

2. Select **Administrator** > **Serverless Environments**.
3. On the **Serverless Environments** tab, expand the Actions menu for the required serverless runtime environment, and then select **Edit**.
4. On the **Runtime Configuration Properties** tab, select **Data Integration Server** as the service and **Tomcat_JRE** as the type.
5. Click **Add Property**.
6. Enter JAVA_LIBS in the **Name** field and set the following value:
   `../bin/rdtm-extra/tpl/sap/sapjco3.jar:../bin/rdtm/javalib/sap/sap-adapter-common.jar`
7. Click **Save**.

For more information about how to configure and use the serverless runtime environment, see *Serverless Runtime Environments* in the Administrator help.

Configure the elastic runtime environment

You can configure custom binary files in an elastic runtime environment to ensure that the runtime environment can access and execute these files during mapping runs.

Before you configure custom binary files, make sure that you deploy the elastic runtime environment on AWS to create a Kubernetes cluster that can process data within Informatica Intelligent Cloud Services.

For more information about deploying an elastic runtime environment, see Deploy an elastic runtime environment.

After you deploy the elastic runtime environment, place the custom binary files on the mounted disk and copy the exact path of the binary files to use in the POST request.

Perform the following steps within Informatica Intelligent Cloud Services for the elastic runtime environment to manage the custom binary files:

1. Log in to your organization and obtain the session ID and runtime environment ID.
2. Make a POST call to the REST API, passing the session ID, runtime environment ID, and the binary file path copied earlier from the mounted disk.
   For more about information about making the POST calls, see Supplementary files in the REST API Reference guide.

   The following is an example of the POST request:

```
POST <base URL>/api/v3/RuntimeEnvironment/<runtime environment ID>/ElasticConfig
Content-Type: application/json
Accept: application/json
INFA-SESSION-ID: <SessionId>
{
  "rteId": "rte-12345",
  "specification": {
    "agent": {
      "dataIntegrationServer": {
        "sap": {
          "jcos": [{"sourcePath": "/<path to binaries>/jco1"}],
          "nwrfcs": [{"sourcePath": "/<path to binaries>/nwrfc1"}],
          "hanas": [{"sourcePath": "/<path to binaries>/hana1"}]
        }
```

   The POST call triggers a restart of the Data Integration Server.

3. Verify that the elastic runtime environment is up and running by checking the status of the Data Integration Server in Administrator.
4. Test a connection or run a mapping to confirm that the elastic runtime environment can access and use the custom binary files.

For more information about how to configure and use the elastic runtime environment, see *Elastic Runtime Environments* in the Administrator help.

INDEX

A

add-on connectors
  building 7
  installing 7
  purpose 7
authentication
  OAuth 2.0 authorization code 26
  OAuth 2.0 client credentials 29

C

Cloud Application Integration community
  URL 5
Cloud Developer community
  URL 5
connection dependencies 14
connection properties
  SAP BAPI 34
connections
  add-on connectors 7
  configuring properties 10
  creating 10
  FTP/SFTP 17
  guidelines for 9
  overview 9
  purpose 7
  REST V3 25
  rules for 9
  rules for FTP/SFTP 19
  testing 10
  using sample data 14

D

Data Integration community
  URL 5
dependencies
  connections 14

F

FTP/SFTP
  connection properties 17
FTP/SFTP connections
  local directory 17
  overview 17
  remote directory 17
  rules and guidelines 19

I

Informatica Global Customer Support
  contact information 6
Informatica Intelligent Data Management Cloud
  web site 5

K

key exchange algorithms
  SFTP connections 18

M

maintenance outages 6
mock connectors 14

R

REST V3
    authentication
      standard 25
  connection properties 25

S

SAP BAPI
  connection properties 34
SAP BAPI Connector
  administration 37
secrets managers
  connection property format 12
  examples 12
SFTP connections
  key exchange algorithms 18
status
  IDMC 6
system status 6

T

trust site
  description 6

U

upgrade notifications 6

V

viewing connection dependencies 14

W

web site 5