How-To Library

Informatica

How to Configure SAP BCI Delta Initialization Without Transfer

© Copyright Informatica LLC 2014, 2022. Informatica Corporation. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica Corporation. All other company and product names may be trade names or trademarks of their respective owners and/or copyrighted materials of such owners.

Abstract

You can use PowerExchange for SAP NetWeaver to extract business content data from SAP Business Suite applications. When you extract business content data, the first step that you perform is delta initialization with transfer. Based on your business needs, you can also configure for delta initialization without transfer. This article describes how to configure delta initialization without transfer.

Supported Versions

- PowerExchange for SAP NetWeaver 10.2 or later

Table of Contents

BCI Update Modes Overview. 2
Delta Initialization with Transfer. 3
Use Case for Delta Initialization without Transfer. 3
Configuring Delta Initialization without Transfer. 3

BCI Update Modes Overview

PowerExchange for SAP NetWeaver integrates with SAP business content to provide an efficient, high-volume data warehousing solution. You can use PowerExchange for SAP NetWeaver to extract business content data from SAP Business Suite applications. You create a processing workflow to extract the data and select an update mode to specify the kind of data that you want to extract.

You can specify one of the following update modes:

- Full. Extracts all the data that meets the selection parameters you specify.
- Delta. Extracts only the changed data since the last data extraction.

You can select one of the following delta update options:

Delta initialization with transfer

The PowerCenter Integration Service extracts all the data from a DataSource.

Use this option when you want to extract data from a DataSource for the first time and want to build an initial set of the data.

Delta update

The PowerCenter Integration Service extracts only the changed data since the last data extraction.

Use this option when you want to read only the changed data since the last data extraction.

Delta repeat

The PowerCenter Integration Service repeats the previous delta update.

Use this option when you encountered errors in a previous delta update and want to repeat the delta update.

Delta Initialization with Transfer

Delta initialization with transfer is generally the first step that you perform when you extract business content data by using PowerExchange for SAP NetWeaver.

When you initialize the delta queue, the PowerCenter Integration Service adds an entry in the SAP ROOSPRMSC table to indicate that the delta queue was initialized. You can use transaction RSA7 to view this entry.

After you initialize the delta queue and deploy a send request file with the **Delta Init with Transfer** update mode, SAP sends all the records in the DataSource to the BCI listener workflow. SAP updates the entry in transaction RSA7 to indicate the last record of the DataSource that was extracted. It also adds this pointer information in the SAP ROOSGENDLM table.

If you perform a delta update after this point, SAP sends only the data that has changed after the last record that is mentioned in the ROOSGENDLM table. Each time a delta update is made, SAP updates the pointer information in the SAP ROOSGENDLM table with the last record that was extracted.

Use Case for Delta Initialization without Transfer

In certain business scenarios, you might want to read only the changed business content data from SAP Business Suite applications. You might want to skip the first step of performing an initial transfer of the entire data and reading the entire data by using the BCI listener workflow. In such cases, you can configure for delta initialization without transfer.

For example, you have a DataSource named Customers that contains 5 million records. You want to read the initial set of records by using another product such as Informatica Data Replication and then write the records to a Teradata data warehouse. You then want to use the BCI functionality of PowerExchange for SAP NetWeaver to read only the new customer records that get added. In this case, you can configure for delta initialization without transfer.

Configuring Delta Initialization without Transfer

To configure delta initialization without transfer, perform the following steps:

1. In step 3 of the **Generate Mapping for BCI Wizard**, specify a directory for the request file or click the **Browse** button and select a directory.
2. Select **Create New** to create a new delta initialization request.
3. Select the update mode as **Delta**.
4. Click the **Initialize** button.

   The delta queue is initialized and the delta pointer in the ROOSGENDLM table is set to the maximum value present for the delta column.
5. In the update mode list, select **Delta**.
6. Click **Save** to save all the settings to the request file.

   The PowerCenter Client saves the request file to the specified directory.

After you read the initial set of data by using another product, you can deploy the send request file to extract only the changed data. SAP sends only the data that has the delta column greater than the maximum value that is stored in the ROOSGENDLM table.

Authors

Anu Chandrasekharan
Senior Technical Writer

Acknowledgements

The author would like to acknowledge Raghu Rajanna, Principal QA Engineer, for his technical assistance.