How-To Library

Informatica

Materializing a Target from an Adabas Unload File

© Copyright Informatica LLC 2011, 2021. Informatica LLC. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica Corporation.

Abstract

You can use a decompressed Adabas unload file as a data source in a PowerExchange bulk data movement session. This article describes how to create a decompressed Adabas unload file, create a data map for it, and create a bulk data movement session to materialize a target from the data source.

Supported Versions

- PowerExchange 10.0 or later

Table of Contents

Overview. 2
Create a Decompressed Adabas Unload File. 2
Example JCL to Create a Decompressed Adabas Unload File. 2
Map the Adabas Unload File. 3
Materialize the Target from the Unload File. 3

Overview

To create a decompressed Adabas unload file and use it to materialize a target in a bulk data movement session, complete the following steps:

1. Create a decompressed Adabas unload file. Use the DECOMPRESS function of the ADACMP utility.
2. Map the unload file in PowerExchange. Create a data map for the unload file, send the data map to the PowerExchange Listener on the remote system, and run a database row test.
3. Materialize the target. In PowerCenter, create a mapping, import the data map, and create and run the workflow.

Create a Decompressed Adabas Unload File

To create a decompressed Adabas unload file, use the DECOMPRESS function of the ADACMP utility. The input to the ADACMP DECOMPRESS function can be either a single compressed Adabas file or an output data set unloaded by the ADAULD utility function. To select specific records, include the appropriate ADACMP or ADAULD keywords.

Example JCL to Create a Decompressed Adabas Unload File

The following example JCL shows how to unload and decompress a single Adabas file:

```
//ADADECMP EXEC PGM=ADARUN
//STEPLIB  DD DSN=<ADABAS loadlib>,DISP=SHR
//DDASSOR1 DD DISP=SHR,DSN=<ASSOR>
//DDDATAR1 DD DISP=SHR,DSN=<DATA>
//DDWORKR1 DD DISP=SHR,DSN=<WORK>
//DDAUSBA  DD DSN=<decompressed output>,DISP=(,CATLG,DELETE),
//         SPACE=(TRK,(30,50),RLSE),UNIT=SYSDA
//DDFEHL   DD SYSOUT=*              ** REJECTED DATA **
//DDPRINT  DD SYSOUT=*
//DDDRUCK  DD SYSOUT=*
//DDCARD   DD *
ADARUN DB=<dbid>,DE=3390,SVC=249
ADARUN PROG=ADACMP
//DDKARTE  DD *
```

```
ADACMP DECOMPRESS INFILE=<File ID>,ISN
/*
//
```

Map the Adabas Unload File

Use this procedure to create a PowerExchange data map for the decompressed Adabas unload file, send the data map to the PowerExchange Listener on the remote system, and run a database row test.

Before you begin, create the unload file.

1. From the PowerExchange Navigator, create a data map. If an Adabas data map already exists, create a copy by opening the data map and selecting **File > Save As**. Otherwise, create a new data map, and select **ADABAS** at **Access Method**.
2. To add the ISN to the mapping, perform the following actions:
   - Open the data map.
   - Select the record.
   - In the **Record - *record_name*** dialog box, select the **Expr** tab.
   - Right-click anywhere in the dialog box, and select **Add Field at End**.
   - Enter **ISN** for the name, and select **NUM32U** for the type.
   - Click in the **Expression** column, click the ellipsis (. . .) to display the **Expression Editor**, and enter **GetDatabaseKey()**.
3. Iin the Resource Explorer, right-click the table, and select **Properties**. Under **Column Generation**, select **Refresh with missing columns**.
4. Send the data map to the PowerExchange Listener on the remote system. In the Resource Explorer, select the data map and click **File > Send to Remote Node**. This step enables PowerExchange extraction routines to access the data map at runtime.

   In the **Location** field, enter the PowerExchange Listener node name that is specified in the NODE statement of the dbmover.cfg file on the local PowerExchange system. Complete the other fields, as needed.

   Note: If you do not complete this step, you are prompted to send the data map to the remote node when you run a database row test.
5. Run a database row test on the table view of the metadata to verify that data can be returned from the source unload file.

Materialize the Target from the Unload File

Use this procedure to materialize a target from a decompressed Adabas unload file. The procedure assumes that you are using PWXPC to integrate PowerExchange with PowerCenter.

Before you begin, create a data map in PowerExchange for the unload file, and run a database row test.

1. Create a target database structure, such as a table.
2. In the PowerCenter Designer, create a mapping. Include the Adabas table for which you created the unload file as the source and the database object from step 1 as the target. In the **Import from PowerExchange** dialog box, select **ADABAS** as the **Source Type**.
3. In the PowerCenter Workflow Manager, create a workflow and session.

   When configuring the session, select **PowerExchange Reader for Adabas Unload Files** as the reader and **NRDB Batch application connection** as the connection value.
4. Start the workflow to move the unload file data to the target table.

Author

Jim Middleton