Informatica® Cloud Data Governance and Catalog

July 2026

Bulk Import Assets

Informatica Cloud Data Governance and Catalog Bulk Import Assets
July 2026

© Copyright Informatica LLC 2021, 2026

Publication Date: 2026-07-30

Table of Contents

Preface . . . 5

Chapter 1: Overview . . . 6

Prerequisites . . . 7

Chapter 2: Template file properties . . . 10

AI Model . . . 11
AI System . . . 18
Business Area . . . 23
Data Quality Rule Template . . . 27
Data Quality Rule Occurrence . . . 35
Data Set . . . 43
Geography . . . 48
Glossary Domain . . . 51
Glossary Subdomain . . . 56
Glossary Business Term . . . 61
Glossary Metric . . . 67
Legal Entity . . . 73
Manual Data Element . . . 77
Policy . . . 81
Process . . . 85
Project . . . 91
Regulation . . . 96
System . . . 100
Stakeholders . . . 105
Relationships . . . 106

Chapter 3: Bulk import process . . . 108

Import assets using template files . . . 108
- Step 1: Get template file . . . 109
- Step 2: Populate template file . . . 110
- Step 3: Import the file . . . 111
- Step 4: Prepare to import the assets . . . 112
- Step 5: Start import of assets . . . 114

Re-import assets from an exported search results file . . . 117
- Step 1. Exporting the search results in a Microsoft Excel file . . . 118
- Step 2. Modify the exported file . . . 120
- Step 3. Preparing to re-import the exported file . . . 123
- Step 4. Re-importing the exported file . . . 124

Viewing import job status . . . 126

Chapter 4: Troubleshooting bulk import of assets. 128

Index. 129

Preface

Refer to *Bulk Import Assets* to learn how to import business assets to Data Governance and Catalog. When you have many assets, relationships, and stakeholders to enter in Data Governance and Catalog, you can bulk import them with predefined or custom Microsoft Excel templates.

CHAPTER 1

Overview

Use a template file to create, update, or delete a large number of business assets in Data Governance and Catalog. You can also import assets using a search export file.

The import or export time varies depending on the number and type of assets in your template file or search.

When exporting assets from a search result, Data Governance and Catalog exports quicker for an export of up to 10,000 assets. If you include asset hierarchy, every level of an asset's hierarchy counts as one asset and adds to the asset limit required for a faster export.

If you include asset relationships or export more than 10,000 assets, your export might take longer. For more information about how you can export assets from a search result, see "Step 1. Exporting the search results in a Microsoft Excel file" on page 118.

When you import assets using a downloaded template file or a search export file, your import is faster under the following conditions:


- You are creating or updating assets and not deleting assets. For assets associated with a workflow, you can simultaneously create or update a maximum of 500 assets. Data Governance and Catalog creates tickets only if you selected **Yes** for the **Submit Ticket** column in the template file or if you have left the field empty.
  For more information about the template file, see Chapter 2, "Template file properties" on page 10.
- Your import file has no more than 500 rows, which comprises no more than 2000 update requests. Update requests include operations to create, update, assign, or classify assets.
- You are adding or removing up to 50 asset stakeholders. For technical assets, the assets you import must have fewer than 50 child assets.
- Your import file does not include update requests for relationships between technical data elements and business data sets.
- Your import file does not contain sheets for relationships and stakeholders.

Prerequisites

Before you can use the bulk import or export process, ensure that the necessary privileges are enabled for your role in the Intelligent Data Management Cloud™ (IDMC) Administrator .


- To bulk import data, the organization administrator must assign the **Import** privilege to your user role in the Administrator. To export the results of a search, the organization administrator must enable the **Export** privilege to your user role. Both the **Import** and **Export** privileges are enabled by default for the Governance Administrator role in the Administrator.

  The following image shows the Governance Administrator role with the **Export** and **Import** feature privileges enabled in Administrator:




- To download a predefined Microsoft Excel template file for the assets that you want to import, the organization administrator must assign the read privilege for the **Role** asset to your user role in the Administrator.

The following image shows a sample user with the **Read** privilege enabled for the **Role** asset in the Administrator:



- To modify an asset or its details, the organization administrator must assign the **Create**, **Delete**, **Manage**, **Access**, **Read**, and **Update** privileges to your user role through access policies in Metadata Command Center.

  The following image shows the privileges you must assign to your user role through access policies access Metadata Command Center:



For more information about the available feature privileges that the organization administrator can enable, see the *Asset Management* help.

CHAPTER 2

Template file properties

Download a predefined Microsoft Excel template file to bulk import data and create, modify or delete assets in Data Governance and Catalog.

The downloaded predefined template file contains various sheets with field names for the respective values that you can enter. Column headers in red indicate mandatory fields, and column headers in black indicate optional fields. The column headers also contain notes to help you enter the values correctly.

The template file you download contains the **Instructions** sheet, which provides instructions on using the template for bulk import in Data Governance and Catalog.

The following notes apply for the values that you enter in the template files:

- The system administrator might disable some fields in Data Governance and Catalog according to the requirements of your organization. Such fields will not appear in the template files that you download.
- When you create a new asset using the bulk import template, you can create assets that are in the 'Draft' or 'Published' lifecycle status. You cannot choose the asset lifecycle status as 'In Review'.
- If assets are in 'Published' or 'Draft' state, you can bulk update or delete stakeholders for the business assets using the asset types template or the additional stakeholders sheet.

  You can download additional sheets for stakeholders and relationships while downloading the bulk import templates for business assets.
- When you specify values for custom attributes, enter values that match their data types. The following table describes the guidelines for adding values to custom attributes:

Custom Attribute	Value
Text Field	Enter a single line or multi-line rich text that has letters, integers including decimals with multiple decimals places, and special characters.
Numeric Value	Enter integers or decimals with multiple decimal places.
Dropdown List	Create a single select or a multi-select list. Use commas without spaces to separate options for a multi-select list. If an option has a comma, you must enclose the option within double quotes without spaces.
Check Box	Select `True` or `False`.

Custom Attribute	Value
Date Field	Enter dates in the format `MM/DD/YYYY`.

URL Field	You can enter a hyperlinked label, a URL, or both a label and URL.
	If you enter both label and URL, do not enter the URL as a hyperlink, and use a colon to separate the values.
	Examples: `Label :http://www.your-url.com`
	For valid URL entries, refer to the following examples:
	`- http://site.com/path/to/resource`
	`- www1.example.org/test`
	`- test123.example.net/path/to/file`
	`- http://192.168.1.1`

For more information, see "Step 1: Get template file" on page 109.

AI Model

An AI model asset represents the essential parameters of an AI model. These parameters also include the environment where the model is run, the input parameters and the output data, and the business purpose and rules for the model. AI models provide insights for many activities so that you can make decisions faster and easier or provide prediction modeling.

The following table describes the columns where you must enter asset values for AI models:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.

Column	Type	Description
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Accuracy	Optional	Aggregate score of the degree to which data can accurately demonstrate the real-world entities.
AI Model Purpose	Optional	Describe the business or technical purpose of the asset. Type of Entry: Formatted text
Architecture Type	Optional	Defines the architecture and algorithms of the AI Model asset. You can select one of the following options: - `Linear Regression`. The architecture type that computes the linear relationship between the dependent variable and other independent variables. - `Logistic Regression`. The architecture model that accomplishes binary classification tasks by predicting the probability of an outcome, event, or observation. - `Lineage Discrimant Analysis`. The architecture model that is used as a classifier and a dimensionality reduction algorithm. - `Decision Trees`. The architecture type that models decisions, outcomes, and predictions using a flowchart-like tree structure, commonly used for classification and regression tasks. - `K-Nearest Neighbors`. The architecture model that uses proximity to form classifications or predictions about the grouping of an individual data point. This architecture is used for solving both classification and regression problems. - `Naive Bayes`.The architecture model that works on the principle of conditional probability used for predictive modeling and classification tasks. - `Learning Vector Quantization`. Learning Vector Quantization (LVQ) is an algorithm commonly used for statistical classification and pattern recognition. - `Support Vector Machines`. The architecture type used for linear or nonlinear classification, regression, and outlier detection tasks, where the algorithm creates a line or a hyperplane which separates the data into classes. - `Others`. If none of the other options meet your requirements, select this option.
Bias Score	Optional	Measure of bias in the model. A higher value indicates a greater difference between the predicted result and the actual result. Use the bias score to determine if the assumptions in the model are correct. Type of Entry: Numeric value. Enter a value between `0` and `100`. Ensure that the value you specify has a maximum precision of `5` digits and a scale of `2` decimal places.
Drift Score	Optional	Measure of degradation of the model. A higher value indicates greater degradation. Use the drift score to determine if the model can provide results within an acceptable range of accuracy. Type of Entry: Numeric value. Enter a value between `0` and `100`. Ensure that the value you specify has a maximum precision of `5` digits and a scale of `2` decimal places.

Column	Type	Description
Environment	Optional	Select the environment for the asset. You can select one of the following options: - `Training` - `Validation` - `Production`
F1 Score		Metric used to evaluate the quality of data classification, matching, or search/retrieval results.
Input	Optional	Input parameters for the AI model. Type of Entry: Formatted text
Libraries	Optional	Software libraries that are used to build the AI model. Type of Entry: Alphanumeric characters, including spaces and special characters.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset's lifecycle to `In Review`. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.
MAE	Optional	Model Accuracy Evaluation (MAE) is a standardized governance attribute that allows to track how closely a deployed AI model's predictions align with actual real-world data.
Model Format	Optional	The format in which the asset is maintained. You can select one of the following options: - `Docker`. Use Docker to create an operating system bundle with deep learning environment and packaging it within a single file called a docker image. - `ONNX`. Open Neural Network Exchange (ONNX) is an open format that represents machine learning models, that facilitates interchanging models between various ML frameworks and tools. - `Others`. If none of the other formats meet your requirements, select this option.
Model Rules	Optional	Define the rules that govern the use of the AI model. Type of Entry: Formatted text
MSE	Optional	Mean Squared Error (MSE) is a specialized metric designed to flag models that suffer from large, erratic prediction mistakes. It ensures that an enterprise's AI assets are reliable, transparent, and compliant with corporate risk thresholds.
Output	Optional	Result of the AI model after it is run. Use this field to inform users of what they can expect from the model. Type of Entry: Formatted text
Precision	Optional	Performance metric column used to measure the model's accuracy when it makes a positive prediction.

Column	Type	Description
ROC-AUC	Optional	Receiver Operating Characteristic - Area Under the Curve (ROC-AUC) is the gold-standard metric for evaluating how well a model distinguishes between two different classes.
Source Model Repository	Optional	Repository in which the source of the AI model is maintained. Type of Entry: Alphanumeric characters, including spaces and special characters.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: `(Stakeholder role name)`	Optional	User or user group that you want to assign as stakeholders of the asset under the `(Stakeholder role name)` stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

AI System

The AI System asset is a machine learning-based system that uses multiple AI models to perform a range of tasks, such as generating predictions, content, recommendations, decisions, and actions. The asset records information about the technologies, AI models, and data that is used to perform these tasks.

The following table describes the columns where you must enter asset values for AI Systems:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
AI System Type	Optional	The type of AI system. You can select one of the following options: - AI Application. A software program that uses artificial intelligence techniques to perform specific tasks. - AI Agent. An autonomous AI entity that is designed to take action within a given environment to achieve specific goals. - Retrieval System. An AI system that searches and retrieves relevant data in response to queries. - Conversational. An AI system, such as a chatbot or virtual assistant, that interacts with users through natural language dialogue.
Development Stage	Optional	A phase in the AI system lifecycle where data preparation, model design, training and validation might be carried out to build and improve the AI system's performance. You can select one of the following options: - In Development. The AI System is in development. - Validation. The AI System is being validated. - Production. The AI System is already in use.

Column	Type	Description
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset's lifecycle to `In Review`. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane"

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Business Area

A Business Area asset represents a department or business function with certain assigned responsibilities in the wider organization.

The following table describes the columns where you must enter asset values for business area:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Business Area	Optional	Enter the reference ID or the name of the parent Business Area asset. Ensure that you specify only one parent Business Area asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Data Quality Rule Template

A Data Quality Rule Template asset is the business representation of a data quality rule specification. You can use a data quality rule template to create a data quality rule. The actual data quality score of data elements are expressed as Data Quality Rule Occurrences in Data Governance and Catalog. As data quality

rules set business expectations, they are often associated with glossary assets such as Business Terms and Metrics.

The following table describes the columns where you must enter asset values for data quality rule templates:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Criticality	Optional	Select the criticality of the rule template. You can select one of the following options: - `High`. The level of impact for a data quality issue is high if there is a high risk of operational, customer, regulatory and financial impact. - `Medium`. The level of impact for a data quality issue is medium if there is a moderate risk of operational, customer, regulatory and financial impact. - `Low`. The level of impact for a data quality issue is low if there is a low risk of operational, customer, regulatory and financial impact.

Column	Type	Description
Dimension	Required	Specify the data quality dimension for which the data quality rule is run. You can select one of the following options: - `Accuracy`. Data Accuracy refers to the degree to which data can accurately demonstrate the real-world entities. - `Validity`. Validity dimension signifies the data values that follow a specific format or align with business rules. - `Completeness`. Completeness dimension suggests if the data fulfills the minimum essential information criteria to deliver meaningful inferences. - `Consistency`. Consistency dimension indicates if the information stored and utilized in multiple instances is conflicting with itself. - `Uniqueness`. Data Uniqueness is a measurement to identify and remediate duplication and overlaps. - `Timeliness`. Timeliness dimension indicates the timely availability of the required and valid data. **Note:** If the data quality dimensions listed here differ from what is available in the predefined Microsoft Excel template, the administrator might have defined a different list of dimensions for your organization. For more information about how your administrator can customize the data quality dimensions, see the *Administration* help in Metadata Command Center.
DQ Rule Custom	Optional	Specify the data quality rule to map corporate data quality definitions to physical system rules.
Enable Automation	Optional	Enable or disable data quality rule automation for the rule template. You can select one of the following values: - `TRUE`. Create rule occurrences automatically for data elements that are linked to the associated Glossary assets. After the bulk import job, Data Governance and Catalog initiates a job to create a schedule to run the data quality rule for the catalog source. The rule occurrences are created as per the schedule. The frequency of the data quality rule execution depends on the frequency set in the `Frequency` column of the rule template file. - `FALSE`. No automated rule occurrences are generated. You can manually run the data quality rule for the associated data elements. **Note:** If automation was previously enabled on a rule template, then you cannot use a bulk import template to modify the value from `True` to `False`.
Frequency	Optional	Select the frequency of running the data quality rules in the rule template. You can select one of the following options: - `Daily`. The schedule for data quality rule run gets repeated every day. - `Weekly`. The schedule for data quality rule run gets repeated once every week. - `Monthly`. The schedule for data quality rule run gets repeated once every month.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.

Column	Type	Description
Measuring Method	Required	Specify the method by which the data quality rules for the rule occurrence are evaluated. You can select one of the following options: - `Business extract`. This rule is measured on the data that is exported for a particular business case. - `System function`. This rule is measured by the data quality system. - `Technical script`. This rule is measured by a script that is manually run by an analyst. - `Informatica Cloud Data Quality`. This rule is measured by Informatica Cloud Data Quality service. If you select `Informatica Cloud Data Quality` as the measuring method, ensure that you use the **Technical Rule Reference** field to specify the identifier of the data quality rule that is defined in `Informatica Cloud Data Quality`. If you don't specify the data quality rule identifier, the bulk import process fails.
Input Port Name	Optional	Specify an input port name for the primary data element on which the technical rule reference will run in the data quality system. The primary data element must have only one input port. Type of Entry: Formatted text
Ouput Port Name	Optional	Specify an output port for the technical rule reference that will run in the data quality system. The primary data element must have only one output port. Type of Entry: Formatted text
Technical Description	Optional	Specify the technical parameters of the rule definition. Type of Entry: Formatted text
Technical Rule Reference	Required	Specify the internal ID of the rule specification in the data quality system that you want to run on the data elements. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in rule references.
Target	Required	Specify the minimum acceptable data quality value for the asset to be considered "Good". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign. Example: `90` means on or above 90%. This is the target threshold to be achieved.
Threshold	Required	Specify the minimum acceptable data quality value for an asset to be considered as "Acceptable". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign.
Primary Glossary	Required	Enter the name or reference ID of the Glossary asset that applies to the data quality rule template. Specify the Glossary asset that represents the data elements on which multi-port data quality rules in the rule template apply. You can add only one primary glossary to a data quality rule template. Field Type: Required Type of Entry: Reference ID or the name of the primary Glossary asset Example: `Email Address`, `BT-12`

Column	Type	Description
Secondary Glossary	Optional	Enter the name or reference ID of the Secondary Glossary asset that applies to the data quality rule template. Specify the Glossary asset that represents the data elements on which multi-port data quality rules in the rule template apply. You can add glossary names or reference IDs followed by port names and separated by colons in a single line. Don't include spaces after the glossary name or reference ID. You can add multiple entries in a single line without spaces and separated by semicolons. Field Type: Optional Type of Entry: Reference ID or the name of the glossary asset followed by the port name Example: `Marketing Email:InputPort1;BT-12:InputPort2`
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"


Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Note: If you connect Data Governance and Catalog to Data Quality, perform the following steps to identify the value that you must enter in the **Technical Rule Reference** field:

1. In Data Quality, open the rule specification for which you want to identify the internal ID.
2. In the address bar of the browser, locate the string that appears after the last slash. This string is the internal ID of the rule specification.

The following image shows the internal ID for a rule specification:



3. Copy the string so that you can paste it into the **Technical Rule Reference** field.

Data Quality Rule Occurrence

A data quality rule occurrence is the business representation of a data quality rule that is run on data elements. You can rate a Data Quality Rule Occurrence asset to indicate your assessment of the quality of the asset or add your comments to the asset to provide your inputs on the data present within the asset. This enables different users to collaborate on assets and make collective decisions on using the data.

The following table describes the columns where you must enter asset values for data quality rule occurrences:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.

Column	Type	Description
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Criticality	Optional	Select the criticality of the rule occurrence. You can select one of the following options: - `High`. The level of impact for a data quality issue is high if there is a high risk of operational, customer, regulatory and financial impact. - `Medium`. The level of impact for a data quality issue is medium if there is a moderate risk of operational, customer, regulatory and financial impact. - `Low`. The level of impact for a data quality issue is low if there is a low risk of operational, customer, regulatory and financial impact.
Dimension	Required	Specify the data quality dimension for which the data quality rule is run. You can select one of the following options: - `Accuracy`. Data Accuracy refers to the degree to which data can accurately demonstrate the real-world entities. - `Validity`. Validity dimension signifies the data values that follow a specific format or align with business rules. - `Completeness`. Completeness dimension suggests if the data fulfills the minimum essential information criteria to deliver meaningful inferences. - `Consistency`. Consistency dimension indicates if the information stored and utilized in multiple instances is conflicting with itself. - `Uniqueness`. Data Uniqueness is a measurement to identify and remediate duplication and overlaps. - `Timeliness`. Timeliness dimension indicates the timely availability of the required and valid data. **Note:** If the data quality dimensions listed here differ from what is available in the predefined Microsoft Excel template, the administrator might have defined a different list of dimensions for your organization. For more information about how your administrator can customize the data quality dimensions, see the *Administration* help in Metadata Command Center.
DQ Rule Custom	Optional	Specify the data quality rule to map corporate data quality definitions to physical system rules.
Exception File Path	Optional	Specify the path where the exception records are stored. An exception is a record that fails to meet the criteria defined by the data quality rule occurrence. Type of Entry: Formatted text. Enter the complete path of the location of the file where the exception records are stored. Ensure that the path includes the name and extension of the file. Do not enter hyperlinks.

Column	Type	Description
Frequency	Optional	Select the frequency of running the data quality rules in the rule template. You can select one of the following options: - `Daily`. The schedule for data quality rule run gets repeated every day. - `Weekly`. The schedule for data quality rule run gets repeated once every week. - `Monthly`. The schedule for data quality rule run gets repeated once every month.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.
Measuring Method	Required	Specify the method by which the data quality rules for the rule occurrence are evaluated. You can select one of the following options: - `Business extract`. This rule is measured on the data that is exported for a particular business case. - `System function`. This rule is measured by the data quality system. - `Technical script`. This rule is measured by a script that is manually run by an analyst. - `Informatica Cloud Data Quality`. This rule is measured by Informatica Cloud Data Quality service. If you select `Informatica Cloud Data Quality` as the measuring method, ensure that you use the **Technical Rule Reference** field to specify the identifier of the data quality rule that is defined in `Informatica Cloud Data Quality`.
Input Port Name	Optional	Specify an input port name for the primary data element on which the technical rule reference will run in the data quality system. The primary data element must have only one input port. Type of Entry: Formatted text
Ouput Port Name	Optional	Specify an output port for the technical rule reference that will run in the data quality system. The primary data element must have only one output port. Type of Entry: Formatted text
Scanned Time	Optional	Specify the date and time on which the data quality rule was run on the assets. Type of Entry: To specify a date and time, use the `YYYY-MM-dd'T'HH:mm:ss.SSS'Z'` format. Example: `2000-10-31T01:30:00.000-05:00` If you have entered a score in the **Score** column, ensure that you specify a value in the **Scanned Time** column.

Column	Type	Description
Score	Optional	Specify the data quality rule score for the asset that corresponds to the rule occurrence. Type of Entry: Numeric value. If you have entered a score in the **Score** column, ensure that you specify a value in the **Scanned Time**, **Total Rows** and **Failed Rows** columns. If you update data quality scores through bulk import, the updated data quality scores can take up to one hour to reflect in the **Total Runs Table** of the **Score** tab of a rule occurrence. **Note:** When you upload data quality scores in Data Governance and Catalog using bulk upload, the scores are automatically rounded to two decimal places. If you set a score with more than two decimal points, the score is rounded to the nearest value and retains only two decimal places.
Technical Description	Optional	Specify the description of the rule template as it is defined in the integrated data quality system. Type of Entry: Formatted text
Technical Rule Reference	Optional	Specify the internal ID of the rule specification in the data quality system that you want to run on the data element. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in rule references. If you select `Informatica Cloud Data Quality` as the measuring method, the **Technical Rule Reference** field is mandatory. This field is not mandatory for other measuring methods.
Target	Required	Specify the minimum acceptable data quality value for the asset to be considered "Good". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign. Example: `90` means on or above 90%. This is the target threshold to be achieved.
Threshold	Required	Specify the minimum acceptable data quality value for an asset to be considered as "Acceptable". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign.
Total Rows	Optional	Specify the total number of rows for which the data quality rule is run. Type of Entry: Numeric value. If you have entered a score in the **Score** column, ensure that you specify a value in the **Total Rows** column.
Failed Rows	Optional	Specify the number of rows where the data quality rule run failed. Type of Entry: Numeric value. If you have entered a score in the **Score** column, ensure that you specify a value in the **Failed Rows** column.
Primary Data Element	Required	Enter the path of the data element on which you want to execute the data quality rule. The data quality score is generated only for the **Primary Data Element**. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used. To enter the data element path, use the following format: `<Catalog Source Name>://<Database Name>/<Schema Name>/<Table Name>/<Column Name>` Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER ID`

Column	Type	Description

Secondary Data Element	Optional	Enter the path or the Reference ID of the secondary data element.
		The secondary data element is one of the parameters of the data quality score that is executed on the Primary Data Element. You can add multiple secondary data element paths to a data quality rule occurrence. You can also add Port Names separated by colons in a single line without any spaces at the end of the secondary data element path.
		Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used.
		To add multiple secondary data elements, enter data element paths in a single line separated by semicolons and a single space.
		- To enter the data element path, use the following format:
		`CSNAME://DBNAME/SCHEMA/TABLE/COLNAME`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS`
		- To add multiple secondary data elements, use the following format:
		`CSNAME://DBNAME/SCHEMA/TABLE/COLNAME1; CSNAME://DBNAME/SCHEMA/TABLE/COLNAME2`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS; CUSTOMER_Oracle://CUST_DS/CUST_SCHEMA/CUSTOMERDETAILS/CUSTOMER STATUS`
		- To enter a secondary data element path with a port name, use the following format:
		`CSNAME1://DBNAME1/SCHEMA1/TABLE1/COLNAME1:PORTNAME1`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS:InputPort1`
		- To add secondary data elements with multiple port names, use the following format:
		`CSNAME://DBNAME/SCHEMA/TABLE/COLNAME1:PORTNAME1; CSNAME://DBNAME/SCHEMA/TABLE/COLNAME2:PORTNAME2`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS:InputPort1; CUSTOMER_Oracle://CUST_DS/CUST_SCHEMA/CUSTOMERDETAILS/CUSTOMER STATUS:InputPort2`

Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"


Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Note: If you connect Data Governance and Catalog to Data Quality, perform the following steps to identify the value that you must enter in the **Technical Rule Reference** field:

1. In Data Quality, open the rule specification for which you want to identify the internal ID.
2. In the address bar of the browser, locate the string that appears after the last slash. This string is the internal ID of the rule specification.

The following image shows the internal ID for a rule specification:



3. Copy the string so that you can paste it into the **Technical Rule Reference** field.

Data Set

A Data Set asset represents identifiable groupings of data for a particular purpose. Data Sets are business-friendly representations of technical assets such as tables, files, and more. A Data Set asset focuses less on the technical aspects of how the data is delivered and more on the information provided by the data set.

The following table describes the columns where you must enter asset values for data sets:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.

Column	Type	Description
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset's lifecycle to `In Review`. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Parent: System	Required	Enter the reference ID or the name of the parent System asset. When you create or import a Data Set asset, link the data set with a parent System asset or parent AI System asset. You can specify only one parent asset.
Parent: AI System	Required	Enter the reference ID or the name of the parent AI System asset. When you create or import a Data Set asset, link the data set with a parent System asset or parent AI System asset. You can specify only one parent asset. The AI System asset is a machine learning-based system that uses multiple AI models to perform a range of tasks, such as generating predictions, content, recommendations, decisions, and actions. The asset records information about the technologies, AI models, and data that is used to perform these tasks.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Geography

A Geography asset captures areas, regions, or countries relevant to where your organization operates. You can use a geography asset to show how different business assets are relevant to different locations.

The following table describes the columns where you must enter asset values for geography:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Geography	Optional	Enter the reference ID or the name of the parent **Geography** asset. Ensure that you specify only one parent **Geography** asset.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Domain

A glossary asset of the Domain type refers to a collection of business concepts and activities that can be grouped together for a specific function or requirement. A domain is a subject matter area under which many

terms can be organized. You can use a glossary domain to assign semantic and business context to an actual business concept.

The following table describes the columns of the bulk import template for glossary domains:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published` You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Subdomain

A glossary asset of the Subdomain type refers to a concept or activity that constitutes a specific business function or requirement. A domain is divided into subdomains to help organize business terms and metrics. You can use a glossary subdomain to assign semantic and business context to an actual business concept.

The following table describes the columns where you must enter asset values for glossary subdomains:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Business Logic	Optional	Description of any business logic that is relevant to the asset. Type of Entry: Formatted text

Column	Type	Description
Examples	Optional	Enter an example that is representative of the asset. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in examples. To enter multiple values, use a comma to separate each value. Example: For the subdomain ‘`Product Identifer`,’ examples can be '`Model Number`' or '`Brand Name`'
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Security Level	Optional	Security Level of the asset with respect to the sensitivity of the information. This is manually specified for the asset and is suitable only as a governance record. It is not related to data classification or any other system classification. You can select one of the following options: - `Public`. The assets can be freely used, reused, and distributed without repercussions. - `Internal`. The assets are strictly accessible to internal employees who are granted access. - `Confidential`. Confidential assets are mostly protected by laws and access to these assets would require confidential data. - `Restricted`. Restricted assets, if compromised or accessed without authorization, can cause irreparable damage to the organization.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Subdomain	Optional	Enter the reference ID or the name of the parent Glossary Subdomain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Subdomain asset.

Column	Type	Description
Parent: Domain	Optional	Enter the reference ID or the name of the parent Glossary Domain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Domain asset.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Business Term

A glossary asset of the Business Term type can be used to capture a business definition that is used in your organization. Most business terms tend to be realized as data elements and can be used to indicate that different data elements represent the same concept, whatever the name they have in each table.

The following table describes the columns where you must enter asset values for glossary business terms:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Business Logic	Optional	Description of any business logic that is relevant to the asset. Type of Entry: Formatted text

Column	Type	Description
Critical Data Element	Optional	Specify whether the asset should be marked as a Critical Data Element. A Critical Data Element is an important or elite asset that you can use in your governance environment to calculate key metrics or generate key reports. For example, in an HR data warehouse, 'Employee Number' can be a Critical Data Element, because it uniquely identifies the employees in the organization. You can select one of the following values: - `True`. The asset is marked as a Critical Data Element. - `False`. The asset isn't marked as a Critical Data Element.
Examples	Optional	Enter an example that is representative of the asset. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in examples. To enter multiple values, use a comma to separate each value. Example: For the business term 'Credit Card Type,' examples can be `VISA`, `MASTERCARD`.
Format Type	Optional	Select the format in which the business term is expressed. You can select one of the following options: - `Text` - `Number` - `Decimal` - `Percentage` - `Fraction` - `Date` - `Time` - `Date time`
Format Description	Optional	Description of the asset format. Example: For the business term 'Date of Birth,' the **Format Type** will be `Date`, and the **Format Description** will be the date format `YYYY-MM-DD`.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Security Level	Optional	Security Level of the asset with respect to the sensitivity of the information. This is manually specified for the asset and is suitable only as a governance record. It is not related to data classification or any other system classification. You can select one of the following options: - `Public`. The assets can be freely used, reused, and distributed without repercussions. - `Internal`. The assets are strictly accessible to internal employees who are granted access. - `Confidential`. Confidential assets are mostly protected by laws and access to these assets would require confidential data. - `Restricted`. Restricted assets, if compromised or accessed without authorization, can cause irreparable damage to the organization.

Column	Type	Description
Classification	Optional	Name for the Data Element or Data Entity Classification that you want to associate with the asset. Consider entering unique data element or data entity classification so that you can distinguish between different classifications. Type of Entry: Alphanumeric characters, including spaces and special characters such as –, _, /,\, &, (,), ., #, +, * and %. To specify multiple values, enter the values in the same row and use a semicolon to separate each value. Example: `First Name`, `BA Name: 29`
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Subdomain	Optional	Enter the reference ID or the name of the parent Glossary Subdomain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Subdomain asset.
Parent: Metric	Optional	Enter the reference ID or the name of the parent **Metric** asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent **Metric** asset.
Parent: Business Term	Optional	Enter the reference ID or the name of the parent **Business Term** asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent **Business Term** asset.
Parent: Domain	Optional	Enter the reference ID or the name of the parent Glossary Domain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Domain asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Reference Data	Optional	Associate reference data from Reference 360 with business terms by entering the path of one or more code list attributes from Reference 360. Example: `Reference360Catalog Source/Country/Enterprise Country/Code` To enter multiple code list attributes, use a semicolon to separate each name. Do not use a space to separate multiple attributes. Ensure that all the attributes that you specify belong to the same code list. Example: `Reference Catalog Source/Country/Enterprise Country/Code;Reference Catalog Source/Country/Enterprise Country/Name;Reference Catalog Source/Country/Enterprise Country/Description`
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Metric

A glossary asset of the Metric type refers to the definition of the measurement of a business result. This measurement is typically a numerical indicator of business success. You can use a metric asset to assign semantic and business context to an actual business measurement.

The following table describes the columns where you must enter asset values for glossary metrics:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Business Logic	Optional	Description of any business logic that is relevant to the asset. Type of Entry: Formatted text

Column	Type	Description
Critical Data Element	Optional	Specify whether the asset should be marked as a Critical Data Element. A Critical Data Element is an important or elite asset that you can use in your governance environment to calculate key metrics or generate key reports. For example, in an HR data warehouse, 'Employee Number' can be a Critical Data Element, because it uniquely identifies the employees in the organization. You can select one of the following values: - `True`. The asset is marked as a Critical Data Element. - `False`. The asset isn't marked as a Critical Data Element.
Examples	Optional	Enter an example that is representative of the asset. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in examples. To enter multiple values, use a comma to separate each value. Example: For the Metric '`Year Over Year Growth`,' example can be `40%`
Format Type	Optional	Select the format in which the business term is expressed. You can select one of the following options: - `Text` - `Number` - `Decimal` - `Percentage` - `Fraction` - `Date` - `Time` - `Date time`
Format Description	Optional	Description of the asset format. Example: For the business term 'Employee's Hire Date,' the **Format Type** will be `Date`, and the **Format Description** will be the date format `YYYY-MM-DD`.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Security Level	Optional	Security Level of the asset with respect to the sensitivity of the information. This is manually specified for the asset and is suitable only as a governance record. It is not related to data classification or any other system classification. You can select one of the following options: - `Public`. The assets can be freely used, reused, and distributed without repercussions. - `Internal`. The assets are strictly accessible to internal employees who are granted access. - `Confidential`. Confidential assets are mostly protected by laws and access to these assets would require confidential data. - `Restricted`. Restricted assets, if compromised or accessed without authorization, can cause irreparable damage to the organization.

Column	Type	Description
Classification	Optional	Name for the Data Element or Data Entity Classification that you want to associate with the asset. Consider entering unique data element or data entity classification so that you can distinguish between different classifications. Type of Entry: Alphanumeric characters, including spaces and special characters such as –, _, /,\, &, (,), ., #, +, * and %. To specify multiple values, enter the values in the same row and use a semicolon to separate each value. Example: `First Name`,`BA Name: 29`
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Domain	Optional	Enter the reference ID or the name of the parent Glossary Domain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Domain asset.
Parent: Subdomain	Optional	Enter the reference ID or the name of the parent Glossary Subdomain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Subdomain asset.
Parent: Metric	Optional	Enter the reference ID or the name of the parent **Metric** asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent **Metric** asset.
Parent: Business Term	Optional	Enter the reference ID or the name of the parent Glossary Business Term asset. To form a hierarchy use one of the following columns: - **Parent: Subdomain** - **Parent: Metric** - **Parent: Business Term** - **Parent: Domain** Ensure that you specify only one parent Glossary Business Term asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Reference Data	Optional	Associate reference data from Reference 360 with metrics by entering the path of one or more code list attributes from Reference 360. Example: `Reference360Catalog Source/Country/Enterprise Country/Code` To enter multiple code list attributes, use a semicolon to separate each name. Do not use a space to separate multiple attributes. Ensure that all the attributes that you specify belong to the same code list. Example: `Reference Catalog Source/Country/Enterprise Country/Code;Reference Catalog Source/Country/Enterprise Country/Name;Reference Catalog Source/Country/Enterprise Country/Description`
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Legal Entity

A Legal Entity asset captures corporate entities, whether these are part of the customer's own group of companies or trusted partners and vendors, that can be used to make relationships to other business assets to provide context.

The following table describes the columns where you must enter asset values for legal entities:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Long Name	Optional	Long form name for the Legal Enity. Enter a value to make the Legal Entity easily identifiable by users. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in names. Example: If you have a legal entity with the name 'SO_ENT', you can enter '`State-Owned Enterprise`' in the **Long Name** field. This helps both technical teams and business teams to identify the legal entity.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Legal Entity	Optional	Enter the reference ID or the name of the parent **Legal Entity** asset. Ensure that you specify only one parent **Legal Entity** asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Manual Data Element

A manual data element is the business representation of data that might not be available in the catalog but is essential to capture for governance purposes in your organization. As a business user, you can manually create a data element within a data set. A data set can either have technical data elements or manual data elements or a combination of both. Although a manual data element is a type of business asset, it exists in a

business data set and not as a standalone business asset. You can associate a manual data element with one business data set only.

The following table describes the columns where you must enter asset values for manual data elements:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
AI System	Optional	Enter the reference ID or the name of the AI System asset that is the parent of the asset that you specified in the **Parent: Data Set** field. If multiple data sets have the same name as the asset specified in the **Parent: Data Set** field, consider specifying a value in the **System** field or the **AI System** field to help distinguish the parent Data Set asset from the other assets. Ensure that you specify only one parent asset. The AI System asset is a machine learning-based system that uses multiple AI models to perform a range of tasks, such as generating predictions, content, recommendations, decisions, and actions. The asset records information about the technologies, AI models, and data that is used to perform these tasks.

Column	Type	Description
Data Element Classification	Optional	Name for the Data Element Classification that you want to associate with the manual data element. To distinguish between different classifications, consider entering unique classification names. Type of Entry: Alphanumeric characters, including spaces and special characters such as –, _, /,\, &, (,), ., #, +, * and %. To specify multiple values, enter the values in the same row and use a semicolon to separate each value. To add a data element classification, prefix the data element classification with the term `ADD:`. To remove a data element classification, prefix the data element classification with the term `DELETE:`. Examples: To add data element classifications: `ADD:Classification1,Classification2` To remove data element classifications: `DELETE:Classification1,Classification2`
Glossaries	Optional	Enter the name or the Reference IDs of the glossaries that you want to associate with the manual data element. To enter multiple values, use a semicolon to separate each value. To add a glossary, prefix the glossary with the term `ADD:`. To remove a glossary, prefix the glossary with the term `DELETE:`. Examples: To add glossaries: `ADD:Glossary1,Glossary2` To remove glossaries: `DELETE:Glossary1,Glossary2`
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset's lifecycle to `In Review`. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.
System	Optional	Enter the reference ID or the name of the System asset that is the parent of the asset that you specified in the **Parent: Data Set** field. If multiple data sets have the same name as the asset specified in the **Parent: Data Set** field, consider specifying a value in the **System** field or the **AI System** field to help distinguish the parent Data Set asset from the other assets. Ensure that you specify only one parent asset.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Parent: Data Set	Required	Enter the reference ID or the name of the parent Data Set asset. Ensure that you specify only one parent Data Set asset.
Reference Data	Optional	Associate reference data from Reference 360 with the manual data element by entering the path of the code list attribute from Reference 360. You can associate only one code list attribute with a manual data element. Example: `Reference360Catalog Source/Country/Enterprise Country/Code`
Referenced Glossary	Optional	Enter the name or reference ID of a Glossary asset that is associated with reference data. The reference data that is associated with the Glossary asset gets associated with the manual data element. You can specify only one Glossary asset. Example: `TERM-102`
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Policy

A Policy asset represents an internal collection of rules and guidance on how to conduct business and manage data. They might be inspired by company goals, external regulations, or commercial agreements.

The following table describes the columns where you must enter asset values for policies:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Comments	Optional	Additional comments that apply to the asset. You can describe the policy in detail, add relevant comments, and provide links to policy related documents. Type of Entry: Formatted Text
Effective Date	Optional	Date on which the policy goes into effect. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: '`2023-09-27`'
End Date	Optional	Date on which the policy lapses. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: '`2023-09-28`' Ensure that you enter a value that occurs after the date that you specified in the **Effective Date** field.

Column	Type	Description
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Policy Type	Required	Type of the policy. You can select one of the following options: - `Conduct Standards`. A policy that guides conduct in various scenarios. - `Data Standards`. A policy that applies to data management. - `Technical Standards`. A policy that applies to technical management. - `Business Rule`. A policy that defines rules for business functions.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Policy	Optional	Enter the reference ID or the name of the parent **Policy** asset. Ensure that you specify only one parent **Policy** asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Process

Use a Process asset to document important business activities so that the activity can be contextualized through relationships. These activities allow business users to record the key reasons on why they consume data. Processes are typically structured as a parent process using the recognized name of the activity, with a

series of child process steps that explain the key stages involved in executing that activity. Each individual process object can have its own set of relationships to explain key metadata associations.

The following table describes the columns where you must enter asset values for processes:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Duration	Optional	Duration of the process. You can specify the process duration in weeks, days, or hours. Type of Entry: Specify a positive integer and enter `Hour`, `Hours`, `Week`, `Weeks`, `Day` or `Days`. The duration value isn't case-sensitive. If you enter only a positive integer, the system considers the process duration in days. Examples: - `4` - The system considers the process duration as 4 days. - `5 week` - The system considers the process duration as 5 weeks. - `7 HOUR` - The system considers the process duration as 7 hours.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Process Type	Optional	The type of process. You can select one of the following values: - `Process`. An entire process. - `Step`. A specific step in the process. - `Control`. An intermediate option within the process that determines the direction of the subsequent steps.
Step Type	Optional	Specify the type of step in the process. You can select one of the following values: - `Common`. A step that is linked to more than one tasks in a process. - `Starting`. The starting step indicates the onset of a process and a process can have only one starting step. - `Ending`. The ending step specifies that the process is completed or failed.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Process	Optional	Enter the reference ID or the name of the parent **Process** asset. Ensure that you specify only one parent **Process** asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Project

A Project asset represents a collection of activities that are planned and organized to achieve a particular set of objectives.

The following table describes the columns where you must enter asset values for projects:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Start Date	Optional	Date on which the project work commences. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: '`2023-09-27`'
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
End Date	Optional	Date on which the project work is completed. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: '`2023-09-28`' Ensure that you enter a value that occurs after the date that you specified in the **Start Date** field.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Project	Optional	Enter the reference ID or the name of the parent **Project** asset. Ensure that you specify only one parent **Project** asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Regulation

Use a Regulation asset type to document the important clauses of a major legislation. A regulation is a key driver of internal policies that direct how an organization conducts its business.

The following table describes the columns where you must enter asset values for regulations:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Long Name	Optional	Long form name for the Regulation. Enter a value to make the regulation easily identifiable by users. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in names. Example: If you have a regulation with the name 'ENV_PROTECT', you can enter '`Environmental Protection Regulation`' in the **Long Name** field. This helps both technical teams and business teams to identify the asset.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Regulation	Optional	Enter the reference ID or the name of the parent **Regulation** asset. Ensure that you specify only one parent **Regulation** asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

System

A System asset represents a recognizable location or application that typically contains multiple data sets. In a System asset, the system name is often more business-friendly than the technical names used for technical

assets. The system name allows the business users that create and manage the data to easily identify the asset.

The following table describes the columns where you must enter asset values for systems:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Asset ID	Optional	Asset ID is a unique identifier that represents the system uniquely in its source. This value is useful for scenarios where you already have a specific way to depict the system at its source. The Asset ID value represents the system uniquely in its source while the Reference ID value represents the system uniquely in Data Governance and Catalog. For example, a system is uniquely identified at the source level as '`SYSTEM_10`', which is its Asset ID value. Meanwhile, as per the governance operating model, the same system can be assigned a Reference ID value '`SYS-1`' through automated generation or '`SYS MODEL 1`' manually. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: '`SYSTEM_10`'

Column	Type	Description
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Long Name	Optional	Long form name for the system. Enter a value to make the system easily identifiable by users. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in names. Example: If you have a system with the name 'Sys_Gdw', you can enter '`Global Data Warehouse System`' in the **Long Name** field. This helps both technical teams and business teams to identify the system.
System Purpose	Optional	Indicates the purpose of the system that best describes its function. Choose from a list of predefined values.
System Type	Optional	Select the type that represents the system asset. You can select one of the following options: - `Software Application`. The system type that performs specific functions for the end users by directly interacting with it. - `File System`. A system type that manages, stores, and organizes files and directories on a storage device. It facilitates convenient identification and retrieval of data. - `Email`. Email is the method of exchanging computer-stored messages from one system to another. - `Paper` . A traditional system type that stores and organizes information using paper documents. - `User Specified`. A tailor-made system type that is developed for specific user or organization.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: System	Optional	Enter the reference ID or the name of the parent **System** asset. Ensure that you specify only one parent **System** asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Stakeholders

Stakeholders are authorized users who are responsible for the asset, and can approve or reject change requests for the asset.

The following table describes the columns where you must enter values to assign stakeholders to assets:

Column	Type	Description
Asset	Required	Name or Reference ID of the asset. If you have one or more assets with the same name, consider entering their respective **Reference ID** values to help the system to distinguish between them.
Asset Type	Required	Type of the asset for which you want to specify the stakeholders. Enter the exact name of the asset type. Examples: `Business Term`, `Domain`

Column	Type	Description
User or User Group	Required	User or user group that you want to assign as stakeholders of the asset. Enter one stakeholder per asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, the username, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. The respective user or user group page URL contains the internal ID. Example of an internal ID: `23XVYy0NVSdiVYcf4ItJaQ` Example of an email address: `steve@yourorg.com` Example of a user name: `eclarke` Example of a full name: `Rhodes,Jane`
Role	Required	Role of the Stakeholder that you want to assign to the asset. If the user or user group that you want to assign as the asset stakeholder has multiple roles assigned to them, enter each role in a new row. Do not use comma to separate the values.
Operation	Required	Select an operation for the stakeholders. You can select one of the following options: - `Create`. You want to add a stakeholder to an asset. - `Delete`. You want to remove the stakeholder of an asset.

Relationships

A relationship between assets shows how the assets relate to one another. When data from a source system is ingested into the catalog, Data Governance and Catalog can automatically create relationships among the

technical assets of that source system. You can connect business assets to each other and to relevant technical assets using different types of relationships.

The following table describes the columns where you must enter values to create relationships between assets:

Column	Type	Description
Source Asset	Required	Name or Reference ID of source asset of the relationship. If you have one or more source assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Source Asset Type	Required	Enter the exact name of the asset type of the source asset. Examples: `Business Term`, `Domain`
Target Asset	Required	Enter the name or Reference ID of target asset of the relationship. If you have one or more target assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Target Asset Type	Required	Enter the exact name of the asset type of the target asset. Examples: `Business Term`, `Domain`
Relationship Type	Required	Type of the relationship between the source asset and the target asset. Enter the exact type of the relationship. To see all possible values that you can enter here, see the Relationship Type column in the Annexure sheet of the spreadsheet. Examples: `Is related to`, `Parent Child Relationship` For more information about the predefined relationships that can be created between assets, see the *Types of direct relationships* topic in the *Asset Discovery* help. **Note:** It's possible that one or more of the relationship types listed in the Annexure sheet are exclusive to your organization. To ensure that you have the updated list of relationship types, consider downloading the latest template file. For more information about such relationships, contact your administrator. For more information about how your administrator can customize relationship types, see the *Administration* help in Metadata Command Center.
Operation	Required	Select an operation for the relationship. You can select one of the following options: - `Create`. You want to create a relationship between assets. - `Delete`. You want to remove a relationship between assets.

Note: In the predefined Microsoft Excel template that you download, you can refer to the **Annexure** sheet for the relationships that you can create in Data Governance and Catalog.

CHAPTER 3

Bulk import process

Create, update, or delete assets in bulk using the bulk import process.

To create, update, or delete a large number of business assets in the catalog, enter the asset details in one or more predefined Microsoft Excel template files and import the files to Data Governance and Catalog. You can curate technical assets and enrich them with governance metadata by importing a Microsoft Excel (.xlsx and .xlsm) file but cannot create or delete them through the bulk import process.

Alternatively, you can search for business or technical assets in the catalog and export the results of the search to a Microsoft Excel file. You can then update the exported file to enrich and curate the assets, or mark the exported business assets for deletion. After making changes to the exported file, you can re-import the file to Data Governance and Catalog.


Import assets using template files

Import business assets in Data Governance and Catalog using the predefined template files for each asset type.

Download predefined Microsoft Excel (.xlsx and .xlsm) templates for different asset types from Data Governance and Catalog, enter the details of assets in the templates, and import the template files. Data Governance and Catalog reads the details of assets in the template files and then creates, updates, or deletes assets in the catalog depending on the operation specified in the template file.

Alternatively, you can also use your own Microsoft Excel file to import the assets into the catalog. Informatica recommends that you use the predefined templates that you download from Data Governance and Catalog.

The following image shows the steps that you need to perform to bulk import assets in Data Governance and Catalog using the template file:



Perform the following tasks to import assets into the catalog using the template files:

- "Step 1: Get template file" on page 109
- "Step 2: Populate template file" on page 110
- "Step 3: Import the file" on page 111
- "Step 4: Prepare to import the assets" on page 112
- "Step 5: Start import of assets" on page 114

After you successfully import assets using the bulk import template file, you can search and find the imported assets in Data Governance and Catalog.

Step 1: Get template file


Download a predefined Microsoft Excel (.xslx and .xlsm) template file for the asset types that you want to import.

When you download a predefined template, the file already contains the field names that you must enter for the assets. The file also indicates the properties that are mandatory and the properties that are optional. The column header cells contain notes for the properties to help you enter the values correctly. When you download the template file for an asset, you can also download additional sheets for adding relationships between assets and adding stakeholders. To ensure that the bulk import operation is successful, download the latest predefined template.

To download the template for any asset, the organization administrator must assign the read privilege for the Role asset to your user role in the Administrator service.

Perform the following steps to download a template file:

1. On the **Home** page, click **New** > **Import Assets** > **Download Import Template**.
2. In the **Download Import Template** dialog box, select the asset types and additional fields for which you want to import values.



Note: The following information applies to other file types that you can use apart from the predefined template:

- Instead of using the predefined template, you can use your own Microsoft Excel (.xslx and .xlsm), comma-separated value (.csv), or archive (.zip) file to import the assets. However, this requires you to manually map each sheet, column, or parameter in the file to the fields in Data Governance and Catalog. Consider using the predefined template files to upload the assets. The system can read the predefined templates quickly and import the assets correctly.
- The archive (.zip) file can contain a combination of Microsoft Excel (.xslx and .xlsm) and comma-separated value (.csv) files within it.

3. Click **Download**.

Step 2: Populate template file

After you download the template file, enter the asset details in the file.

For more information about entering asset values in the template file, see Chapter 2, “Template file properties” on page 10.
The following guidelines apply when you populate a template file:

- Each asset type appears as a separate sheet in the Microsoft Excel template file. In each sheet, enter the asset details. Enter one asset per row. Column headers in red color indicate a mandatory field, and column headers in black color indicate an optional field. See the note in the column headers for helpful tips on entering the asset details correctly.

  Note:

  - The columns in the template file will depend on how the asset's fields are configured by your administrator. If your administrator has configured new custom fields for an asset, it might affect the order of all the fields in the template file.
  - The order in which you specify the assets in the import file doesn't influence the sequence in which the assets are imported. The asset import sequence is randomized.

- An asset's position in the import sequence determines the ref ID that the system assigns to it. Consider the following example:

  You want to import a file that contains 10 assets that are of a type that is not present in your catalog. In the import file, you had specified the details about `Asset 1` in the first row, about `Asset 2` in the second row and so on. Despite this, it is possible for `Asset 1` to be the tenth asset in the import sequence. If `Asset 1` is the tenth asset that is imported, the system assigns the ref ID `AST-10` to it.


- If you are using your own personalized Microsoft Excel file, make sure that you enter one asset per row while populating the file with asset details.
- If you are using a comma-separated value (.csv) file, make sure that you populate the file as per the rules of the .csv file format.
- If you are using an archive (.zip) file with multiple supported file formats, make sure that you archive the import files.
- If you are updating the name of the stakeholder of an asset, add a space only between the first name and the second name of the stakeholder in the template file. For stakeholder names with more than two words, enter the username or the email ID of the stakeholder in the template file. For example, to enter `John Daniel Smith` as a stakeholder, enter the username `johndsmith`.

Step 3: Import the file

After you populate one or more template file, import the files containing asset details into Data Governance and Catalog.

Perform the following steps to import one or more files:

1. On the **Home** page, click **New** > **Import Assets** > **Import**.
2. On the **New Import** page, click **Import Files** and select the import file, or drag the file to the window. Ensure that the file name doesn't contain the following characters: `[, /, !, {, }, ], |, <, [, ^, >, ], *, >`



   When you import the file, the system reads the file to understand and interpret the values for any errors.
3. The system verifies for duplicate files with the same file name. If there is a duplicate file, you can select an option from the **Duplicate Files** dialog box.


Step 4: Prepare to import the assets

You can validate the asset types and columns from the import files to map with the respective asset types and the asset properties that are imported into Data Governance and Catalog.

Preparing a predefined import file

If you use a predefined Microsoft Excel file as the template, the column headers should already map correctly to the correct interface fields. Before you move to the next step, perform the following steps to verify that the mapping is correct:

1. In the **New Import** dialog box, select the sheet in the template file for which you want to map the column headers. Each sheet corresponds to an asset type.




2. Confirm if the column header in the import file corresponds to the correct field in Data Governance and Catalog.

Preparing a custom Microsoft Excel file

If you use a custom Microsoft Excel file as the template, the sheets in the file might not match the asset types in Data Governance and Catalog. Before you move to the next step, perform the following steps to verify that the mapping is correct with the corresponding asset types that you want to import:

1. Click **Map Sheets** for the custom Microsoft Excel file.
2. In the **Map Sheets** dialog box, map the sheets in the file to the corresponding asset types in Data Governance and Catalog.


3. Click **OK** to map the sheets.



Preparing a CSV file

If you use a comma-separated value (.csv) file as the template, the data in the file might not match the asset types in Data Governance and Catalog. Before you move to the next step, perform the following steps to verify that the mapping is correct with the corresponding asset types that you want to import:


1. Click **Map File** for the comma-separated value (.csv) file.
2. In the **Map File** dialog box, select the asset type that corresponds to the file in Data Governance and Catalog.
3. Click **OK** to map a .csv file.



Preparing an archive file

The archive (.zip) file can contain a combination of Microsoft Excel (.xslx and .xlsm) and comma-separated value (.csv) files. Before you move to the next step, perform the following steps to import the assets into Data Governance and Catalog:

1. Click **Map Files** for the archive (.zip) file to map the constituent files and sheets with the corresponding asset types.
2. In the **Map Files** dialog box, map the sheets of each individual file type to the corresponding asset types in Data Governance and Catalog.
3. Click **OK** to map the files.




Step 5: Start import of assets

When the file is ready and you have mapped all the asset types and asset properties in the file with the corresponding asset types and asset properties in Data Governance and Catalog, you are ready to import the assets.

Perform the following steps to import a file:

1. Click **Start Import**.

2. In the **Start Import** dialog box, enter the **Job Name** field and select an **Error Handling** option.




The following table lists the **Error Handling** options:

Error type	Description
Stop import on warning	The system evaluates the data in the file. If the system encounters a row with warning data, the process stops, and no data is imported. Select this option if you want to import only data that is correct and ready for use.
Stop import on error	The system evaluates the data in the file and ignores rows with warning data. If the system encounters a row with error data, the process stops, and no data is imported. If there are no rows with error data, the system imports valid data from the file, and warning data is marked as skipped. Select this option if you want to ignore the warnings and proceed with the import process. You can later download the error report, correct the warning data, and re-upload the file.
Skip errors and warnings	The system imports all valid rows from the template. Rows with warning and error data are marked as skipped. Select this option if you want to ignore the warnings and errors and proceed with the import process. You can later download the error report, correct the warning and error data, and re-upload the file.

3. Click **Start Import**.

   A new page displays the progress of the import file.

4. The new import file page displays the **Job Status**, **Job Summary**, **Job Details**, and **Imported Assets** fields.



Note: If assets in the import file are still in-review lifecycle status, such assets cannot be imported to Data Governance and Catalog. Only assets that in published and draft status can be imported to the catalog.

Managing tickets for imported assets

If an asset that you create or update through bulk import is associated with a workflow, Data Governance and Catalog triggers the ticket creation for that asset type.

After the import job is complete, you can view the tickets created for the imported assets.


1. On the import file page, click **View Details** from the **Imported Assets** section.
2. Select the tickets associated with each asset to view their details on the **Ticket Manager** page.

   Note: When you manage tickets for assets, consider the following guidelines:

   - When you specify that a ticket is required for a new asset, the bulk import operation creates assets in the Draft state. The system doesn't consider the Lifecycle value that you specified in the template and is driven by the workflow configuration in Metadata Command Center.
   - The system creates tickets only if all required stakeholders are specified. If some required stakeholders are missing, the asset update and ticket creation will fail.
   - When you delete assets, the system checks for open tickets associated with the asset. The system can't delete assets that have open tickets.

For more information about managing tickets, see Workflows and tickets in the Asset Management help.

The following image shows the **Imported Assets** dialog box with asset details like **Name**, **Operation** and **Ticket**.



Re-import assets from an exported search results file


If you exported the results of a search, you can perform the following activities on the exported file and bulk re-import technical and business assets in Data Governance and Catalog:

- Enrich the exported file by adding additional information to technical and business assets. For example, you can add name, description, custom attribute, and so on. You can only update technical assets but cannot delete.
- Add business metadata to technical assets. For example, associate data elements to a business term.
- Curate glossary terms for technical assets by accepting or rejecting recommended glossary terms, or adding glossary terms to the asset.
- Curate data element or data entity classifications for technical assets. You can accept or reject the classification recommendations, or add classifications to the asset. You can promote, reject, or demote generated classifications for the asset.
- Curate document classifications for unstructured data assets such as PDFs and text files. You can accept or reject classification recommendations, or manually add document classifications to the asset.
- Create and delete relationships between business assets.

After updating the exported file, you can re-import this updated Microsoft Excel file with your changes to Data Governance and Catalog.

Use the export search results file to share it with governance users and data scientists for review purposes before re-importing to the system, and also share the updated export files within the team or across other team to create awareness about all assets available within the organization. You can only export technical and business assets but cannot export collaborations, tickets, classification definition, or relationships in the export file.

The following image shows the steps required to bulk re-import assets to Data Governance and Catalog:



Step 1. Exporting the search results in a Microsoft Excel file


You can search for assets and export the results of a search as a Microsoft Excel file in .xlsx or .xls file format.

You can export the search results only if your user role has the Export privilege for exporting search results. To import updated assets back in the catalog, ensure that your user role has the Import privilege. Both the Import and Export privileges are enabled by default for the Governance Administrator role.

Note: Data Governance and Catalog triggers a faster import if you export up to 10,000 assets and don't include their relationships.


1. Enter a search query in the search bar.
2. Optionally, apply one or more filters to your search. You can additionally sort the search results.
3. On the **Search Results** page, click **Action**.

   The **Action** menu appears.



4. Click **Export**.


The **Export Assets** dialog box appears.



5. On the **Export Assets** dialog box, enter a new file name or retain the system-generated file name.
6. Optionally, select the following options:
   - **Include Child Assets**. Export all child assets associated with parent assets.
   - **Include Asset Details**. Export the custom attributes and stakeholder details of all assets and additional details of technical assets.

     Note: If you select the **Include Asset Details** option, the export file for technical assets includes sheets where changes are restricted. To curate assets, use the editable columns in the **Technical Data Set** and **Technical Data Element** sheets.
   - **Include Relationships**. Export the relationships between business assets and between business assets and technical assets.
     The **Export Assets** dialog box displays the **Include Relationships** check box if the search results contain business assets.
7. Click **Start Export** to export the results of your search.

   This triggers an export job that you can monitor on the **Job Status** panel.
   The **Job Status** page appears.



Note: A Microsoft Excel export file can contain a maximum of 50,000 assets. If the export contains over 50,000 assets and you choose the Microsoft Excel file format, the downloaded file is compressed into a ZIP file format. If you choose the CSV file format for over 50,000 assets, the downloaded file contains all the assets in a single file.

8. After the export job is complete, click **Download Export File**.
9. Optionally, check the status of your export job on the **Job Monitoring** page.

Step 2. Modify the exported file

Download the Microsoft Excel export file containing the results of a search, and modify the exported file in order to enrich business and technical assets with additional information.

The format of the export files for business assets is similar to the bulk import template files. The export files contain a table of contents and one sheet each for assets of the same type. Each asset sheet has some columns where changes are restricted. You can add, delete, or modify values in the available fields before re-importing the file in Data Governance and Catalog.

The following guidelines apply if you want to modify the contents of an exported file:

- To delete the value of a field of an asset using the UPDATE operation, replace the value in the field with double quotes without spaces.
- To create or modify the value of a custom attribute where the value contains a comma, enclose the value in double quotes and without spaces. For example, a multiselect drop-down for an asset has the following values:

  - `string`

  - `apache`

  - `home,work`

  Enter the values in the bulk import file cell in the following format: `string,apache,"home,work"`.
- Use a column header to sort the contents of the file. When you sort the contents of the file by ref ID, Microsoft Excel sorts the assets only alphabetically. You can't sort the assets numerically.

Modify the exported file in one of the following ways:

Enrich assets in bulk

Enrich the exported technical assets with business context using the available fields in the exported file. For example, add or update the business names and descriptions of technical data sets and technical data elements. To enter a description for the assets while re-importing technical assets into the catalog, use the **Description** field of the exported file.

Note: The values in the **Business Description** field is ignored during the re-import process. Copy the data from the **Business Description** field to the **Description** field before re-importing the file.

Create relationships between the technical and business assets. For example, associate data element to a business term.

Associate reference data with data elements in bulk

Modify the exported data elements to associate reference data with data elements from Reference 360. You can then import the exported file back to Data Governance and Catalog to make the association between the data elements and the reference data.

The following table describes the two columns in the template to associate reference data with data elements.

Column	Type	Description
Reference Data	Optional	Associate reference data from Reference 360 with the data element by entering the path of a code list attribute from Reference 360. You can associate only one code list attribute with data element. Example: `Reference360Catalog Source/Country/Enterprise Country/Code`
Referenced Glossary	Optional	Enter the name or reference ID of a Glossary asset that is associated with a reference data. The reference data that is associated with the Glossary asset gets associated with the data element. You can specify only one Glossary asset. Example: `TERM-102`

Curate assets in bulk

Use the exported technical data set and technical data element sheets to curate assets in bulk and re-import the file into Data Governance and Catalog.

The following ways describe how you can curate glossary and data classification recommendations for technical data sets and data elements:

Accept or reject system-generated glossary recommendations

The **Glossaries: Recommended** field contains the system-generated glossary recommendations for the assets. Use the **Glossaries: Accepted** or **Glossaries: Rejected** fields in the exported sheets to accept or reject a recommendation.

Accept or reject classifications

Use the following fields in the export sheets to accept or reject classifications:

- For technical assets, use the **Data Classifications: Accepted** and **Data Classifications: Rejected** fields to accept or reject data classifications.
- For unstructured technical assets, use the **Document Classifications: Accepted** and **Document Classifications: Rejected** fields to accept or reject document classifications.

Automatically assign business names and descriptions to technical data elements

You can choose to automatically assign business names and descriptions to the technical data elements. The system assigns the business name and description to the technical data element from either an accepted glossary or from a glossary in the catalog that isn't already rejected for the data element.

To automatically assign business names and descriptions to the technical data elements during glossary association, specify the value of the **Automatic Assignment** field as `Enabled` in the technical asset export sheet. In the **Glossary: Accepted** field, enter the name or reference ID of an accepted glossary that you want to use to assign a business name and description to the technical data element. To curate the technical data element with a glossary in the catalog which isn't already accepted for the data element, enter the name or reference ID of the glossary in the **Business Name** column.

To add a business name manually for the technical data element, select the `Disabled` value for **Automatic Assignment** field. If you don't specify a value for the **Automatic Assignment** field, the system considers the input value as `Disabled`.

The following guidelines apply if you choose to automatically assign business names and descriptions to the technical data elements:

- If multiple glossaries are assigned the name that you specified in the **Glossary: Accepted** field, enter the reference ID of the glossary in the **Glossary: Accepted** field to enable the system to differentiate between duplicate glossaries.
- If you specify multiple glossaries in the **Glossary: Accepted** field, enter in the **Business Name** field the name of glossary that you want to use to assign a business name and description to the technical data element.
- If multiple glossaries are assigned the business name that you specified in the **Business Name** field, enter the reference ID of the glossary in the **Business Name** field to enable the system to differentiate between duplicate glossaries.
- In the **Glossary: Accepted** and the **Business Name** fields, enter the name of the glossary that isn't already rejected for the technical asset.
- If multiple glossaries are assigned the name that you specified in the **Glossary: Rejected** field, enter the reference ID of the glossary in the **Glossary: Rejected** field to enable the system to differentiate between duplicate glossaries.


Update generated classifications in bulk

The **Generated Classifications: Recommended** field of the technical data element sheet shows generated classifications for data elements. To reject the generated classifications that you don't wish to promote, use the **Generated Classification: Rejected** column of the technical data element sheet.

To bulk promote generated classifications to data element classifications, or demote already promoted data classifications, perform the following tasks:

- Search and export all generated classifications in a Microsoft Excel file.
- On the generated classification sheet, use the **Data Element Classification: Promoted** column to promote a generated classification to a data element classification.
- Demote an already promoted data classification by using the **Data Element Classification: Demoted** column.

The following image shows the Generated Classification sheet that you can use to promote or demote generated classifications in bulk:



Create or delete asset relationships in bulk

If you chose to include asset relationships in the exported file, you can create or delete relationships between business assets in bulk and re-import the file into Data Governance and Catalog.

The following table describes the columns that you can view in the exported file:

Column	Type	Description
Source Asset	Required	Name or Reference ID of the source asset of the relationship. If you have one or more source assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Source Asset Type	Required	Enter the exact name of the asset type of the source asset. Examples: `Business Term`, `Domain`
Target Asset	Required	Name or Reference ID of the target asset of the relationship. If you have one or more target assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Target Asset Type	Required	Enter the exact name of the asset type of the target asset. Examples: `Business Term`, `Domain`
Relationship Type	Required	Type of the relationship between the source asset and the target asset. Enter the exact type of the relationship. Examples: `Is related to`, `Parent Child Relationship` For more information about the predefined relationships that can be created between assets, see the *Types of direct relationships* topic in the *Working With Details* help.
Operation	Required	Select an operation for the relationship. You can select one of the following options: - `Create`. You want to create a relationship between assets. - `Delete`. You want to remove a relationship between assets.

Step 3. Preparing to re-import the exported file

You can validate the business and technical asset types and map columns from the re-import file with respect to asset types and the asset properties imported to Data Governance and Catalog. Use the updated exported file to re-import business and technical assets to Data Governance and Catalog. The format of the


updated exported file is same as the predefined import template file. Before you move to the next step, perform the following steps to verify that the mapping is correct:

1. In the **New Import** page, click **Add Files**.

   Select the re-import file of same or different asset types. Each sheet corresponds to an asset type.

   Note: You can also bulk import technical assets.

   Validate and map the re-import assets on the **New Import** page. The technical data sets do not have custom fields so the drop-down icon to map column is not enabled for technical assets after validating the technical assets sheet. The business assets can have custom fields so the drop-down icon is enabled, you can manually map the custom field with the respective field in the system. For example, see the following image, the Metric_Export.xlsx (business assets) row displays the drop-down icon to manually map the custom field with corresponding field in the system.



2. Verify, if the column header in the exported file corresponds to the correct field or column name in Data Governance and Catalog.

   From the **New Import** page, manually map the business assets custom field to the respective field by choosing the column name available in the system from the drop-down list.

Step 4. Re-importing the exported file

When the file is ready and you have mapped all the asset types and asset properties in the exported file with the corresponding asset types and asset properties in Data Governance and Catalog, you are ready to re-import the assets.


Note:

- When you export technical assets, the exported file might have several sheets that contain the same attributes for the same assets. In such a file, some attributes are editable only in one sheet but not in the other. This prevents any kind of conflicting updates for the same asset.

  For example, if you export a relational database asset, the exported file might contain attributes in the Column, Database and Schema sheets that are also present in the Catalog Source, Technical Data Source, Technical Data Set, and Technical Data Element sheets. These attributes are not editable in the Column, Database and Schema sheets. The rows for these attributes are greyed out in the file. To modify the same attributes, update the values in the Catalog Source, Technical Data Source, Technical Data Set, and Technical Data Element sheets.

- When you export a child asset with the **Inherited Stakeholder Assignment** status, and then you assign new stakeholders and re-import this child asset, only the stakeholders that are added using the bulk import process display the **Stakeholder Assignment** status as **Specifically Assigned**. The stakeholders with the **Inherited Stakeholder Assignment** status are removed.

1. On the **New Import** page, click **Start Import**.
2. In the **Start Import** dialog box, enter the job name and select an **Error Handling** option.




The following table lists the **Error Handling** options:

Error type	Description
Stop import on warning	The system evaluates the data in the file. If the system encounters a row of data with warnings, the process stops, and no data is imported. Select this option if you want to import only data that has no warnings.
Stop import on error	The system evaluates the data in the file and ignores rows of data with warnings. If the system encounters a row with errors, the process stops, and no data is imported. If there are no rows with errors, the system imports valid data from the file, and warnings are marked as skipped. Select this option if you want to ignore the warnings and proceed with the import process. You can later download the report, correct the data with warnings, and re-upload the file.
Skip errors and warnings	The system imports all valid rows from the template. Rows of data with warnings and errors are marked as skipped. Select this option if you want the ignore the warnings and errors and proceed with the import process. You can later download the report, correct the warnings and errors for the data, and re-upload the file.

3. To import the assets, click the **Start Import**.
   If the exported search results file has assets in review lifecycle status, such assets cannot be re-imported to Data Governance and Catalog. You cannot update or delete an asset in the in-review lifecycle status, assets that are only in the published and draft lifecycle status are re-imported to Data Governance and Catalog.

   The job is triggered. Click the corresponding job from the **Job Monitoring** page or **Notification** page to display the progress of the re-import file.




4. The job page displays the **Job Status**, **Job Summary**, **Job Details**, and **Imported Assets** fields.

The re-import file is uploaded to the Data Governance and Catalog

Viewing import job status


When you import assets using the bulk import process, Data Governance and Catalog creates a job for the bulk import task. You can monitor the status of the job in Data Governance and Catalog to determine the completion status.

1. On the **Home** page, click the **Job Monitoring** icon.



The **Job Monitoring** page displays the list of all jobs.

2. View basic information such as job type, start and end date, and the status of each job on this page.



3. To download job log, click the **Action** menu for the job, and click **Download Log**.
4. To see more details of the job, click the job name to open the job on a new page.

   After the import job is complete, verify the assets and asset details that you have imported by opening the assets in Data Governance and Catalog.

Note: Irrespective of the import job status, verify the assets and asset details that you have imported by opening the assets in Data Governance and Catalog.

CHAPTER 4

Troubleshooting bulk import of assets

Consider the following troubleshooting tips when you export or import assets in bulk.

If you export data quality rule occurrences that are associated with data quality scorecards, Data Governance and Catalog does not export the primary data elements associated with the rule occurrences.

Also, if you update the rule occurrences and re-import them back into Data Governance and Catalog, the bulk import operation does not update the rule occurrences.

To make changes to these scorecard rule occurrences, use Cloud Data Profiling.

If you export assets that contain images and then re-import the exported file, the images are not re-imported back into Data Governance and Catalog.

You cannot import images using the bulk import process. Instead, use the user interface to update or add a new image.

The bulk import job fails if I create a glossary and assign it to an asset during the same job.

Creating the glossary and assigning it to an asset during the same bulk import job might cause the bulk import to fail with an error.

To associate a glossary with any asset, first create the glossary and then associate the glossary with the asset during the next bulk import job.

If you are a user with the Super Admin privilege and you mark a parent asset for deletion through the bulk import process, then all the child assets in the hierarchy are automatically deleted. This might lead to errors.

As a workaround, delete all the child assets in a bulk import operation, and then delete the parent asset in a different operation.

For the same asset, you cannot update one parent in the hierarchy and delete another parent in the hierarchy using the same bulk import job.

For example, you cannot delete the parent subdomain `Payroll` and update the parent domain `Finance` in the same bulk import job.

To work around this, first, delete the parent asset using the DELETE operation and run the bulk import operation. You can then add another parent asset using the UPDATE operation and run the bulk import operation again.

INDEX

A

asset
  importing assets 108

B

bulk import process
  preparing a custom Microsoft Excel file 112
  preparing a predefined import file 112, 124
  preparing an archive file 114
  step 1:get template file 109
  step 2:populate template file 110
bulk import process *(continued)*
  step 3:add the import file 111
  step 4:prepare to import the files 112
  step 5:start import of assets 114
Bulk import template
  Stakeholders 105
business assets
  viewing import job status 126

O

overview
  bulk import 6