How-To Library

Informatica

Configuring Hierarchy and Network Relationships

© Copyright Informatica LLC 2020, 2021. Informatica and the Informatica logo are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html.

Abstract

You can use the Provisioning tool to configure hierarchy and network relationships between business entities. This article describes how to configure hierarchy and network relationships between business entities.

Supported Versions

- Multidomain MDM 10.4 or later

Table of Contents

Configuring Hierarchy and Network Relationships Overview. 2
Hierarchy Relationships. 3
Network Relationships. 4
Prerequisites. 4
Configuring Hierarchy Relationships. 5
Step 1. Create a Hierarchy. 5
Step 2. Configure the Root Node in a Hierarchy. 5
Step 3. Add a Business Entity to a Hierarchy. 6
Step 4. Configure a Hierarchy Relationship. 6
Step 5. Configure the Hierarchy Settings. 7
Step 6. Configure Additional Relationship Attributes (Optional). 8
Configuring Network Relationships. 9
Step 1. Add a Business Entity to the Network. 9
Step 2. Configure a Network Relationship. 9
Step 3. Configure the Network Settings. 10
Step 4. Configure the Relationship Properties (Optional). 11
Configuring Hierarchy Tasks. 12
Step 1. Configuring a Hierarchy Task Type. 12
Step 2. Configuring a Hierarchy Task Template. 13
Step 3. Configuring Hierarchy Workflow Triggers. 15
Configuring Default Hierarchy for the Dashboard. 16
Designing Data Director Interfaces to Manage Relationships. 16

Configuring Hierarchy and Network Relationships Overview

A relationship is a connection between two business entities. Use the Provisioning tool to configure hierarchy relationships and network relationships between business entities. Then Data Director users can use the relationships between business entities to create relationships between records.

You can create the following relationships:

hierarchy relationship

A connection between two business entities that is hierarchical. For example, the Organization business entity acts as the parent of the Person business entity.

network relationship

A connection between two related business entities. For example, the Person business entity is related to the Credit Card business entity.

Important: If you have relationships in Hierarchy Manager that you want to continue to use, you must upgrade your relationships and create them as hierarchy relationships or network relationships. For instructions about upgrading hierarchies, see the *Multidomain MDM Upgrade Guide*.

Hierarchy Relationships

A hierarchy consists of a root business entity node and hierarchy relationships that define parent-child relationships between business entities. When you create a hierarchy, you must specify a business entity as the root node. Then you add a business entity to the hierarchy and configure a hierarchy relationship from the root business entity to the business entity.

You can add additional business entities and configure hierarchy relationships between the business entities. Each hierarchy relationship in a hierarchy must have a direct or indirect relationship to the root business entity. You can create as many hierarchy relationships as you need to represent the hierarchy model.


For example, a telecom service provider wants to track individual subscribers based on their country of origin. In the Provisioning tool, create the following hierarchy relationships:

1. Create an Organization hierarchy to show the relationships between the Telecom Service Provider, Country, and Subscriber business entities.
2. Configure the Telecom Service Provider business entity as the root node in the hierarchy.
3. Create a hierarchical relationship named *SubscriberIn* between the Telecom Service Provider business entity and Country business entity.
4. Create a hierarchical relationship named *Subscriber* between the Country business entity and Subscriber business entity.

Later, you can create the following hierarchical relationship between records in the Data Director:

- From Vodafone record to South-Korean record.
- From South-Korean record to Jung Su-young record.

The following image shows a sample hierarchy model in the Hierarchy Designer:



Network Relationships

The network is a collection of network relationships between business entities. A network relationship is a connection between related business entities.

When you edit the network, you add business entities and configure network relationships between the business entities. Each network relationship becomes part of the network of relationships. The network does not contain a root node.


For example, an automobile ancillary manufacturer wants to track automobile manufacturers based on the spare parts they have purchased. In the Provisioning tool, create the following network relationships:

1. Create a network relationship named *AutoManufacturerIn* between the Automobile Ancillary Manufacturer business entity and the Automobile Manufacturer business entity.
2. Create a network relationship named *ProductsIn* between the Automobile Ancillary Manufacturer business entity and the Spare Parts business entity.
3. Create a network relationship named *AutoManufacturerOwnProducts* between the Automobile Manufacturer business entity and the Spare Parts business entity.

Later, you can create the following network relationships between the records in the Data Director:

- Magna International Inc record to Aston Martin record.
- Magna International Inc record to Hybrid Transmissions record.
- Aston Martin record to Hybrid Transmissions record.

The following image shows a sample network in the Network Designer:



Prerequisites

Before you configure the relationships, perform the following prerequisite tasks:

1. Create base objects in the MDM Hub.
2. Define the business entity structure.
3. If you want to add additional attributes for a relationship, ensure that the required columns are present in the base object that maintains the relationship.

Configuring Hierarchy Relationships

Configure a hierarchy by adding a root business entity node, adding business entities, and then configuring hierarchy relationships between business entities.

To configure hierarchy relationships, perform the following steps:

1. Create a hierarchy.
2. Configure a root node in a hierarchy.
3. Add a business entity to a hierarchy.
4. Configure a hierarchy relationship.
5. Configure the hierarchy settings.
6. Optionally, configure additional relationship attributes.

Tip: You can configure icons that represent business entities and business entity records in Data Director. When Data Director users view business entities in the **Hierarchy** view, the icon for each record appears.

Step 1. Create a Hierarchy

Create a hierarchy to contain a collection of hierarchy relationships. For example, you want to configure the organization hierarchy for your business.

1. Click **Business Entity** > **Modeling**, and then select **Hierarchies**.
2. Click **Create** > **New Hierarchy**.
3. In the properties panel, specify the following hierarchy properties:

Property	Description
Name	Unique name for the hierarchy.
Label	Label for the hierarchy.
Description	A meaningful description for the hierarchy.

4. Click **Apply**.

The hierarchy name appears in the modeling panel and the hierarchy structure appears in the tree view panel.

Step 2. Configure the Root Node in a Hierarchy

Configure the root node in the hierarchy. For example, you have an Organization Structure hierarchy. You might define the Organization business entity as the root node.

1. Click **Edit Hierarchy**.

   The Hierarchy Designer opens with an undefined root node in the canvas.
2. Select the **Root Business Entity (Undefined)** node.
3. In the properties panel, select the business entity that you want to specify as the root node of the hierarchy. For example, select Organization.
4. Click **Apply**.

Step 3. Add a Business Entity to a Hierarchy

Add a business entity to a hierarchy. For example, you have an Organization Structure hierarchy. You configured the Organization business entity as the root node. You want to add the Person business entity so that you can create a relationship from the Organization business entity to the Person business entity.

1. Click the add icon.

   An undefined node appears on the canvas.
2. In the properties panel, select a business entity.
   For example, select **Person**.
3. Click **Apply**.

Step 4. Configure a Hierarchy Relationship

Configure the relationship between two business entities in a hierarchy. For example, you have an Organization Structure hierarchy with the Organization business entity as the root node and the Person business entity as a node. You want to configure the relationship between the Organization business entity and the Person business entity. The relationship might be that Organization employs Person.

1. Hover over the business entity from which you want to create a relationship.

   The add icon and arrow icon appear.
2. Click the arrow icon, and then release the arrow over the node to which you want to create a relationship.

   For example, on the Organization business entity, click the arrow icon, and then release the arrow over the Person business entity.
3. To define an relationship between nodes, perform the following actions:
   a. Select the red arrow between two business entity nodes.

      The relationship properties appear in the properties panel.
   b. In the properties panel, specify the following relationship properties:

Property	Description
Name	Unique name for the relationship.
Description	A meaningful description for the relationship.
Data-driven Relationship based on	Lookup field that dynamically defines the relationship between records. A data-driven relationship uses data in lookup tables to define relationships between records in Data Director. For example, you create a relationship from the Organization business entity to the Person business entity. The relationship is data-driven based on the relName field. Then in Data Director, when users create a relationship from the Informatica record to the John Smith record, the relationship is defined as Employee. Or, when users create a relationship from the Informatica record to the Jane Smith record, the relationship is defined as CEO.
Label	Label for the relationship that appears in the Data Director user interface.
Label Format	Indicates whether you want to show labels on the user interface.

Property	Description
Exists Format	Title to display when you view the relationship.
No Fields Format	Title to display when all the fields in the Exists Format have NULL values.
Parent Constraint	The column that the foreign key points to.
Child Constraint	The column that the foreign key points to.

c. Click **Apply**.

4. To copy relationship properties from system-suggested similar relationship, perform the following actions:
   a. Select the red arrow between two business entity nodes.

      The relationship properties appear in the properties panel.
   b. In the properties panel, hover over the bulb icon and select the **Similar Relationships Identified** link.

      The Copy Properties window appears.
   c. In the **Similar Relationships** panel, select a relationship with properties that you want to copy.
   d. In the **Select Properties to Copy from** panel, select the relationship properties that you want to copy.
   e. Click **OK**.
   f. Click **Apply**.

Step 5. Configure the Hierarchy Settings

Configure the display and export settings for a hierarchy. For example, when users view a hierarchy in Data Director, you might want 10 child relationships to appear by default. Or, when users export a hierarchy, you might want to include the same fields in the business entity views.

1. Click **Business Entity** > **Modeling**, and then select **Hierarchies**.
2. Select the hierarchy you want to configure.
3. In the tree view panel, click the settings icon.

   The **Hierarchy Settings** dialog box appears.
4. Optionally, in the **Display** tab, enter the number of expanded child relationships in a hierarchy that you want to appear by default.
5. Click **Export**.

   The **Export** tab opens.
6. Optionally, select the business entity views that contain the fields that you want to include in exports.
7. Click **OK**.
8. Publish the changes to the MDM Hub.
   a. Click **Publish**.

      A confirmation dialog box appears that prompts you to publish or review the changes.
   b. Review the changes or publish without a review.
      - To publish without a review, click **Publish**.
      - To publish after a review, click **Review Changes** and follow the instructions that appear on the screen.

Step 6. Configure Additional Relationship Attributes (Optional)

You can configure additional relationship attributes for a relationship. For example, a relationship between an organization and person can have an additional attributes, such as salary and designation of employee. A relationship between a person and automobile can have additional attributes, such as purchase date, mileage, and price. The fields appear in the Data Director user interface when creating or viewing the relationship.

Before you begin, you must configure hierarchy relationships. Also, the base object that maintains the relationship must have the columns that correspond to the attributes you want to add.

1. Click **Business Entity** > **Modelling**, and then select **Hierarchies**.
2. Select the hierarchy you want to configure.
3. In the tree view panel, expand the relationship for which you want to configure relationship attributes.
4. In the tree view panel, select **Fields**, and then click **Create**.
5. Specify the following properties:

Property	Description
Name	Name of the field.
Label	Display name of the field in the user interface.
Read Only	Indicates whether the field is read only.
Required	Indicates whether you must specify the field when you create a relationship.
URI	URI for where your custom data types are defined, if you want to associate a custom data type with the business entity field,
Type	Name of the custom data type that you define in the URI. Used with the URI property.
Display Format	The display format for the date fields.
Filter	Regulates the data that users can enter in the field. If you enable the **Filter** property, the following properties appear: - **Operator**. Controls whether the specified values are allowed or not allowed in the field. You can choose one of the following options: 1. In. Displays the values to the user. If you add a list of comma-separated values as allowed values, Data Director users can choose a value from a lookup list. **Note:** If you also configure a field filter on the same field, the displayed values reflect the intersection of the static filter and the field filter. 2. Not In. Does not display the values to the user. - **Value**. Add values that match the data type of the field. To add multiple values, enter a comma-separated list of values. To allow users to leave the field blank, add empty quotes ("") as a value. **Note:** The Provisioning tool does not validate the values. If you add a value of the wrong data type, the value does not appear in Data Director.
Column	Business entity field.

6. Click **Apply**.
7. Repeat step 4 to 6 for each additional relationship attribute that you want to configure.

Configuring Network Relationships

Configure the network by adding business entities to the network and then configuring network relationships between business entities.

To configure the network, perform the following steps:

1. Add a business entity to the network.
2. Configure a network relationship.
3. Configure the network settings.
4. Optionally, configure additional relationship properties.

Tip: You can configure icons that represent business entities and business entity records in Data Director. When Data Director users view business entities in the **Network** view, the icon for each record appears.

Step 1. Add a Business Entity to the Network

Add a business entity to the network. For example, you want to define a network relationship between the Person business entity and the Product business entity.

1. Click **Business Entity** > **Modeling**, and then select **Network**.
2. Click **Edit Network**.

   The Network Designer opens.
3. Click the add icon.

   An undefined node appears on the canvas.
4. In the properties panel, select a business entity.
   For example, select **Person**.
5. Click **Apply**.
6. Repeat step 3 to 5 to add additional business entities.

Step 2. Configure a Network Relationship

Configure the relationship between two business entities in a network. For example, you want to define the relationship between the Person business entity and the Product business entity. The relationship might be that Person owns Product.

1. Hover over the business entity from which you want to create a relationship.

   The add icon and arrow icon appear.
2. Click the arrow icon, and then release the arrow over the node to which you want to create a relationship.

   For example, on the Person business entity, click the arrow icon, and then release the arrow over the Product business entity.
3. To define an relationship between nodes, perform the following actions:
   a. Select the red arrow between two business entity nodes.

      The relationship properties appear in the properties panel.

b. In the properties panel, specify the following relationship properties:

Property	Description
Name	Unique name for the relationship.
Description	A meaningful description for the relationship.
Data-driven Relationship based on	Lookup field that dynamically defines the relationship between records. A data-driven relationship uses data in lookup tables to define relationships between records in Data Director. For example, you create a relationship from the Organization business entity to the Person business entity. The relationship is data-driven based on the relName field. Then in Data Director, when users create a relationship from the Informatica record to the John Smith record, the relationship is defined as Employee. Or, when users create a relationship from the Informatica record to the Jane Smith record, the relationship is defined as CEO.
Label	Label for the relationship that appears in the Data Director user interface.
Label Format	Indicates whether you want to show labels on the user interface.
Exists Format	Title to display when you view the relationship.
No Fields Format	Title to display when all the fields in the Exists Format have NULL values.
Parent Constraint	The column that the foreign key points to.
Child Constraint	The column that the foreign key points to.

c. Click **Apply**.

4. To copy relationship properties from system-suggested similar relationship, perform the following actions:
   a. Select the red arrow between two business entity nodes.

      The relationship properties appear in the properties panel.
   b. In the properties panel, hover over the bulb icon and select the **Similar Relationships Identified** link.

      The Copy Properties window appears.
   c. In the **Similar Relationships** panel, select a relationship with properties that you want to copy.
   d. In the **Select Properties to Copy from** panel, select the relationship properties that you want to copy.
   e. Click **OK**.
   f. Click **Apply**.

You configured a network relationship between two business entities. You can add additional business entities and configure network relationships between the business entities.

Step 3. Configure the Network Settings

Configure the display and export settings for the network. For example, when users view a network in Data Director, you might want 10 relationships to initially appear and three relationships to appear when expanding a node. Or, when users export a network, you might want to include the same fields in the business entity views.

1. Click **Business Entity** > **Modeling**, and then select **Network**.

2. Select the network relationship you want to configure.
3. In the tree view panel, click the settings icon.

   The **Network Settings** dialog box appears.
4. In the **Display** tab, specify the following display settings:

Setting	Description
Number of Initial Relationships	The initial number of relationships that appear in a network.
Number of Expanded Relationships	The number of relationships that appear when expanding a node in a network.

5. Click **Export**.

   The **Export** tab opens.
6. Optionally, select the business entity views that contain the fields that you want to include in exports.
7. Click **OK**.
8. Publish the changes to the MDM Hub.
   a. Click **Publish**.

      A confirmation dialog box appears that prompts you to publish or review the changes.
   b. Review the changes or publish without a review.
      - To publish without a review, click **Publish**.
      - To publish after a review, click **Review Changes** and follow the instructions that appear on the screen.

Step 4. Configure the Relationship Properties (Optional)

You can configure the relationship properties, such as the relationship line color and additional relationship attributes for a relationship. The relationship line color represents the relationship in a network. The relationship attributes are fields that appear in the Data Director user interface when creating or viewing the relationship.

Before you begin, you must configure a network with network relationships between business entities.

1. Click **Business Entity** > **Modelling**, and then select **Network**.
2. Select the network relationship you want to configure.
3. In the properties panel, from the **Line Color** field, select the icon, and then select a color.

   A preview of the color appears in the icon.
4. In the tree view panel, select **Fields**, and then click **Create**.
5. Specify the following properties:

Property	Description
Name	Name of the field.
Label	Display name of the field in the user interface.
Read Only	Indicates whether the field is read only.

Property	Description
Required	Indicates whether you must specify the field when you create a relationship.
URI	URI for where your custom data types are defined, if you want to associate a custom data type with the business entity field,
Type	Name of the custom data type that you define in the URI. Used with the URI property.
Display Format	The display format for the date fields.
Filter	Regulates the data that users can enter in the field. If you enable the **Filter** property, the following properties appear: - **Operator**. Controls whether the specified values are allowed or not allowed in the field. You can choose one of the following options: 1. In. Displays the values to the user. If you add a list of comma-separated values as allowed values, Data Director users can choose a value from a lookup list. **Note:** If you also configure a field filter on the same field, the displayed values reflect the intersection of the static filter and the field filter. 2. Not In. Does not display the values to the user. - **Value**. Add values that match the data type of the field. To add multiple values, enter a comma-separated list of values. To allow users to leave the field blank, add empty quotes ("") as a value. **Note:** The Provisioning tool does not validate the values. If you add a value of the wrong data type, the value does not appear in Data Director.
Column	Business entity field.

6. Click **Apply**.
7. Repeat step 3 to 6 for each additional relationship attribute that you want to configure.

Configuring Hierarchy Tasks

Hierarchy tasks ensures changes to hierarchies move through an approval workflow. To use hierarchy tasks, you configure the task type, workflow triggers, and a task template. Then when Data Director users edit or create hierarchies, ActiveVOS creates hierarchy tasks with specific properties.

Hierarchy tasks are a type of task.

To configure hierarchy tasks, perform the following steps:

1. Configure a hierarchy task type.
2. Configure a hierarchy task template.
3. Configure hierarchy workflow triggers.

Step 1. Configuring a Hierarchy Task Type

Create the hierarchy task type and configure which users can claim or be assigned tasks. For example, you might want Senior Managers to review hierarchy tasks.

1. Click **Business Entity** > **Tasks**, and then select **Task Types**.
2. Click **Create**.
3. In the properties panel, in the **Name** field, enter **HierarchyFinalReview**.
4. Optionally, in the **Label** field, enter a label for the task type.

5. To support attachments when users edit the task details, select the **Enable File Attachments in Task Details** check box.
6. Click **Apply**.

   The **Roles** and **Task Action Configuration** folders appear in the tree view panel.
7. Select roles that can claim or be assigned the task.
   a. In the tree view panel, select **Roles**, and then click **Create**.
   b. In the properties panel, from the **Role** list, select an MDM Hub user role.
   c. Click **Apply**.

      The role appears in the tree view panel.
   d. Optionally, create additional roles.
8. Optionally, configure the hierarchies that the role can access.

   Tip: If you do not configure hierarchies, users assigned the selected roles can manage tasks for all hierarchies.
   a. In the tree view panel, select a role.
   b. Select **Hierarchy**, and then click **Create**.
   c. In the properties panel, from the **Hierarchy** list, select a hierarchy.
   d. Click **Apply**.
   e. Optionally, configure additional hierarchies.
9. Publish the changes to the MDM Hub.
   a. Click **Publish**.

      A confirmation dialog box appears that prompts you to publish or review the changes.
   b. Review the changes or publish without a review.
      - To publish without a review, click **Publish**.
      - To publish after a review, click **Review Changes** and follow the instructions that appear on the screen.

Step 2. Configuring a Hierarchy Task Template

To configure a task template for hierarchy tasks, set the default task properties, such as the task title, due date, and priority. When ActiveVOS creates hierarchy tasks, the tasks are created with the specified properties.

1. Click **Business Entity** > **Tasks**, and then select **Templates**.
2. Click **Create**.
3. In the properties panel, enter the template properties.
   a. In the **Name** field, enter **HierarchyApprovalTemplate**.
   b. In the **Title** field, enter the title format for task title.

      Title Example

      You want the task title to be `Review hierarchy changes in <record label>`.

      Enter the following value for title: `Review hierarchy changes in {taskRecord[0].label}`.

Where

- `taskRecord[0]` is the target record.
- `label` is the value of the task format in the business entity label format configuration.

c. Select a task priority.

The following table describes the possible task priorities:

Priority	Description
HIGH	The task has a high priority.
NORMAL	The task has a medium priority. Default is NORMAL.
LOW	The task has a low priority.

d. In the **Due Date** field, enter the amount of time from the day that the task is created that the task is due.

The following table describes the due date syntax:

Type of Parameter	Description	Values
sign	Determines if the due date is set to a date after the task is created or before the task is created.	If `+`, the due date is determined by adding time to the date the task is triggered. If `–`, the due date is determined by subtracting time from the date the task is triggered.
number	The amount of units to add or subtract from the current date when establishing the due date.	Any integer value.
unit	The number of days, weeks, or months that the due date is from the date the task is triggered.	If `d`, the specified number of days determines the due date. If `w`, the specified number of weeks determines the due date. If `m`, the specified number of months determines the due date.

e. Optionally, in the **Comment** field, enter the text that populates the task comment field.

f. Optional, in the **Status** field, select the status of the task.

The following table describes the possible task statuses:

Status	Description
OPEN	The task status is Open. Default is OPEN.

4. Click **Apply**.

Step 3. Configuring Hierarchy Workflow Triggers

Create a trigger that launches the hierarchy workflow and creates a hierarchy task. For example, you might want changes that Data Stewards make to a hierarchy to trigger a hierarchy task.

1. Configure a workflow trigger.
   a. Click **Business Entity** > **Tasks**, and then select **Triggers**.
   b. Click **Create**.
   c. In the properties panel, enter **HierarchyOneStepApproval**.

      The Repository Manager refers to the name when reporting trigger validation errors.
   d. Select **Start Workflow** so that the event trigger launches a workflow.
   e. Configure the following parameters:

Parameter	Input
Template	HierarchyApprovalTemplate
Task Type	HierarchyFinalReview
Task Kind	Hierarchies
Process	HierarchyOneStepApprovalTask

   f. Click **Apply**.

2. Configure events for a workflow trigger.
   a. In the tree view panel, select **Events**, and then click **Create**.
   b. In the properties panel, from the **Event** list, select **ModifyHierarchy**.
   c. Click **Apply**.
3. Configure roles for a workflow trigger.
   a. In the tree view panel, select **Roles**, and then click **Create**.
   b. In the properties panel, from the **Role** list, select the MDM Hub role.
      For example, select Data Steward if you want changes that Data Stewards make to a hierarchy to trigger a hierarchy task.
   c. Click **Apply**.
   d. Optionally, configure additional roles.
4. Optionally, configure the hierarchies that trigger hierarchy tasks.

   Tip: If you do not configure hierarchies, hierarchy tasks are triggered for all hierarchies.
   a. In the tree view panel, select a role.
   b. Select **Hierarchy**, and then click **Create**.
   c. In the properties panel, from the **Hierarchy** list, select a hierarchy.
   d. Click **Apply**.
   e. Optionally, configure additional hierarchies.

Configuring Default Hierarchy for the Dashboard

In the customer dashboard, the Hierarchies panel displays how a record is related to other records in a hierarchical format. A record can belong to multiple hierarchies. If you define a default hierarchy for the hierarchy component, the Hierarchies panel loads the default hierarchy for the record. Otherwise, the Hierarchies panel loads the list of hierarchies to which the record belongs.

1. In the Provisioning tool, click **Configuration** > **Component Editor**.

   The **Component Editor** appears.
2. In the **Component Editor** list, select **Hierarchy Widget**.

   The **Properties** panel appears.
3. Specify the following hierarchy properties:

Property	Description
Name	Unique name for the relationship.
Label	Label for the relationship that appears in the Data Director user interface.
Default Hierarchy	List of available hierarchies. Set one of the hierarchies as the default hierarchy.
Widget Height in px	Display height of the widget in pixels.

4. Click **Apply**.

   A confirmation dialog box appears confirming that the changes were applied successfully.
5. Click **Publish**

   A confirmation dialog box appears that prompts you to confirm or review the changes.
6. Review the changes or publish without a review.
   - To publish without a review, click **Publish**.
   - to publish after a review, click **Review Changes** and follow the instructions that appear on the screen.

Designing Data Director Interfaces to Manage Relationships

By default, the **Hierarchy** view and **Network** view are available to all Data Director users. Data Director users can use the **Hierarchy** view to view, create, and manage hierarchy relationships. Data Director users can use the **Network** view to view, create, and manage network relationship and to view hierarchy relationships.

You can design a **Quick View** tab for the **Hierarchy** view to provide a summary of record details for the selected record in the hierarchy. You can also design a **Quick View** tab for the **Network** view to provide a summary of record details for the selected record in the network.

Author

Kalaiarasan Ramaswamy