Informatica® Cloud Data Governance and Catalog

October 2026

Bulk Import Assets

Informatica Cloud Data Governance and Catalog Bulk Import Assets
October 2026

© Copyright Informatica LLC 2021, 2026

Publication Date: 2026-10-29

Table of Contents

Preface. 5

Chapter 1: Overview. 6

Prerequisites and guidelines. 6

Chapter 2: Template file properties. 8

AI Model. 9

AI Agent. 16

AI Agent sheet. 16

Capabilities. 19

AI System. 20

AI Use Case. 25

AI Use Case sheet. 26

Associated Questionnaires. 29

Associated Risks. 33

Associated Mitigation Plans. 35

Business Area. 38

Data Quality Rule Template. 42

Data Quality Rule Occurrence. 50

Data Set. 59

Geography. 65

Glossary Domain. 69

Glossary Subdomain. 75

Glossary Business Term. 81

Glossary Metric. 88

Legal Entity. 95

Manual Data Element. 99

Mitigation plan template. 104

Policy. 107

Process. 112

Project. 119

Questionnaire template. 123

Risk template. 131

Regulation. 133

System. 137

Stakeholders. 144

Relationships. 145

Chapter 3: Bulk import process. 146

Import assets using template files. 146

Step 1: Get template file. 147
Step 2: Populate template file. 148
Step 3: Import the file. 149
Step 4: Map asset types and asset fields. 150
Step 5: Start import of assets. 151
Re-import assets from an exported assets file. 152
Modify the exported file. 153
Viewing import job status. 160

Chapter 4: Troubleshooting bulk import of assets. 161

Index. 162

Preface

Refer to *Bulk Import Assets* to learn how to import business assets in bulk using the predefined templates. You can also enrich and curate business and technical assets in bulk using the assets file that you export from the catalog.

CHAPTER 1

Overview

Use predefined template files to create, update, or delete a large number of business assets in Data Governance and Catalog. You can also enrich and curate business and technical assets in bulk using the exported assets file from the catalog.

When you export assets from the catalog, the assets are exported in a spreadsheet. You can then modify the various attributes of the assets in the spreadsheet and import the file back into Data Governance and Catalog to update several assets in bulk.

Prerequisites and guidelines

Review the privileges that your organization administrator must grant before you use the bulk import process, and the conditions that help your import run faster.

Before you can use the bulk import or export process, your organization administrator must grant the following privileges to your user role:

Action	Required privilege
Bulk import data	The **Import** privilege granted through the Administrator
Export the results of a search	The **Export** privilege granted through the Administrator
Download a predefined Microsoft Excel template file for the assets that you want to import	Read privilege for the **Role** asset granted through Administrator
Modify an asset or its details	The **Create**, **Delete**, **Manage**, **Access**, **Read**, and **Update** privileges granted through access policies in Metadata Command Center.

For more information about the feature privileges that the organization administrator can enable, see the *Asset Management* help.

When you import assets using a downloaded template file or a search export file, your import is faster under the following conditions:

- You are creating or updating assets and not deleting assets. For assets associated with a workflow, you can simultaneously create or update a maximum of 500 assets. Data Governance and Catalog creates tickets only if you selected **Yes** for the **Submit Ticket** column in the template file or if you leave the field empty.
  For more information about the template file, see Chapter 2, “Template file properties” on page 8.

- The import file has a maximum of 500 rows, which comprises no more than 2000 updates to assets. Updates include operations to create, update, assign, or classify assets.
- You are adding or removing up to 50 asset stakeholders. For technical assets, the assets you update through bulk import must have fewer than 50 child assets.
- Your import file does not include updates to relationships between technical data elements and business data sets.
- Your import file does not contain sheets for relationships and stakeholders.

CHAPTER 2

Template file properties

Download a predefined Microsoft Excel template file to bulk import data and create, modify or delete assets in Data Governance and Catalog.

The downloaded predefined template file contains various sheets with field names for the respective values that you can enter. Column headers in red indicate mandatory fields, and column headers in black indicate optional fields. The column headers also contain notes to help you enter the values correctly.

The template file you download contains the **Instructions** sheet, which provides instructions on using the template for bulk import in Data Governance and Catalog.

The following notes apply for the values that you enter in the template files:

- The system administrator might disable some fields in Data Governance and Catalog according to the requirements of your organization. Such fields will not appear in the template files that you download.
- When you create a new asset using the bulk import template, you can create assets that are in the 'Draft' or 'Published' lifecycle status. You cannot choose the asset lifecycle status as 'In Review'.
- If assets are in 'Published' or 'Draft' state, you can bulk update or delete stakeholders for the business assets using the asset types template or the additional stakeholders sheet.

  You can download additional sheets for stakeholders and relationships while downloading the bulk import templates for business assets.
- When you specify values for custom attributes, enter values that match their data types. The following table describes the guidelines for adding values to custom attributes:

Custom Attribute	Value
Text Field	Enter a single line or multi-line rich text that has letters, integers including decimals with multiple decimals places, and special characters.
Numeric Value	Enter integers or decimals with multiple decimal places.
Dropdown List	Create a single select or a multi-select list. Use commas without spaces to separate options for a multi-select list. If an option has a comma, you must enclose the option within double quotes without spaces.
Check Box	Select `True` or `False`.

Custom Attribute	Value
Date Field	Enter dates in the format `MM/DD/YYYY`.

URL Field	You can enter a hyperlinked label, a URL, or both a label and URL.
	If you enter both label and URL, do not enter the URL as a hyperlink, and use a colon to separate the values.
	Examples: `Label :http://www.your-url.com`
	For valid URL entries, refer to the following examples:
	`- http://site.com/path/to/resource`
	`- www1.example.org/test`
	`- test123.example.net/path/to/file`
	`- http://192.168.1.1`

For more information, see "Step 1: Get template file" on page 147.

AI Model

An AI model asset represents the essential parameters of an AI model. These parameters also include the environment where the model is run, the input parameters and the output data, and the business purpose and rules for the model. AI models provide insights for many activities so that you can make decisions faster and easier or provide prediction modeling.

The following table describes the configurable columns for AI models:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.

Column	Type	Description
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Accuracy	Optional	Aggregate score of the degree to which data can accurately demonstrate the real-world entities.
AI Model Purpose	Optional	Describe the business or technical purpose of the asset. Type of Entry: Formatted text
Architecture Type	Optional	Defines the architecture and algorithms of the AI Model asset. You can select one of the following options: - `Linear Regression`. The architecture type that computes the linear relationship between the dependent variable and other independent variables. - `Logistic Regression`. The architecture model that accomplishes binary classification tasks by predicting the probability of an outcome, event, or observation. - `Lineage Discrimant Analysis`. The architecture model that is used as a classifier and a dimensionality reduction algorithm. - `Decision Trees`. The architecture type that models decisions, outcomes, and predictions using a flowchart-like tree structure, commonly used for classification and regression tasks. - `K-Nearest Neighbors`. The architecture model that uses proximity to form classifications or predictions about the grouping of an individual data point. This architecture is used for solving both classification and regression problems. - `Naive Bayes`.The architecture model that works on the principle of conditional probability used for predictive modeling and classification tasks. - `Learning Vector Quantization`. Learning Vector Quantization (LVQ) is an algorithm commonly used for statistical classification and pattern recognition. - `Support Vector Machines`. The architecture type used for linear or nonlinear classification, regression, and outlier detection tasks, where the algorithm creates a line or a hyperplane which separates the data into classes. - `Others`. If none of the other options meet your requirements, select this option.
Bias Score	Optional	Measure of bias in the model. A higher value indicates a greater difference between the predicted result and the actual result. Use the bias score to determine if the assumptions in the model are correct. Type of Entry: Numeric value. Enter a value between `0` and `100`. Ensure that the value you specify has a maximum precision of `5` digits and a scale of `2` decimal places.
Drift Score	Optional	Measure of degradation of the model. A higher value indicates greater degradation. Use the drift score to determine if the model can provide results within an acceptable range of accuracy. Type of Entry: Numeric value. Enter a value between `0` and `100`. Ensure that the value you specify has a maximum precision of `5` digits and a scale of `2` decimal places.

Column	Type	Description
Environment	Optional	Select the environment for the asset. You can select one of the following options: - `Training` - `Validation` - `Production`
F1 Score		Metric used to evaluate the quality of data classification, matching, or search/retrieval results.
Input	Optional	Input parameters for the AI model. Type of Entry: Formatted text
Libraries	Optional	Software libraries that are used to build the AI model. Type of Entry: Alphanumeric characters, including spaces and special characters.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.
MAE	Optional	Model Accuracy Evaluation (MAE) is a standardized governance attribute that allows to track how closely a deployed AI model's predictions align with actual real-world data.
Model Format	Optional	The format in which the asset is maintained. You can select one of the following options: - `Docker`. Use Docker to create an operating system bundle with deep learning environment and packaging it within a single file called a docker image. - `ONNX`. Open Neural Network Exchange (ONNX) is an open format that represents machine learning models, that facilitates interchanging models between various ML frameworks and tools. - `Others`. If none of the other formats meet your requirements, select this option.
Model Rules	Optional	Define the rules that govern the use of the AI model. Type of Entry: Formatted text
MSE	Optional	Mean Squared Error (MSE) is a specialized metric designed to flag models that suffer from large, erratic prediction mistakes. It ensures that an enterprise's AI assets are reliable, transparent, and compliant with corporate risk thresholds.
Output	Optional	Result of the AI model after it is run. Use this field to inform users of what they can expect from the model. Type of Entry: Formatted text
Precision	Optional	Performance metric column used to measure the model's accuracy when it makes a positive prediction.

Column	Type	Description
ROC-AUC	Optional	Receiver Operating Characteristic - Area Under the Curve (ROC-AUC) is the gold-standard metric for evaluating how well a model distinguishes between two different classes.
Source Model Repository	Optional	Repository in which the source of the AI model is maintained. Type of Entry: Alphanumeric characters, including spaces and special characters.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

AI Agent

An AI Agent asset represents an AI-powered autonomous entity that uses a model and a set of tools to make decisions and take actions toward a specific goal.

The template file that you use to create AI Agent assets contains the following sheets:

- "AI Agent sheet" on page 16
- "Capabilities" on page 19

You can use the AI Agent sheet in the file to configure the properties of the AI Agent assets that you want to create and use the Capabilities sheet in the file to associate one or more capabilities with the AI agents.

AI Agent sheet

In the main sheet of the bulk import template file, enter the details of the AI Agent assets that you want to create.

The following table describes the configurable columns for AI agents:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Agent Scope	Optional	Range of actions and data that the AI agent can access across all its capabilities.
Agent Type	Optional	The classification of the agent.

Column	Type	Description
Autonomy Level	Optional	The degree of independence with which the agent operates.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Orchestration Pattern	Optional	The approach the agent uses to plan and coordinate its actions. Type of entry: Formatted text.

Column	Type	Description
Stakeholder: `(Stakeholder role name)`	Optional	User or user group that you want to assign as stakeholders of the asset under the `(Stakeholder role name)` stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Capabilities

A Capability asset represents a specific function that an AI agent can perform.

The following table describes the configurable columns for capabilities:

Column	Type	Description
AI Agent	Required	Enter the reference ID or the name of the AI Agent asset to add the capability to. You can enter the reference ID and the name in the following format: `<Asset Name>|<Reference ID>` Example: AIAgent1 | AIA-1
Name	Required	Name of the capability. To distinguish this capability from others in the AI Agent asset, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Examples: Discovery1, ModifyFields
Description	Required	Enter a description of the capability. The description appears on the Capability asset page. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.

Column	Type	Description
Capability Scope	Optional	Range of actions and data that the AI agent can access through the capability.
Capability Type	Optional	The category of the AI agent's capability.
Operation	Optional	Select an operation for the Capability asset. You can select one of the following options: - Create. You want to add the capability to an AI Agent asset. - Update. You want to modify an existing capability. When you select the Update operation, ensure that you specify a value in the **AI Agent** column and in the columns that you want to modify. For example, if you want to modify the **Description** of a capability, you must enter the **AI Agent** and **Description** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - Delete. You want to delete an existing capability. When you select the Delete operation, ensure that you specify a value in the **AI Agent** column. You don't need to specify values for any other columns, including the columns that are marked as required.

AI System

The AI System asset is a machine learning-based system that uses multiple AI models to perform a range of tasks, such as generating predictions, content, recommendations, decisions, and actions. The asset records information about the technologies, AI models, and data that is used to perform these tasks.

The following table describes the columns where you must enter asset values for AI Systems:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.

Column	Type	Description
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
AI System Type	Optional	The type of AI system. You can select one of the following options: - AI Application. A software program that uses artificial intelligence techniques to perform specific tasks. - AI Agent. An autonomous AI entity that is designed to take action within a given environment to achieve specific goals. - Retrieval System. An AI system that searches and retrieves relevant data in response to queries. - Conversational. An AI system, such as a chatbot or virtual assistant, that interacts with users through natural language dialogue.
Development Stage	Optional	A phase in the AI system lifecycle where data preparation, model design, training and validation might be carried out to build and improve the AI system's performance. You can select one of the following options: - In Development. The AI System is in development. - Validation. The AI System is being validated. - Production. The AI System is already in use.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane"

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

AI Use Case

An AI Use Case asset represents an initiative that uses AI to solve a specific problem or produce measurable outcomes.

By default, the template file to create an AI Use Case asset contains only one sheet. For more information about the columns in the sheet, see "AI Use Case sheet" on page 26.

If you want to associate the AI Use Case assets that you want to create with questionnaires, risks, or mitigation plans, you can select the **Add Associations** option when you download the template file from Data Governance and Catalog.

If you select the **Add Associations** option, the template file to create an AI Use Case asset additionally contains the following sheets in addition to the main sheet:

- "Associated Questionnaires" on page 29
- "Associated Risks" on page 33

- "Associated Mitigation Plans" on page 35

AI Use Case sheet

In the main sheet of the bulk import template file, enter the details of the AI Use Case assets that you want to create.

The following table describes the columns where you must enter asset values for AI use cases:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
AI Use Case Stage	Optional	The current phase of the AI use case.
Benefits	Optional	The measurable business value the AI use case aims to deliver. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters.
Budget	Optional	The funds allocated, spent, or remaining for the AI use case. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `$100,000`, `Hundred-thousand dollars`, `100000`

Column	Type	Description
Cost	Optional	The estimated or actual expenses for the AI use case. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `$100,000,Hundred-thousand dollars,100000`
Goal	Optional	The primary objective of the AI use case. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters.
Key Deliverables	Optional	The main results that the AI use case delivers. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `Identify customers at high risk of churn and provide recommended retention actions. Generate personalized product recommendations based on customer behavior.`
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: `"Sales;EMEA Finance"` - To add asset groups using the `ADD` prefix: `"ADD:Sales;ADD:EMEA Finance"` - To remove an asset group: `"DELETE:Sales"` **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.

Column	Type	Description
Stakeholder: `(Stakeholder role name)`	Optional	User or user group that you want to assign as stakeholders of the asset under the `(Stakeholder role name)` stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Associated Questionnaires

A questionnaire represents a set of questions that gathers information for a governance assessment, such as an impact, risk, or intake review. To add questionnaires to an AI Use Case asset that you want to assess, associate a Questionnaire Template asset with the AI Use Case asset.

The following table describes the configurable columns for the questionnaires that you want to associate with the AI Use Case asset:

Column	Type	Description
AI Use Case	Required	Enter the reference ID or the name of the AI Use Case asset with which you want to associate the Questionnaire Template asset. You can enter the reference ID and the name in the following format: `<Asset Name>|<Reference ID>` Example: `AI UseCase1|AIUC-1`
Questionnaire Template	Required	Enter the reference ID or the name of the Questionnaire Template asset to use for the AI Use Case asset. When you associate a questionnaire template with an AI Use Case asset, Data Governance and Catalog creates a questionnaire instance. You can associate a questionnaire template only once with an AI Use Case asset. Subsequent changes to the questionnaire template don't apply to a questionnaire instance. To use the latest version of a questionnaire template, remove the questionnaire instance and associate the questionnaire template again. To enter both the name and reference ID, use the following format: `<Asset Name>|<Reference ID>` Example: `Question1|AIQ-1`

Column	Type	Description
Questionnaire Stakeholders	Required	User or user group that you want to assign as stakeholders of the questionnaire. If you enter the name of the user, the user becomes a stakeholder of the questionnaire. If you enter a user group here, all users that belong to the user group become stakeholders of the questionnaire. You can also remove a user or user group as a stakeholder of the questionnaire. Ensure that the users or user groups that you specify are already assigned as stakeholders on an AI Use Case asset. For example, to add a user as a Governance Owner stakeholder on a questionnaire, the user must already have the Governance Owner role on the AI Use Case asset. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. For example, 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane"
Questionnaire Completion Rate	Optional	The percentage of the questionnaire's questions that were answered. Type of Entry: Enter a numeric value between `0` to `100` without the percent sign. Example: `90`, `84`, `83` In the first example, `90` means that 90% of the questionnaire's questions are answered.
Section Name	Required	Enter the name of a section in the Questionnaire Template asset that you associate with this AI Use Case asset. A section is a group of related questions within a questionnaire.
Section Due Date	Required	The date for completing the questions within a section. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: `2023-09-28`

Column	Type	Description
Section Completion Rate	Optional	The percentage of the questionnaire's questions that were answered. Type of Entry: Enter a numeric value between `0` to `100` without the percent sign. Example: `90`, `84`, `83` In the first example, `90` means that 90% of the questionnaire's questions are answered.

Column	Type	Description
Section Stakeholders	Required	User or user group that you want to assign as stakeholders to a section of the questionnaire. If you enter the name of the user, the user becomes a stakeholder of the section. If you enter a user group here, all users that belong to the user group become stakeholders of the section. You can also remove a user or user group as a stakeholder of the section. Ensure that the users or user groups that you specify are already assigned as stakeholders on an AI Use Case asset. For example, to add a user as a Governance Owner stakeholder on a section, the user must already have the Governance Owner role on the AI Use Case asset. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. For example, 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane"
Operation	Required	Select an operation for the questionnaire. You can select one of the following options: - Create. You want to add a questionnaire to an AI Use Case asset. - Update. You want to modify an existing questionnaire. When you select the Update operation, ensure that you specify a value in the **AI Use Case** column, the **Questionnaire Template** column, and in the columns that you want to modify. For example, if you want to modify the **Section Due Date** of a questionnaire, you must enter the **AI Use Case**, **Questionnaire Template**, and **Section Due Date** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - Delete. You want to delete an existing questionnaire. When you select the Delete operation, ensure that you specify a value in the **AI Use Case** and **Questionnaire Template** columns. You don't need to specify values for any other columns, including the columns that are marked as required.

Associated Risks

A risk is a possible event that might prevent an enterprise initiative from meeting its objectives. To add risks to an AI Use Case asset, associate a Risk Template asset with the AI Use Case asset.

The following table describes the configurable columns for the risks that you want to associate with the AI Use Case asset:

Column	Type	Description
AI Use Case	Required	Enter the reference ID or the name of the AI Use Case asset with which you want to associate the Risk Template asset. You can enter the reference ID and the name in the following format: `<Asset Name>|<Reference ID>` Example: `AI UseCase1|AIUC-1`
Risk Template	Required	Enter the reference ID or the name of the Risk Template asset to use for the AI Use Case asset. When you associate a risk template with an AI Use Case asset, Data Governance and Catalog creates a risk instance. You can associate a risk template only once with an AI Use Case asset. Subsequent changes to the risk template don't apply to a risk instance. To use the latest version of a risk template, remove the risk instance and associate the risk template again. To enter both the name and reference ID, use the following format: `<Asset Name>|<Reference ID>` Example: `Risk1|RSK-1`
Due Date	Required	The date for addressing the risk. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: `2023-09-28`
Likelihood	Optional	The estimated probability that the risk will occur. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `High`, `Low`, `50% probability`
Impact	Optional	The estimated severity of consequences if the risk occurs.
Status	Optional	The current state of the risk.
Score	Required	A value representing the overall severity of the risk, typically a combination of its likelihood and impact. Type of Entry: Enter a numeric value between `0` to `100` without the percent sign. Example: `90`, `84`, `83` In the first example, `90` means that the score is 90%.
Justification	Optional	The rationale for associating the risk with the asset and its assigned score.

Column	Type	Description
Stakeholders	Required	User or user group that you want to assign as stakeholders of the risk. If you enter the name of the user, the user becomes a stakeholder of the risk. If you enter a user group here, all users that belong to the user group become stakeholders of the risk. You can also remove a user or user group as a stakeholder of the risk. Ensure that the users or user groups that you specify are already assigned as stakeholders on an AI Use Case asset. For example, to add a user as a Governance Owner stakeholder on a risk, the user must already have the Governance Owner role on the AI Use Case asset. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. For example, 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane"
Operation	Required	Select an operation for the risk. You can select one of the following options: - Create. You want to add a risk to an AI Use Case asset. - Update. You want to modify an existing risk. When you select the Update operation, ensure that you specify a value in the **AI Use Case** column, the **Risk Template** column, and in the columns that you want to modify. For example, if you want to modify the **Score** of a risk, you must enter the **AI Use Case**, **Risk Template**, and **Score** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - Delete. You want to delete an existing risk. When you select the Delete operation, ensure that you specify a value in the **AI Use Case** and **Risk Template** columns. You don't need to specify values for any other columns, including the columns that are marked as required.

Associated Mitigation Plans

A mitigation plan is a set of actions to reduce the likelihood or impact of a risk. You can track the progress of each action in the plan. To add mitigation plans to an AI Use Case asset, associate a Mitigation Plan Template asset with the AI Use Case asset.

The following table describes the configurable columns for the mitigation plans that you want to associate with the AI Use Case asset:

Column	Type	Description
AI Use Case	Required	Enter the reference ID or the name of the AI Use Case asset with which you want to associate the Mitigation Plan Template asset. You can enter the reference ID and the name in the following format: `<Asset Name>|<Reference ID>` Example: `AI UseCase1|AIUC-1`
Mitigation Plan Template	Required	Enter the reference ID or the name of the Mitigation Plan Template asset to use for the AI Use Case asset. When you associate a mitigation plan template with an AI Use Case asset, Data Governance and Catalog creates a mitigation plan instance. You can associate a mitigation plan template only once with an AI Use Case asset. Subsequent changes to the mitigation plan template don't apply to a mitigation plan instance. To use the latest version of a mitigation plan template, remove the mitigation plan instance and associate the mitigation plan template again. To enter both the name and reference ID, use the following format: `<Asset Name>|<Reference ID>` Example: `MitPlan1|MP-1`
Due Date	Required	The date for completing the mitigation plan. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: `2023-09-28`
Mitigation Status	Optional	The current state of mitigation.
Actions	Optional	The specific actions to complete as part of the mitigation strategy. Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported. Example: `Require human review for high-risk predictions, and restrict model access to authorized personnel.`

Column	Type	Description
Evidence	Optional	The supporting documentation that confirms completion of the mitigation actions. Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported. Example: `Signed-off access control policy, Audit log export dated September 1 through September 30, 2026.`

Column	Type	Description
Stakeholders	Required	User or user group that you want to assign as stakeholders of the mitigation plan. If you enter the name of the user, the user becomes a stakeholder of the mitigation plan. If you enter a user group here, all users that belong to the user group become stakeholders of the mitigation plan. You can also remove a user or user group as a stakeholder of the mitigation plan. Ensure that the users or user groups that you specify are already assigned as stakeholders on an AI Use Case asset. For example, to add a user as a Governance Owner stakeholder on a mitigation plan, the user must already have the Governance Owner role on the AI Use Case asset. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. For example, 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane"
Operation	Required	Select an operation for the mitigation plan. You can select one of the following options: - Create. You want to add a mitigation plan to an AI Use Case asset. - Update. You want to modify an existing mitigation plan. When you select the Update operation, ensure that you specify a value in the **AI Use Case** column, the **Mitigation Plan Template** column, and in the columns that you want to modify. For example, if you want to modify the **Evidence** of a mitigation plan, you must enter the **AI Use Case**, **Mitigation Plan Template**, and **Evidence** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - Delete. You want to delete an existing mitigation plan. When you select the Delete operation, ensure that you specify a value in the **AI Use Case** and **Mitigation Plan Template** columns. You don't need to specify values for any other columns, including the columns that are marked as required.

Business Area

A Business Area asset represents a department or business function with certain assigned responsibilities in the wider organization.

The following table describes the columns where you must enter asset values for business area:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Parent: Business Area	Optional	Enter the reference ID or the name of the parent Business Area asset. Ensure that you specify only one parent Business Area asset.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Data Quality Rule Template

A Data Quality Rule Template asset is the business representation of a data quality rule specification. You can use a data quality rule template to create a data quality rule. The actual data quality score of data elements are expressed as Data Quality Rule Occurrences in Data Governance and Catalog. As data quality

rules set business expectations, they are often associated with glossary assets such as Business Terms and Metrics.

The following table describes the configurable columns for data quality rule templates:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Criticality	Optional	Select the criticality of the rule template. You can select one of the following options: - `High`. The level of impact for a data quality issue is high if there is a high risk of operational, customer, regulatory and financial impact. - `Medium`. The level of impact for a data quality issue is medium if there is a moderate risk of operational, customer, regulatory and financial impact. - `Low`. The level of impact for a data quality issue is low if there is a low risk of operational, customer, regulatory and financial impact.

Column	Type	Description
Dimension	Required	Specify the data quality dimension for which the data quality rule is run. You can select one of the following options: - `Accuracy`. Data Accuracy refers to the degree to which data can accurately demonstrate the real-world entities. - `Validity`. Validity dimension signifies the data values that follow a specific format or align with business rules. - `Completeness`. Completeness dimension suggests if the data fulfills the minimum essential information criteria to deliver meaningful inferences. - `Consistency`. Consistency dimension indicates if the information stored and utilized in multiple instances is conflicting with itself. - `Uniqueness`. Data Uniqueness is a measurement to identify and remediate duplication and overlaps. - `Timeliness`. Timeliness dimension indicates the timely availability of the required and valid data. **Note:** If the data quality dimensions listed here differ from what is available in the predefined Microsoft Excel template, the administrator might have defined a different list of dimensions for your organization. For more information about how your administrator can customize the data quality dimensions, see the *Administration* help in Metadata Command Center.
DQ Rule Custom	Optional	Specify the data quality rule to map corporate data quality definitions to physical system rules.
Enable Automation	Optional	Enable or disable data quality rule automation for the rule template. You can select one of the following values: - `TRUE`. Create rule occurrences automatically for data elements that are linked to the associated Glossary assets. After the bulk import job, Data Governance and Catalog initiates a job to create a schedule to run the data quality rule for the catalog source. The rule occurrences are created as per the schedule. The frequency of the data quality rule execution depends on the frequency set in the `Frequency` column of the rule template file. - `FALSE`. No automated rule occurrences are generated. You can manually run the data quality rule for the associated data elements. **Note:** If automation was previously enabled on a rule template, then you cannot use a bulk import template to modify the value from `True` to `False`.
Frequency	Optional	Select the frequency of running the data quality rules in the rule template. You can select one of the following options: - `Daily`. The schedule for data quality rule run gets repeated every day. - `Weekly`. The schedule for data quality rule run gets repeated once every week. - `Monthly`. The schedule for data quality rule run gets repeated once every month.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.

Column	Type	Description
Measuring Method	Required	Specify the method by which the data quality rules for the rule occurrence are evaluated. You can select one of the following options: - `Business extract`. This rule is measured on the data that is exported for a particular business case. - `System function`. This rule is measured by the data quality system. - `Technical script`. This rule is measured by a script that is manually run by an analyst. - `Informatica Cloud Data Quality`. This rule is measured by Informatica Cloud Data Quality service. If you select `Informatica Cloud Data Quality` as the measuring method, ensure that you use the **Technical Rule Reference** field to specify the identifier of the data quality rule that is defined in `Informatica Cloud Data Quality`. If you don't specify the data quality rule identifier, the bulk import process fails.
Input Port Name	Optional	Specify an input port name for the primary data element on which the technical rule reference will run in the data quality system. The primary data element must have only one input port. Type of Entry: Formatted text.
Ouput Port Name	Optional	Specify an output port for the technical rule reference that will run in the data quality system. The primary data element must have only one output port. Type of Entry: Formatted text.
Technical Description	Optional	Specify the technical parameters of the rule definition. Type of Entry: Formatted text.
Technical Rule Reference	Required	Specify the internal ID of the rule specification in the data quality system that you want to run on the data elements. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in rule references. To retrieve the internal ID of a rule specification from Data Quality, go to Data Quality. On the respective rule specification page, the URL contains the internal ID. For example, `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following rule specification page URL: `https://usw5-dqcloud.dm-us.informaticacloud.com/dq-product/cloud/main/rulebuilder/23XVYy0NVSdiVYcf4ItJaQ` **Note:** If you select `Informatica Cloud Data Quality` as the measuring method, the **Technical Rule Reference** field is mandatory.
Target	Required	Specify the minimum acceptable data quality value for the asset to be considered "Good". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign. Example: `90` means on or above 90%. This is the target threshold to be achieved.
Threshold	Required	Specify the minimum acceptable data quality value for an asset to be considered as "Acceptable". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign.

Column	Type	Description
Primary Glossary	Required	Enter the name or reference ID of the Glossary asset that applies to the data quality rule template. Specify the Glossary asset that represents the data elements on which multi-port data quality rules in the rule template apply. You can add only one primary glossary to a data quality rule template. Field Type: Required Type of Entry: Reference ID or the name of the primary Glossary asset Example: `Email Address`, `BT-12`
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Secondary Glossary	Optional	Enter the name or reference ID of the Secondary Glossary asset that applies to the data quality rule template. Specify the Glossary asset that represents the data elements on which multi-port data quality rules in the rule template apply. You can add glossary names or reference IDs followed by port names and separated by colons in a single line. Don't include spaces after the glossary name or reference ID. You can add multiple entries in a single line without spaces and separated by semicolons. Field Type: Optional Type of Entry: Reference ID or the name of the glossary asset followed by the port name Example: `Marketing Email:InputPort1;BT-12:InputPort2`
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.

Column	Type	Description
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Data Quality Rule Occurrence

A data quality rule occurrence is the business representation of a data quality rule that is run on data elements. You can rate a Data Quality Rule Occurrence asset to indicate your assessment of the quality of

the asset or add your comments to the asset to provide your inputs on the data present within the asset. This enables different users to collaborate on assets and make collective decisions on using the data.

The following table describes the configurable columns for data quality rule occurrences:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Criticality	Optional	Select the criticality of the rule occurrence. You can select one of the following options: - `High`. The level of impact for a data quality issue is high if there is a high risk of operational, customer, regulatory and financial impact. - `Medium`. The level of impact for a data quality issue is medium if there is a moderate risk of operational, customer, regulatory and financial impact. - `Low`. The level of impact for a data quality issue is low if there is a low risk of operational, customer, regulatory and financial impact.

Column	Type	Description
Dimension	Required	Specify the data quality dimension for which the data quality rule is run. You can select one of the following options: - `Accuracy`. Data Accuracy refers to the degree to which data can accurately demonstrate the real-world entities. - `Validity`. Validity dimension signifies the data values that follow a specific format or align with business rules. - `Completeness`. Completeness dimension suggests if the data fulfills the minimum essential information criteria to deliver meaningful inferences. - `Consistency`. Consistency dimension indicates if the information stored and utilized in multiple instances is conflicting with itself. - `Uniqueness`. Data Uniqueness is a measurement to identify and remediate duplication and overlaps. - `Timeliness`. Timeliness dimension indicates the timely availability of the required and valid data. **Note:** If the data quality dimensions listed here differ from what is available in the predefined Microsoft Excel template, the administrator might have defined a different list of dimensions for your organization. For more information about how your administrator can customize the data quality dimensions, see the *Administration* help in Metadata Command Center.
DQ Rule Custom	Optional	Specify the data quality rule to map corporate data quality definitions to physical system rules.
Exception File Path	Optional	Specify the path where the exception records are stored. An exception is a record that fails to meet the criteria defined by the data quality rule occurrence. Type of Entry: Formatted text. Enter the complete path of the location of the file where the exception records are stored. Ensure that the path includes the name and extension of the file. Do not enter hyperlinks.
Frequency	Optional	Select the frequency of running the data quality rules in the rule template. You can select one of the following options: - `Daily`. The schedule for data quality rule run gets repeated every day. - `Weekly`. The schedule for data quality rule run gets repeated once every week. - `Monthly`. The schedule for data quality rule run gets repeated once every month.
Measuring Method	Required	Specify the method by which the data quality rules for the rule occurrence are evaluated. You can select one of the following options: - `Business extract`. This rule is measured on the data that is exported for a particular business case. - `System function`. This rule is measured by the data quality system. - `Technical script`. This rule is measured by a script that is manually run by an analyst. - `Informatica Cloud Data Quality`. This rule is measured by Informatica Cloud Data Quality service. If you select `Informatica Cloud Data Quality` as the measuring method, ensure that you use the **Technical Rule Reference** field to specify the identifier of the data quality rule that is defined in `Informatica Cloud Data Quality`.
Input Port Name	Optional	Specify an input port name for the primary data element on which the technical rule reference will run in the data quality system. The primary data element must have only one input port. Type of Entry: Formatted text.

Column	Type	Description
Ouput Port Name	Optional	Specify an output port for the technical rule reference that will run in the data quality system. The primary data element must have only one output port. Type of Entry: Formatted text.
Scanned Time	Optional	Specify the date and time on which the data quality rule was run on the assets. Type of Entry: To specify a date and time, use the `YYYY-MM-dd'T'HH:mm:ss.SSS'Z'` format. Example: `2000-10-31T01:30:00.000-05:00` If you have entered a score in the **Score** column, ensure that you specify a value in the **Scanned Time** column.
Score	Optional	Specify the data quality rule score for the asset that corresponds to the rule occurrence. Type of Entry: Numeric value. If you have entered a score in the **Score** column, ensure that you specify a value in the **Scanned Time**, **Total Rows** and **Failed Rows** columns. If you update data quality scores through bulk import, the updated data quality scores can take up to one hour to reflect in the **Total Runs Table** of the **Score** tab of a rule occurrence. **Note:** When you update the scores of a rule occurrence with a bulk upload template, Data Governance and Catalog rounds the scores to two decimal places.
Technical Description	Optional	Specify the description of the rule template as it is defined in the integrated data quality system. Type of Entry: Formatted text.
Technical Rule Reference	Optional	Specify the internal ID of the rule specification in the data quality system that you want to run on the data element. If you select `Informatica Cloud Data Quality` as the measuring method, the **Technical Rule Reference** field is mandatory. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in rule references. To retrieve the internal ID of a rule specification. open the rule specification in Data Quality. The URL in the browser address bar contains the internal ID. For example, 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following rule specification page URL: https://usw5-dqcloud.dm-us.informaticacloud.com/dq-product/cloud/main/rulebuilder/23XVYy0NVSdiVYcf4ItJaQ
Target	Required	Specify the minimum acceptable data quality value for the asset to be considered "Good". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign. Example: `90` means on or above 90%. This is the target threshold to be achieved.
Threshold	Required	Specify the minimum acceptable data quality value for an asset to be considered as "Acceptable". Type of Entry: Numeric value. Enter a value between `0` to `100` without the percent sign.
Total Rows	Optional	Specify the total number of rows for which the data quality rule is run. Type of Entry: Numeric value. If you have entered a score in the **Score** column, ensure that you specify a value in the **Total Rows** column.

Column	Type	Description
Failed Rows	Optional	Specify the number of rows where the data quality rule run failed. Type of Entry: Numeric value. If you have entered a score in the **Score** column, ensure that you specify a value in the **Failed Rows** column.
Primary Data Element	Required	Enter the path of the data element on which you want to execute the data quality rule. The data quality score is generated only for the **Primary Data Element**. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used. To enter the data element path, use the following format: `<Catalog Source Name>://<Database Name>/<Schema Name>/<Table Name>/<Column Name>` Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER ID`

Secondary Data Element	Optional	Enter the path or the Reference ID of the secondary data element.
		The secondary data element is one of the parameters of the data quality score that is executed on the Primary Data Element. You can add multiple secondary data element paths to a data quality rule occurrence. You can also add Port Names separated by colons in a single line without any spaces at the end of the secondary data element path.
		Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used.
		To add multiple secondary data elements, enter data element paths in a single line separated by semicolons and a single space.
		- To enter the data element path, use the following format:
		`CSNAME://DBNAME/SCHEMA/TABLE/COLNAME`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS`
		- To add multiple secondary data elements, use the following format:
		`CSNAME://DBNAME/SCHEMA/TABLE/COLNAME1; CSNAME://DBNAME/SCHEMA/TABLE/COLNAME2`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS; CUSTOMER_Oracle://CUST_DS/CUST_SCHEMA/CUSTOMERDETAILS/CUSTOMER STATUS`
		- To enter a secondary data element path with a port name, use the following format:
		`CSNAME1://DBNAME1/SCHEMA1/TABLE1/COLNAME1:PORTNAME1`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS:InputPort1`
		- To add secondary data elements with multiple port names, use the following format:
		`CSNAME://DBNAME/SCHEMA/TABLE/COLNAME1:PORTNAME1; CSNAME://DBNAME/SCHEMA/TABLE/COLNAME2:PORTNAME2`
		Example: `DQ_Oracle://RND12CR2/DQ_AUTOMATION/USERDETAILS/USER STATUS:InputPort1; CUSTOMER_Oracle://CUST_DS/CUST_SCHEMA/CUSTOMERDETAILS/CUSTOMER STATUS:InputPort2`

Column	Type	Description
Rule Template		Enter the name or reference ID of the Data Quality Rule Template asset to associate with the Data Quality Rule Occurrence asset. You can enter the reference ID and the name in the following format: `<Asset Name>|<Reference ID>` Example: Rule Template1 | DQRT-133 When you specify a Data Quality Rule Template, the rule occurrence inherits the following attributes from the template: - Criticality - Dimension - Frequency - Measuring Method - Target - Technical Rule Reference - Threshold You can leave these attributes blank when you import a rule occurrence that is linked to a rule template, even if the attributes are required. Data Governance and Catalog populates them from the template. If a rule occurrence already has scores, it keeps its current **Technical Rule Reference** value and doesn't inherit the value from the rule template.
Sync with Rule Template		Select whether to synchronize the rule occurrence with the rule template that you specify. You can select one of the following options: - TRUE. Subsequent changes to the rule template automatically apply to the rule occurrence. - FALSE. Subsequent changes to the rule template don't automatically apply to the rule occurrence. If a rule occurrence already has scores, it keeps its current **Technical Rule Reference** value and doesn't inherit the value from the rule template.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.

Column	Type	Description
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Lifecycle	Optional	Lifecycle status of the asset. The default status is Published. You can select one of the following options: - Draft. Typically used when you are creating a fresh asset. - In Review. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to In Review, don't use the bulk import template for that purpose. - Published. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Data Set

A Data Set asset represents identifiable groupings of data for a particular purpose. Data Sets are business-friendly representations of technical assets such as tables, files, and more. A Data Set asset focuses less on the technical aspects of how the data is delivered and more on the information provided by the data set.

The following table describes the columns where you must enter asset values for data sets:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset's lifecycle to `In Review`. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Parent: System	Required	Enter the reference ID or the name of the parent System asset. When you create or import a Data Set asset, link the data set with a parent System asset or parent AI System asset. You can specify only one parent asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Parent: AI System	Required	Enter the reference ID or the name of the parent AI System asset. When you create or import a Data Set asset, link the data set with a parent System asset or parent AI System asset. You can specify only one parent asset. The AI System asset is a machine learning-based system that uses multiple AI models to perform a range of tasks, such as generating predictions, content, recommendations, decisions, and actions. The asset records information about the technologies, AI models, and data that is used to perform these tasks.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Stakeholder Type	Optional	Indicates how stakeholders are associated with the asset and the types of stakeholder associations the asset can have. You can specify if the asset's stakeholders are directly assigned, inherited from a parent asset, or both. **Note:** The parent asset's **Propagate Stakeholders** and **Append Stakeholders** settings determine whether stakeholders propagate from the parent asset and how far the propagation continues. Check these settings on the parent assets before you import this file. Select one of the following options: - `Assigned`. The asset can have directly assigned stakeholders. - `Inherited`. The asset inherits stakeholders from a parent asset. - `Both`. The asset can have both assigned and inherited stakeholders.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Geography

A Geography asset captures areas, regions, or countries relevant to where your organization operates. You can use a geography asset to show how different business assets are relevant to different locations.

The following table describes the columns where you must enter asset values for geography:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Parent: Geography	Optional	Enter the reference ID or the name of the parent **Geography** asset. Ensure that you specify only one parent **Geography** asset.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Domain

A glossary asset of the Domain type refers to a collection of business concepts and activities that can be grouped together for a specific function or requirement. A domain is a subject matter area under which many

terms can be organized. You can use a glossary domain to assign semantic and business context to an actual business concept.

The following table describes the columns of the bulk import template for glossary domains:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published` You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Subdomain

A glossary asset of the Subdomain type refers to a concept or activity that constitutes a specific business function or requirement. A domain is divided into subdomains to help organize business terms and metrics. You can use a glossary subdomain to assign semantic and business context to an actual business concept.

The following table describes the columns where you must enter asset values for glossary subdomains:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Business Logic	Optional	Description of any business logic that is relevant to the asset. Type of Entry: Formatted text

Column	Type	Description
Examples	Optional	Enter an example that is representative of the asset. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in examples. To enter multiple values, use a comma to separate each value. Example: For the subdomain 'Product Identifer,' examples can be 'Model Number' or 'Brand Name'
Lifecycle	Optional	Lifecycle status of the asset. The default status is Published. You can select one of the following options: - Draft. Typically used when you are creating a fresh asset. - In Review. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to In Review. - Published. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - Obsolete. Typically used when a business asset is no longer in use. Once an asset is in the Obsolete status, the only other status change allowed is Published.
Security Level	Optional	Security Level of the asset with respect to the sensitivity of the information. This is manually specified for the asset and is suitable only as a governance record. It is not related to data classification or any other system classification. You can select one of the following options: - Public. The assets can be freely used, reused, and distributed without repercussions. - Internal. The assets are strictly accessible to internal employees who are granted access. - Confidential. Confidential assets are mostly protected by laws and access to these assets would require confidential data. - Restricted. Restricted assets, if compromised or accessed without authorization, can cause irreparable damage to the organization.
Operation	Required	Select an operation for the asset. You can select one of the following options: - Create. You want to create the asset. - Update. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - Delete. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Subdomain	Optional	Enter the reference ID or the name of the parent Glossary Subdomain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Subdomain asset.

Column	Type	Description
Parent: Domain	Optional	Enter the reference ID or the name of the parent Glossary Domain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Domain asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Business Term

A glossary asset of the Business Term type can be used to capture a business definition that is used in your organization. Most business terms tend to be realized as data elements and can be used to indicate that different data elements represent the same concept, whatever the name they have in each table.

The following table describes the columns where you must enter asset values for glossary business terms:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Business Logic	Optional	Description of any business logic that is relevant to the asset. Type of Entry: Formatted text

Column	Type	Description
Critical Data Element	Optional	Specify whether the asset should be marked as a Critical Data Element. A Critical Data Element is an important or elite asset that you can use in your governance environment to calculate key metrics or generate key reports. For example, in an HR data warehouse, 'Employee Number' can be a Critical Data Element, because it uniquely identifies the employees in the organization. You can select one of the following values: - `True`. The asset is marked as a Critical Data Element. - `False`. The asset isn't marked as a Critical Data Element.
Examples	Optional	Enter an example that is representative of the asset. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in examples. To enter multiple values, use a comma to separate each value. Example: For the business term 'Credit Card Type,' examples can be `VISA`, `MASTERCARD`.
Format Type	Optional	Select the format in which the business term is expressed. You can select one of the following options: - `Text` - `Number` - `Decimal` - `Percentage` - `Fraction` - `Date` - `Time` - `Date time`
Format Description	Optional	Description of the asset format. Example: For the business term 'Date of Birth,' the **Format Type** will be `Date`, and the **Format Description** will be the date format `YYYY-MM-DD`.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Security Level	Optional	Security Level of the asset with respect to the sensitivity of the information. This is manually specified for the asset and is suitable only as a governance record. It is not related to data classification or any other system classification. You can select one of the following options: - `Public`. The assets can be freely used, reused, and distributed without repercussions. - `Internal`. The assets are strictly accessible to internal employees who are granted access. - `Confidential`. Confidential assets are mostly protected by laws and access to these assets would require confidential data. - `Restricted`. Restricted assets, if compromised or accessed without authorization, can cause irreparable damage to the organization.

Column	Type	Description
Classification	Optional	Name for the Data Element or Data Entity Classification that you want to associate with the asset. Consider entering unique data element or data entity classification so that you can distinguish between different classifications. Type of Entry: Alphanumeric characters, including spaces and special characters such as –, _, /,\, &, (,), ., #, +, * and %. To specify multiple values, enter the values in the same row and use a semicolon to separate each value. Example: `First Name`, `BA Name: 29`
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Subdomain	Optional	Enter the reference ID or the name of the parent Glossary Subdomain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Subdomain asset.
Parent: Metric	Optional	Enter the reference ID or the name of the parent **Metric** asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent **Metric** asset.
Parent: Business Term	Optional	Enter the reference ID or the name of the parent **Business Term** asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent **Business Term** asset.
Parent: Domain	Optional	Enter the reference ID or the name of the parent Glossary Domain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Domain asset.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Reference Data	Optional	Associate reference data from Reference 360 with business terms by entering the path of one or more code list attributes from Reference 360. Example: `Reference360Catalog Source/Country/Enterprise Country/Code` To enter multiple code list attributes, use a semicolon to separate each name. Do not use a space to separate multiple attributes. Ensure that all the attributes that you specify belong to the same code list. Example: `Reference Catalog Source/Country/Enterprise Country/Code;Reference Catalog Source/Country/Enterprise Country/Name;Reference Catalog Source/Country/Enterprise Country/Description`
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Glossary Metric

A glossary asset of the Metric type refers to the definition of the measurement of a business result. This measurement is typically a numerical indicator of business success. You can use a metric asset to assign semantic and business context to an actual business measurement.

The following table describes the columns where you must enter asset values for glossary metrics:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Alias Names	Optional	Alternate names used to refer to the asset. Make sure this name is not the same value as the primary name of asset. You can enter a meaningful business reference name that would help users to identify the asset. Type of Entry: Alphanumeric characters, separated by comma, including spaces and special characters. Example: If the primary name of asset is `Wind pipe`, you can enter `Air pipe, flute` as the alias names.
Business Logic	Optional	Description of any business logic that is relevant to the asset. Type of Entry: Formatted text

Column	Type	Description
Critical Data Element	Optional	Specify whether the asset should be marked as a Critical Data Element. A Critical Data Element is an important or elite asset that you can use in your governance environment to calculate key metrics or generate key reports. For example, in an HR data warehouse, 'Employee Number' can be a Critical Data Element, because it uniquely identifies the employees in the organization. You can select one of the following values: - `True`. The asset is marked as a Critical Data Element. - `False`. The asset isn't marked as a Critical Data Element.
Examples	Optional	Enter an example that is representative of the asset. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in examples. To enter multiple values, use a comma to separate each value. Example: For the Metric '`Year Over Year Growth`,' example can be `40%`
Format Type	Optional	Select the format in which the business term is expressed. You can select one of the following options: - `Text` - `Number` - `Decimal` - `Percentage` - `Fraction` - `Date` - `Time` - `Date time`
Format Description	Optional	Description of the asset format. Example: For the business term 'Employee's Hire Date,' the **Format Type** will be `Date`, and the **Format Description** will be the date format `YYYY-MM-DD`.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Security Level	Optional	Security Level of the asset with respect to the sensitivity of the information. This is manually specified for the asset and is suitable only as a governance record. It is not related to data classification or any other system classification. You can select one of the following options: - `Public`. The assets can be freely used, reused, and distributed without repercussions. - `Internal`. The assets are strictly accessible to internal employees who are granted access. - `Confidential`. Confidential assets are mostly protected by laws and access to these assets would require confidential data. - `Restricted`. Restricted assets, if compromised or accessed without authorization, can cause irreparable damage to the organization.

Column	Type	Description
Classification	Optional	Name for the Data Element or Data Entity Classification that you want to associate with the asset. Consider entering unique data element or data entity classification so that you can distinguish between different classifications. Type of Entry: Alphanumeric characters, including spaces and special characters such as –, _, /,\, &, (,), ., #, +, * and %. To specify multiple values, enter the values in the same row and use a semicolon to separate each value. Example: `First Name`,`BA Name: 29`
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Domain	Optional	Enter the reference ID or the name of the parent Glossary Domain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Domain asset.
Parent: Subdomain	Optional	Enter the reference ID or the name of the parent Glossary Subdomain asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent Glossary Subdomain asset.
Parent: Metric	Optional	Enter the reference ID or the name of the parent **Metric** asset. To form a hierarchy use one of the following columns: - **Parent: Metric** - **Parent: Subdomain** - **Parent: Domain** - **Parent: Business Term** Ensure that you specify only one parent **Metric** asset.
Parent: Business Term	Optional	Enter the reference ID or the name of the parent Glossary Business Term asset. To form a hierarchy use one of the following columns: - **Parent: Subdomain** - **Parent: Metric** - **Parent: Business Term** - **Parent: Domain** Ensure that you specify only one parent Glossary Business Term asset.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Reference Data	Optional	Associate reference data from Reference 360 with metrics by entering the path of one or more code list attributes from Reference 360. Example: `Reference360Catalog Source/Country/Enterprise Country/Code` To enter multiple code list attributes, use a semicolon to separate each name. Do not use a space to separate multiple attributes. Ensure that all the attributes that you specify belong to the same code list. Example: `Reference Catalog Source/Country/Enterprise Country/Code;Reference Catalog Source/Country/Enterprise Country/Name;Reference Catalog Source/Country/Enterprise Country/Description`
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Legal Entity

A Legal Entity asset captures corporate entities, whether these are part of the customer's own group of companies or trusted partners and vendors, that can be used to make relationships to other business assets to provide context.

The following table describes the columns where you must enter asset values for legal entities:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Long Name	Optional	Long form name for the Legal Enity. Enter a value to make the Legal Entity easily identifiable by users. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in names. Example: If you have a legal entity with the name 'SO_ENT', you can enter '`State-Owned Enterprise`' in the **Long Name** field. This helps both technical teams and business teams to identify the legal entity.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Legal Entity	Optional	Enter the reference ID or the name of the parent **Legal Entity** asset. Ensure that you specify only one parent **Legal Entity** asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Manual Data Element

A manual data element is the business representation of data that might not be available in the catalog but is essential to capture for governance purposes in your organization. As a business user, you can manually create a data element within a data set. A data set can either have technical data elements or manual data elements or a combination of both. Although a manual data element is a type of business asset, it exists in a

business data set and not as a standalone business asset. You can associate a manual data element with one business data set only.

The following table describes the columns where you must enter asset values for manual data elements:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
AI System	Optional	Enter the reference ID or the name of the AI System asset that is the parent of the asset that you specified in the **Parent: Data Set** field. If multiple data sets have the same name as the asset specified in the **Parent: Data Set** field, consider specifying a value in the **System** field or the **AI System** field to help distinguish the parent Data Set asset from the other assets. Ensure that you specify only one parent asset. The AI System asset is a machine learning-based system that uses multiple AI models to perform a range of tasks, such as generating predictions, content, recommendations, decisions, and actions. The asset records information about the technologies, AI models, and data that is used to perform these tasks.

Column	Type	Description
Data Element Classification	Optional	Name for the Data Element Classification that you want to associate with the manual data element. To distinguish between different classifications, consider entering unique classification names. Type of Entry: Alphanumeric characters, including spaces and special characters such as –, _, /,\, &, (,), ., #, +, * and %. To specify multiple values, enter the values in the same row and use a semicolon to separate each value. To add a data element classification, prefix the data element classification with the term `ADD:`. To remove a data element classification, prefix the data element classification with the term `DELETE:`. Examples: To add data element classifications: `ADD:Classification1,Classification2` To remove data element classifications: `DELETE:Classification1,Classification2`
Glossaries	Optional	Enter the name or the Reference IDs of the glossaries that you want to associate with the manual data element. To enter multiple values, use a semicolon to separate each value. To add a glossary, prefix the glossary with the term `ADD:`. To remove a glossary, prefix the glossary with the term `DELETE:`. Examples: To add glossaries: `ADD:Glossary1,Glossary2` To remove glossaries: `DELETE:Glossary1,Glossary2`
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you want to create a fresh asset. - `In Review`. Typically used to indicate an asset that is currently under review by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset's lifecycle to `In Review`. - `Published`. Typically used to indicate an asset that is reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used to indicate an asset that is no longer in use. For an asset with the lifecycle status as `Obsolete`, you can only change the status to `Published`.
System	Optional	Enter the reference ID or the name of the System asset that is the parent of the asset that you specified in the **Parent: Data Set** field. If multiple data sets have the same name as the asset specified in the **Parent: Data Set** field, consider specifying a value in the **System** field or the **AI System** field to help distinguish the parent Data Set asset from the other assets. Ensure that you specify only one parent asset.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Parent: Data Set	Required	Enter the reference ID or the name of the parent Data Set asset. Ensure that you specify only one parent Data Set asset.
Reference Data	Optional	Associate reference data from Reference 360 with the manual data element by entering the path of the code list attribute from Reference 360. You can associate only one code list attribute with a manual data element. Example: `Reference360Catalog Source/Country/Enterprise Country/Code`

Column	Type	Description
Referenced Glossary	Optional	Enter the name or reference ID of a Glossary asset that is associated with reference data. The reference data that is associated with the Glossary asset gets associated with the manual data element. You can specify only one Glossary asset. Example: `TERM-102`
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Mitigation plan template

A mitigation plan template helps you document the plan of action for addressing a risk and tracks its progress. You associate the plan with a risk that is identified for an asset.

The following table describes the columns where you must enter asset values for mitigation plan template:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: <Prefix>-<Number> **Example:**MIT-376, MIP-133 If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Example:** MP-53, PLAN-4234
Name	Required	Name of the asset. Consider entering a unique name so that you can distinguish this asset from other assets. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Example:** Mitigation Plan 1, MPlan 1
Strategy	Required	The approach taken to mitigate the associated risk.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: <img src=""""> <img src=""""> You can add only an image of Base64 format to the description. Other image formats are not supported.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.

Column	Type	Description
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`"

Column	Type	Description
		The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Policy

A Policy asset represents an internal collection of rules and guidance on how to conduct business and manage data. They might be inspired by company goals, external regulations, or commercial agreements.

The following table describes the columns where you must enter asset values for policies:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Comments	Optional	Additional comments that apply to the asset. You can describe the policy in detail, add relevant comments, and provide links to policy related documents. Type of Entry: Formatted Text

Column	Type	Description
Effective Date	Optional	Date on which the policy goes into effect. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: 2023-09-27
End Date	Optional	Date on which the policy lapses. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: 2023-09-28 Ensure that you enter a value that occurs after the date that you specified in the **Effective Date** field.
Policy Type	Required	The area that the policy governs. You can select one of the following policy types: - `Conduct Standards`. Guides conduct in various situations. - `Data Standards`. Applies to data management. - `Technical Standards`. Applies to technical management. - `Business Rule`. Defines rules for business functions. - `AI Guardrail`. Applies safety rules and filters that block harmful, unsafe, or incorrect AI output.
Parent: Policy	Optional	Enter the reference ID or the name of the parent **Policy** asset. Ensure that you specify only one parent **Policy** asset.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.
Classifications	Optional	Name for the Data Element or Data Entity Classification that you want to associate with the asset. Consider entering unique data element or data entity classification so that you can distinguish between different classifications. Type of entry: Alphanumeric characters, including spaces, and special characters such as –, `_`, `/`, `&`, `(`, `)`, `.`, `#`, `+`, `*` and `%` . To enter multiple values, enter the values in the same row and use a comma to separate each value. Example: `First Name, BA Name: 29`

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - Yes. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - No. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Process

Use a Process asset to document important business activities so that the activity can be contextualized through relationships. These activities allow business users to record the key reasons on why they consume

data. Processes are typically structured as a parent process using the recognized name of the activity, with a series of child process steps that explain the key stages involved in executing that activity. Each individual process object can have its own set of relationships to explain key metadata associations.

The following table describes the columns where you must enter asset values for processes:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Duration	Optional	Duration of the process. You can specify the process duration in weeks, days, or hours. Type of Entry: Specify a positive integer and enter `Hour`, `Hours`, `Week`, `Weeks`, `Day` or `Days`. The duration value isn't case-sensitive. If you enter only a positive integer, the system considers the process duration in days. Examples: - `4` - The system considers the process duration as 4 days. - `5 week` - The system considers the process duration as 5 weeks. - `7 HOUR` - The system considers the process duration as 7 hours.

Column	Type	Description
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Process Type	Optional	The type of process. You can select one of the following values: - `Process`. An entire process. - `Step`. A specific step in the process. - `Control`. An intermediate option within the process that determines the direction of the subsequent steps.
Step Type	Optional	Specify the type of step in the process. You can select one of the following values: - `Common`. A step that is linked to more than one tasks in a process. - `Starting`. The starting step indicates the onset of a process and a process can have only one starting step. - `Ending`. The ending step specifies that the process is completed or failed.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Process	Optional	Enter the reference ID or the name of the parent **Process** asset. Ensure that you specify only one parent **Process** asset.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Project

A Project asset represents a collection of activities that are planned and organized to achieve a particular set of objectives.

The following table describes the columns where you must enter asset values for projects:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Start Date	Optional	Date on which the project work commences. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: '`2023-09-27`'
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
End Date	Optional	Date on which the project work is completed. Type of Entry: To specify a date, use the `YYYY-MM-DD` format. Enter a value between `1971-01-01` and `2999-12-31`. Example: '`2023-09-28`' Ensure that you enter a value that occurs after the date that you specified in the **Start Date** field.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Parent: Project	Optional	Enter the reference ID or the name of the parent **Project** asset. Ensure that you specify only one parent **Project** asset.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Questionnaire template

A questionnaire template asset gathers structured input from stakeholders as part of a governance assessment, such as an impact, risk, or intake review. You associate the template with an asset that you want to assess, and stakeholders of that asset respond to the questionnaire.

The bulk import file for a questionnaire template uses a separate sheet for each part of the template. Import the questionnaire template sheet first, then the sections sheet, and then the questions sheet.

The following table describes the columns where you must enter asset values for questionnaire template:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: <Prefix>-<Number> **Example:**QUS-376, QUE-133 If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Example:** QS-53, QTMP-4234
Name	Required	Name of the asset. Consider entering a unique name so that you can distinguish this asset from other assets. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Example:** Questionnaire 1, Risk Assessment 1
Description	Optional	Definition of the asset. The description appears in the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder		User or user group that you want to assign as stakeholders of the questionnaire template. You can also remove a user or user group as a stakeholder of the questionnaire template. The stakeholders that you assign to the questionnaire template can add, update, or remove its sections or questions. **Type of Entry:** Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. For example, 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and remove others. **Examples** - To add users: “23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane” - To add users using the ADD: prefix: “ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane” - To remove users using the DELETE: prefix: “DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane” - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane"

Column	Type	Description
Types		The category of assessment for which you want to use the questionnaire. You can select one of the following types of questionnaires: - **Impact assessment:** Reviews the effect of an asset on individuals, operations, or compliance. - **Intake review:** An initial review you complete to decide whether further assessment is needed. - **Risk assessment:** Reviews the likelihood and severity of an asset's risks.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.

Sections

A section is a group of related questions. The following table describes how to add, update or delete sections in a questionnaire template:

Column	Type	Description
Questionnaire Template	Required	Enter the reference ID or the name of the Questionnaire Template asset to which you want to add the section. To enter both the name and reference ID, use the following format: Asset Name | Reference ID **Example:** Questionnaire 1 | QUT-1
Section Name	Required	Enter a name for the section. A section is a group of related questions within a questionnaire. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters.
Operation		Select an operation for the section. You can select one of the following options: - Create. You want to add a question to a section. - Update. You want to modify an existing section. - Delete. You want to delete an existing section.

Questions Sheet

For each question, enter the question text, the response format, and the predefined responses. The following table describes how to add, update, or delete the questions in a section

Column	Type	Description
Section Reference	Required	The section this question belongs to, identified together with its questionnaire. Format: <Section Name>:<Questionnaire Name or Reference ID> Example: PII:Data Privacy
Question	Required	The text of the question as it appears to respondents. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Examples:** What are the affected business verticals? Will this initiative take more than 5 years? What is the expected ROI%?
Response Type	Required	The format of the response.
Responses	Required	The list of predefined responses available for a single-select or multiple-select questions. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Example:** Data Privacy, Bias and Fairness, Model Security, Explainability, Regulatory Compliance

Column	Type	Description
Other Option		Adds an **Other** choice to the question, allowing the respondent to type their answer if none of the predefined choices fit. Select True or False under this field to add an **Other** choice to the question. Available only for single-select questions.
Operation		Select an operation for the question. You can select one of the following options: - Create. You want to add a question to a section. - Update. You want to modify an existing question. When you select the Update operation, ensure that you specify a value in the **Section Name** column, **Question** column, and in the columns that you want to modify. For example, if you want to modify the **Responses** to a question, you must enter the **Section Name**, **Question**, and **Responses** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - Delete. You want to delete an existing question. When you select the Delete operation, ensure that you specify a value in the **Section Name** and **Question** columns. You don't need to specify values for any other columns, including the columns that are marked as required.

Export Sheet - Questions

The following table describes how to update responses that you previously exported:

Column	Type	Description
Response	Required	The response to the question. To update the response, edit this value and re-import the file. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Examples:** The model was evaluated using a set of 10,000 samples across three demographic groups.

Risk template

A risk template asset documents a potential risk in an enterprise initiative. You can associate the risk with another asset, and associate one or more mitigation plans with the risk to address it.

The following table describes the columns where you must enter asset values for risk template:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: <Prefix>-<Number> **Example:**RSK-376, RIS-133 If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Example:** RK-53, RISK-4234
Name	Required	Name of the asset. Consider entering a unique name so that you can distinguish this asset from other assets. **Type of Entry:** Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. **Example:** Risk1, Major Risk 1
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Category	Required	The category of risk.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** To avoid setting an asset's lifecycle to `In Review`, don't use the bulk import template for that purpose. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create an asset. - `Update`. You want to modify an existing asset. When you select the `Update` operation, ensure that you specify a value in the **Reference ID** column and in the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for any other columns, including the columns that are marked as required. - `Delete`. You want to delete an existing asset. When you select the `Delete` operation, ensure that you specify a value in the **Reference ID** column. You don't need to specify values for any other columns, including the columns that are marked as required. Before you delete an asset, remove or delete all associated relationships and parent-child relationships of the asset.

Regulation

Use a Regulation asset type to document the important clauses of a major legislation. A regulation is a key driver of internal policies that direct how an organization conducts its business.

The following table describes the columns where you must enter asset values for regulations:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.

Column	Type	Description
Long Name	Optional	Long form name for the Regulation. Enter a value to make the regulation easily identifiable by users. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in names. Example: If you have a regulation with the name 'ENV_PROTECT', you can enter '`Environmental Protection Regulation`' in the **Long Name** field. This helps both technical teams and business teams to identify the asset.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: Regulation	Optional	Enter the reference ID or the name of the parent **Regulation** asset. Ensure that you specify only one parent **Regulation** asset.
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

System

A System asset represents a recognizable location or application that typically contains multiple data sets. In a System asset, the system name is often more business-friendly than the technical names used for technical

assets. The system name allows the business users that create and manage the data to easily identify the asset.

The following table describes the columns where you must enter asset values for systems:

Column	Type	Description
Reference ID	Optional	Reference ID is the unique reference identifier for the asset. If you don't specify a reference ID, the system automatically assigns a unique value to the object. The identifier that you enter here appears in the **Reference ID** field on the user interface. The system uses the following format to generate a reference ID: `<Prefix>-<Number>` Example: `AI-1`, `DS-10` If you specify a reference ID, ensure that the value that you enter doesn't use the format that is used by the system to automatically generate reference IDs. Type of Entry: Alphanumeric characters, including spaces and special characters. There are no restrictions on special characters. Example: `AST ID-18`, `SYS REF:98`
Name	Required	Name of the asset. To distinguish this asset from other assets, enter a unique name. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: `Model 1`, `Model Name: 29`, `System Name` **Note:** If you use only special characters in the **Name** field, the system will allow the import to succeed, but the **Name** field will remain empty.
Description	Optional	Definition of the asset. The description appears on the asset page. Enter a detailed description of the asset to help users understand how the asset is used in a governance context. Type of Entry: Formatted text. To add an image to the description, use the following syntax: `<p><img src=""""> <img src=""""></p>` You can add only an image of Base64 format to the description. Other image formats are not supported.
Asset ID	Optional	Asset ID is a unique identifier that represents the system uniquely in its source. This value is useful for scenarios where you already have a specific way to depict the system at its source. The Asset ID value represents the system uniquely in its source while the Reference ID value represents the system uniquely in Data Governance and Catalog. For example, a system is uniquely identified at the source level as '`SYSTEM_10`', which is its Asset ID value. Meanwhile, as per the governance operating model, the same system can be assigned a Reference ID value '`SYS-1`' through automated generation or '`SYS MODEL 1`' manually. Type of Entry: Alphanumeric characters, including spaces and special characters. Example: '`SYSTEM_10`'

Column	Type	Description
Lifecycle	Optional	Lifecycle status of the asset. The default status is `Published`. You can select one of the following options: - `Draft`. Typically used when you are creating a fresh asset. - `In Review`. Typically used when an asset is being reviewed by stakeholders. **Note:** Informatica recommends that you don't use a bulk import template to set an asset lifecycle to `In Review`. - `Published`. Typically used when an asset has been reviewed and accepted by stakeholders and is ready for use by the wider organization. - `Obsolete`. Typically used when a business asset is no longer in use. Once an asset is in the `Obsolete` status, the only other status change allowed is `Published`.
Long Name	Optional	Long form name for the system. Enter a value to make the system easily identifiable by users. Type of Entry: Alphanumeric characters, including spaces and special characters. There is no limitation on special characters to be used in names. Example: If you have a system with the name 'Sys_Gdw', you can enter '`Global Data Warehouse System`' in the **Long Name** field. This helps both technical teams and business teams to identify the system.
System Purpose	Optional	Indicates the purpose of the system that best describes its function. Choose from a list of predefined values.
System Type	Optional	Select the type that represents the system asset. You can select one of the following options: - `Software Application`. The system type that performs specific functions for the end users by directly interacting with it. - `File System`. A system type that manages, stores, and organizes files and directories on a storage device. It facilitates convenient identification and retrieval of data. - `Email`. Email is the method of exchanging computer-stored messages from one system to another. - `Paper` . A traditional system type that stores and organizes information using paper documents. - `User Specified`. A tailor-made system type that is developed for specific user or organization.
Operation	Required	Select an operation for the asset. You can select one of the following options: - `Create`. You want to create the asset. - `Update`. You want to modify an existing asset. In this case, the **Reference ID** column is mandatory, along with the columns that you want to modify. For example, if you want to modify the **Lifecycle** of an asset, you must enter the **Reference ID** and **Lifecycle** values, but you don't need to specify values for the other fields, including the fields that are marked as mandatory. - `Delete`. You want to delete an existing asset. In this case, the **Reference ID** is the only column that is mandatory. You don't need to specify values for any field, including mandatory fields. Before you delete an asset, ensure that you have removed or deleted all associated relationships and parent-child relationships of the asset.
Parent: System	Optional	Enter the reference ID or the name of the parent **System** asset. Ensure that you specify only one parent **System** asset.

Column	Type	Description
Asset Groups	Optional	Asset groups that you want to assign to the asset. Select one or more asset groups that you have access to. For an asset hierarchy, you can assign to a child asset either its parent's asset group or a child asset group of the parent asset group. You can't assign to a parent asset an asset group that is assigned to its child assets. Type of Entry: Names of asset groups, separated by semicolons and with no spaces. To add an asset group, you can optionally prefix the asset group name with `ADD:`. To remove an asset group, you must prefix the asset group name with `DELETE:`. Use a colon after the prefix, followed by the asset group name. The following examples shows how you can add and remove asset groups: - To add asset groups: "`Sales;EMEA Finance`" - To add asset groups using the `ADD` prefix: "`ADD:Sales;ADD:EMEA Finance`" - To remove an asset group: "`DELETE:Sales`" **Note:** This column appears in export files if an administrator publishes asset groups in Metadata Command Center, regardless of whether individual assets have asset groups assigned. For more information about modifying asset groups, see "Manage asset groups in bulk" on page 157.
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.

Column	Type	Description
Stakeholder: Governance Administrator	Optional	User or user group that you want to assign as stakeholders of the asset under the Governance Administrator role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: `23XVYy0NVSdiVYcf4ItJaQ` is the internal ID for the following user page URL: `https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ` To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: “`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`” - To add users using the `ADD:` prefix: “`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`” - To remove users using the `DELETE:` prefix: “`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`” - To add some users and remove others simultaneously: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane`" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: (Stakeholder role name)	Optional	User or user group that you want to assign as stakeholders of the asset under the (Stakeholder role name) stakeholder role. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, first name followed by the last name with a space in between, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. On the respective user or user group page, the URL contains the internal ID. Example: 23XVYy0NVSdiVYcf4ItJaQ is the internal ID for the following user page URL: https://usw5.dm-us.informaticacloud.com/cloudUI/products/administer/main/usersAsset/23XVYy0NVSdiVYcf4ItJaQ To enter multiple values, use a semicolon to separate each value. Do not use a space to separate different values. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term ADD: to the user or user group. To remove a stakeholder, you must prefix the term DELETE: to the user or user group. **Note:** You can use the ADD: and DELETE: prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane" - To add users using the ADD: prefix: "ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane" - To remove users using the DELETE: prefix: "DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane" - To add some users and remove others simultaneously: "ADD:23XVYy0NVSdiVYcf4ItJaQ;DELETE:steve@yourorg.com; ADD:John Admin;DELETE:Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.

Column	Type	Description
Stakeholder: Data Steward	Optional	User or user group that you want to assign as stakeholders of the asset under the Data Steward role who maintains high data quality in its underlying pipelines, and remains compliant with corporate risk standards. If you enter the name of the user, the user becomes a stakeholder of the asset. If you enter a user group here, all users that belong to the user group become stakeholders of the asset. You can also remove a user or user group as a stakeholder of the asset. If you want to add a user and a user group as the stakeholders of an asset, you must enter the user names and the user group names in separate rows. To add a stakeholder, you can prefix the term `ADD:` to the user or user group. To remove a stakeholder, you must prefix the term `DELETE:` to the user or user group. **Note:** You can use the `ADD:` and `DELETE:` prefixes in a single upload file to simultaneously add and some remove others. The following examples show how you can add and remove stakeholders: - To add users: "`23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;Rhodes,Jane`" - To add users using the `ADD:` prefix: "`ADD:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;ADD:Rhodes,Jane`" - To remove users using the `DELETE:` prefix: "`DELETE:23XVYy0NVSdiVYcf4ItJaQ;steve@yourorg.com;John Admin;DELETE:Rhodes,Jane`" - To add some users and remove others simultaneously: "`ADD:`23XVYy0NVSdiVYcf4ItJaQ;`DELETE:`steve@yourorg.com; `ADD:`John Admin;`DELETE:`Rhodes,Jane" The template displays all the stakeholder roles that are relevant for the asset. For more information about stakeholder roles, see the *Predefined user roles* topic in the *Asset Management* help.
Submit Ticket	Required	Specify whether you want your action to go through a workflow approval. A ticket will be created to track approvals from the required stakeholders, if the administrator has configured a workflow for the asset in Metadata Command Center. You can select one of the following options: - `Yes`. Creates a workflow ticket for the asset and assigns tasks to the appropriate stakeholders. - `No`. No tickets are created. The asset will remain in **Draft** status. A ticket will be created if the column is left blank.

Stakeholders

Stakeholders are authorized users who are responsible for the asset, and can approve or reject change requests for the asset.

The following table describes the columns where you must enter values to assign stakeholders to assets:

Column	Type	Description
Asset	Required	Name or Reference ID of the asset. If you have one or more assets with the same name, consider entering their respective **Reference ID** values to help the system to distinguish between them.
Asset Type	Required	Type of the asset for which you want to specify the stakeholders. Enter the exact name of the asset type. Examples: `Business Term`, `Domain`
User or User Group	Required	User or user group that you want to assign as stakeholders of the asset. Enter one stakeholder per asset. Ensure that the users or user groups that you specify are already assigned the relevant user role. For example, to add a user as a stakeholder with the Governance Owner stakeholder role on an asset, the user must already be assigned the Governance Owner user role from the Administrator console. Type of Entry: Internal ID, email address of the user, the username, or last name followed by comma and then the first name, without any spaces in between. **Note:** To retrieve the internal ID of a user account or a user group, go to Administrator. The respective user or user group page URL contains the internal ID. Example of an internal ID: `23XVYy0NVSdiVYcf4ItJaQ` Example of an email address: `steve@yourorg.com` Example of a user name: `eclarke` Example of a full name: `Rhodes,Jane`
Role	Required	Role of the Stakeholder that you want to assign to the asset. If the user or user group that you want to assign as the asset stakeholder has multiple roles assigned to them, enter each role in a new row. Do not use comma to separate the values.
Operation	Required	Select an operation for the stakeholders. You can select one of the following options: - `Create`. You want to add a stakeholder to an asset. - `Delete`. You want to remove the stakeholder of an asset.

Relationships

A relationship between assets shows how the assets relate to one another. When data from a source system is ingested into the catalog, Data Governance and Catalog can automatically create relationships among the technical assets of that source system. You can connect business assets to each other and to relevant technical assets using different types of relationships.

The following table describes the columns where you must enter values to create relationships between assets:

Column	Type	Description
Source Asset	Required	Name or Reference ID of source asset of the relationship. If you have one or more source assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Source Asset Type	Required	Enter the exact name of the asset type of the source asset. Examples: `Business Term`, `Domain`
Target Asset	Required	Enter the name or Reference ID of target asset of the relationship. If you have one or more target assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Target Asset Type	Required	Enter the exact name of the asset type of the target asset. Examples: `Business Term`, `Domain`
Relationship Type	Required	Type of the relationship between the source asset and the target asset. Enter the exact type of the relationship. To see all possible values that you can enter here, see the Relationship Type column in the Annexure sheet of the spreadsheet. Examples: `Is related to`, `Parent Child Relationship` For more information about the predefined relationships that can be created between assets, see the *Types of direct relationships* topic in the *Asset Discovery* help. **Note:** It's possible that one or more of the relationship types listed in the Annexure sheet are exclusive to your organization. To ensure that you have the updated list of relationship types, consider downloading the latest template file. For more information about such relationships, contact your administrator. For more information about how your administrator can customize relationship types, see the *Administration* help in Metadata Command Center.
Operation	Required	Select an operation for the relationship. You can select one of the following options: - `Create`. You want to create a relationship between assets. - `Delete`. You want to remove a relationship between assets.

Note: In the predefined Microsoft Excel template that you download, you can refer to the **Annexure** sheet for the relationships that you can create in Data Governance and Catalog.

CHAPTER 3

Bulk import process

Create, update, or delete assets in bulk using the bulk import process.

To create, update, or delete a large number of business assets in the catalog, enter the asset details in one or more predefined Microsoft Excel template files and import the files to Data Governance and Catalog. For more information, see ."Import assets using template files" on page 146.

Alternatively, you can search for business or technical assets in the catalog and export the results of the search to a Microsoft Excel file. You can then update the exported file to curate technical and business assets, enrich assets with governance metadata, or mark the exported business assets for deletion. After making changes to the exported file, you can re-import the file to Data Governance and Catalog. However, you cannot create or delete technical assets through the bulk import process. For more information, see "Re-import assets from an exported assets file" on page 152.


Import assets using template files

Import business assets in Data Governance and Catalog using the predefined template files for each asset type.

Download predefined Microsoft Excel (.xlsx and .xlsm) templates for different asset types from Data Governance and Catalog, enter the details of assets in the templates, and import the template files. Data Governance and Catalog reads the details of assets in the template files and then creates, updates, or deletes assets in the catalog depending on the operation specified in the template file.

Alternatively, you can also use your own Microsoft Excel file to import the assets into the catalog. Informatica recommends that you use the predefined templates that you download from Data Governance and Catalog.

The following image shows the steps that you need to perform to bulk import assets in Data Governance and Catalog using the template file:



Perform the following tasks to import assets into the catalog using the template files:

- "Step 1: Get template file" on page 147
- "Step 2: Populate template file" on page 148
- "Step 3: Import the file" on page 149
- "Step 4: Map asset types and asset fields" on page 150
- "Step 5: Start import of assets" on page 151

After you successfully import assets using the bulk import template file, you can search and find the imported assets in Data Governance and Catalog.

Step 1: Get template file


Download a predefined Microsoft Excel (.xslx and .xlsm) template file for the asset types that you want to import.

When you download a predefined template, the file already contains the field names that you must enter for the assets. The file also indicates the properties that are mandatory and the properties that are optional. The column header cells contain notes for the properties to help you enter the values correctly. When you download the template file for an asset, you can also download additional sheets for adding relationships between assets and adding stakeholders. To ensure that the bulk import operation is successful, download the latest predefined template.

To download the template for any asset, the organization administrator must assign the read privilege for the Role asset to your user role in the Administrator service.

Perform the following steps to download a template file:

1. On the **Home** page, click **New** > **Import Assets** > **Download Import Template**.
2. In the **Download Import Template** dialog box, select the asset types and additional fields for which you want to import values.



Note: The following information applies to other file types that you can use apart from the predefined template:

- Instead of using the predefined template, you can use your own Microsoft Excel (.xslx and .xlsm), comma-separated value (.csv), or archive (.zip) file to import the assets. However, this requires you to manually map each sheet, column, or parameter in the file to the fields in Data Governance and Catalog. Consider using the predefined template files to upload the assets. The system can read the predefined templates quickly and import the assets correctly.
- The archive (.zip) file can contain a combination of Microsoft Excel (.xslx and .xlsm) and comma-separated value (.csv) files within it.

3. Click **Download**.

Step 2: Populate template file

After you download the template file, enter the asset details in the file.

For more information about entering asset values in the template file, see Chapter 2, “Template file properties” on page 8.
The following guidelines apply when you populate a template file:

- Each asset type appears as a separate sheet in the Microsoft Excel template file. In each sheet, enter the asset details. Enter one asset per row. Column headers in red color indicate a mandatory field, and column headers in black color indicate an optional field. See the note in the column headers for helpful tips on entering the asset details correctly.

  Note:

  - The columns in the template file will depend on how the asset's fields are configured by your administrator. If your administrator has configured new custom fields for an asset, it might affect the order of all the fields in the template file.
  - The order in which you specify the assets in the import file doesn't influence the sequence in which the assets are imported. The asset import sequence is randomized.

- An asset's position in the import sequence determines the ref ID that the system assigns to it. Consider the following example:

  You want to import a file that contains 10 assets that are of a type that is not present in your catalog. In the import file, you had specified the details about `Asset 1` in the first row, about `Asset 2` in the second row and so on. Despite this, it is possible for `Asset 1` to be the tenth asset in the import sequence. If `Asset 1` is the tenth asset that is imported, the system assigns the ref ID `AST-10` to it.


- If you are using your own personalized Microsoft Excel file, make sure that you enter one asset per row while populating the file with asset details.
- If you are using a comma-separated value (.csv) file, make sure that you populate the file as per the rules of the .csv file format.
- If you are using an archive (.zip) file with multiple supported file formats, make sure that you archive the import files.
- If you are updating the name of the stakeholder of an asset, add a space only between the first name and the second name of the stakeholder in the template file. For stakeholder names with more than two words, enter the username or the email ID of the stakeholder in the template file. For example, to enter `John Daniel Smith` as a stakeholder, enter the username `johndsmith`.

Step 3: Import the file

After you populate one or more template files, import the files containing asset details into Data Governance and Catalog.

Perform the following steps to import one or more files:

1. On the **Home** page, click **New** > **Import Assets** > **Import**.
2. On the **New Import** page, click **Import Files** and select the import file, or drag the file to the window. Ensure that the file name doesn't contain the following characters: `[, /, !, {, }, ], |, <, [, ^, >, ], *, >`



   When you import the file, the system reads the file to understand and interpret the values for any errors.
3. The system verifies for duplicate files with the same file name. If there is a duplicate file, you can select an option from the **Duplicate Files** dialog box.

Step 4: Map asset types and asset fields


Map and validate the asset types and column headers from the import files to the respective asset types and the asset fields in Data Governance and Catalog.

Mapping a predefined import file

If you import a predefined Microsoft Excel file as the template, the column headers should already map correctly to the correct interface fields. Before you start importing the assets, verify that the mapping is correct.

Perform the following steps to verify the mapping:

1. On the **New Import** page, select the sheet in the template file for which you want to map the column headers. Each sheet corresponds to an asset type.



2. Verify that the column header in the import file corresponds to the correct field in Data Governance and Catalog.

Mapping a custom import file

If you import a custom Microsoft Excel file, CSV, or archive (.zip) file as the template, the sheets in the file might not match the asset types in Data Governance and Catalog. Before you start importing the assets, verify that the mapping corresponds to the asset types that you want to import.

Perform the following steps to map the sheets in a custom import file to the corresponding asset types.

1. On the **New Import** page, click **Map Sheets** for custom Microsoft Excel files or **Map File** for CSV and archive files.
2. In the dialog box, map the sheets in the file to the corresponding asset types in Data Governance and Catalog.

The following table shows the file elements you map for each file type:

File type	What you map
Custom Microsoft Excel	Each sheet to an asset type
CSV (`.csv`)	Each file to one asset type
Archive (`.zip`)	Each sheet or file in the archive to an asset type


3. Click **OK** to complete the mapping.

Step 5: Start import of assets

When the file is ready and you have mapped all the asset types and asset properties in the file with the corresponding asset types and asset properties in Data Governance and Catalog, you are ready to import the assets.

Perform the following steps to import assets:

1. Click **Start Import**.
2. In the **Start Import** dialog box, enter the **Job Name** field and select an **Error Handling** option.



The following table lists the **Error Handling** options:

Error type	Description
Stop import on warning	The system evaluates the data in the file. If the system encounters a row with warning data, the process stops, and no data is imported. Select this option if you want to import only data that is correct and ready for use.
Stop import on error	The system evaluates the data in the file and ignores rows with warning data. If the system encounters a row with error data, the process stops, and no data is imported. If there are no rows with error data, the system imports valid data from the file, and warning data is marked as skipped. Select this option if you want to ignore the warnings and proceed with the import process. You can later download the error report, correct the warning data, and re-upload the file.
Skip errors and warnings	The system imports all valid rows from the template. Rows with warning and error data are marked as skipped. Select this option if you want to ignore the warnings and errors and proceed with the import process. You can later download the error report, correct the warning and error data, and re-upload the file.

3. Click **Start Import**.

   A new page displays the progress of the import job. For more information, see "Viewing import job status" on page 160.

   Note: The assets in the in-review lifecycle status cannot be re-imported into Data Governance and Catalog. You cannot update or delete an asset in the in-review lifecycle status.

If an asset type that you create or update through bulk import is associated with a workflow, Data Governance and Catalog creates a ticket for that asset type. After the import job is complete, you can view the tickets created for the imported assets in the **Imported Assets** section on the import file page. You can select the ticket to view their details on the **Ticket Manager** page.

Note: When you manage tickets for assets, consider the following guidelines:

- When you specify that a ticket is required for a new asset, the bulk import operation creates assets in the Draft state. The system doesn't consider the Lifecycle value that you specified in the template and is driven by the workflow configuration in Metadata Command Center.
- The system creates tickets only if all required stakeholders are specified. If some required stakeholders are missing, the asset update and ticket creation fails.
- When you delete assets, the system checks for open tickets associated with the asset. The system can't delete assets that have open tickets.

For more information about managing tickets associated with workflows, see the *Asset Management* help.

Re-import assets from an exported assets file

If you exported assets from Data Governance and Catalog, you can enrich, curate or update the assets in bulk and re-import the assets in Data Governance and Catalog.

You can perform the following tasks to re-import assets in bulk to Data Governance and Catalog:

1. Export assets from Data Governance and Catalog as a Microsoft Excel file in .xlsx or .xls file format. For more information about exporting assets, see the *Asset Discovery* help.
2. Modify the exported file to enrich, curate, or update business and technical assets. For more information, see "Modify the exported file" on page 153.
3. Import the updated file into Data Governance and Catalog. For more information, see "Step 3: Import the file" on page 149.
4. Validate the asset types and map the columns in the updated export file to the corresponding asset fields in Data Governance and Catalog. The format of the updated exported file is same as the predefined import template file. For more information, see "Mapping a predefined import file" on page 150.
5. When the file is ready and you have mapped all the asset types and asset properties in the exported file with the corresponding asset types and asset properties in Data Governance and Catalog, you are ready to start the import of assets. For more information, see."Step 5: Start import of assets" on page 151

Modify the exported file

Download the exported file containing the assets from the catalog, and modify the file in order to enrich, curate, or update business and technical assets.

For more information about exporting assets, see the *Asset Discovery* help.

The format of the export files for business assets is similar to the bulk import template files. The export files contain a table of contents and one sheet each for assets of the same type. Each asset sheet has some columns where changes are restricted. You can add, delete, or modify values in the available fields before re-importing the file in Data Governance and Catalog.

The following guidelines apply if you want to modify the contents of an exported file:

- To delete the value of a field of an asset using the UPDATE operation, replace the value in the field with double quotes without spaces.
- To create or modify the value of a custom attribute where the value contains a comma, enclose the value in double quotes and without spaces. For example, a multiselect drop-down for an asset has the following values:

  `- string`

  `- apache`

  `- home,work`

  Enter the values in the bulk import file cell in the following format: `string,apache,"home,work"`.
- Use a column header to sort the contents of the file. When you sort the contents of the file by ref ID, Microsoft Excel sorts the assets only alphabetically. You can't sort the assets numerically.
- When you export technical assets, the exported file can contain several sheets with the same attributes for the same assets. To prevent conflicting updates, each such attribute is editable in only one of those sheets.
  For example, if you export a relational database asset, the exported file might contain attributes in the Column, Database and Schema sheets that are also present in the Catalog Source, Technical Data Source, Technical Data Set, and Technical Data Element sheets. These attributes are greyed out and not editable in the Column, Database and Schema sheets. To modify these attributes, update the values in the Catalog Source, Technical Data Source, Technical Data Set, and Technical Data Element sheets.

You can use the bulk re-import process to enrich and curate assets in bulk, associate reference data with data elements in bulk, create or delete asset relationships in bulk, update generated classifications in bulk and much more.

Enrich assets in bulk

Enrich the exported technical assets with additional information and business context using the available fields in the exported file.

For example, you can add or update the business names and descriptions of technical data sets and technical data elements. You can only update technical assets but cannot delete them. To enter a description for the assets while re-importing technical assets into the catalog, use the **Description** field of the exported file.

Note: The values in the **Business Description** field is ignored during the re-import process. Copy the data from the **Business Description** field to the **Description** field before re-importing the file.

You can also create relationships between technical and business assets. For example, you can associate a data element to a business term.

You can use the bulk import file to add business metadata to technical assets. For example, you can associate data elements to a business term

Curate assets in bulk

When you export assets from the catalog, you can use the exported technical data set and technical data element sheets to curate assets in bulk and re-import them into Data Governance and Catalog.

The following ways describe how you can curate glossary and data classification recommendations for technical data sets and data elements:

Accept, reject, or remove glossary recommendations

Curate glossary terms for technical assets by accepting or rejecting recommended glossary terms or adding glossary terms to the asset. The **Glossaries: Recommended** field contains the glossary recommendations for the assets. Use the **Glossaries: Accepted** or **Glossaries: Rejected** fields in the exported sheets to accept or reject a recommendation.

You can also associate a published business term or metric for a unstructured file, such as a PDF, DOC, DOCX, or PPT file.

To remove the association between a glossary and an asset, use the **Glossaries: Remove** field. You can remove a glossary regardless of its current state for the asset. Enter the name or reference ID of the glossary.

Accept, reject, or remove classifications

Curate document classifications for unstructured data assets such as PDFs and text files. You can accept or reject classification recommendations, or manually add document classifications to the asset. For unstructured technical assets, use the **Document Classifications: Accepted** and **Document Classifications: Rejected** fields in the export sheets to accept or reject document classifications. The Policy asset also shows the **Classifications** column, where you can add data classifications to create relationships between them.

Curate data element or data entity classifications for technical assets. You can accept or reject the recommended classifications, or add your own classifications to the asset. You can promote, reject, or demote generated classifications for the asset. For technical assets, use the **Data Classifications: Accepted** and **Data Classifications: Rejected** fields in the export sheets to accept or reject data classifications.

To remove the association between a data classification and an asset, use the **Data Classifications: Remove** field. You can remove a data classification regardless of its current state for the asset.

Guidelines for removing glossaries and classifications

The following guidelines apply when you remove glossaries and classifications from assets:

- The **Remove** columns appear only on the exported sheets for technical data set and technical data element sheets. The template files that you download don't include these columns.
- If you select **Stop import on warning** as the error handling option, the import stops with a warning. To proceed with the removal, select **Stop import on error** or **Skip errors and warnings** and import the file again.
- If you remove a glossary or data classification, a subsequent catalog source sync job might recommend the same glossary or classification again.
- Don't enter the same value in the **Remove**, **Accept**, or **Rejected** columns. You can't remove and curate these associations at the same time.
- The re-import job summary counts a removal as an update, not a delete.

Automatically assign business names and descriptions to technical data elements

You can automatically assign business names and descriptions to technical data elements. The system assigns the business name and description to the technical data element from either an accepted glossary or from a glossary in the catalog that isn't already rejected for the data element.

To automatically assign business names and descriptions to technical data elements during glossary association, specify the value of the **Automatic Assignment** field as `Enabled` in the technical asset export sheet. In the **Glossary: Accepted** field, enter the name or reference ID of an accepted glossary that you want to use to assign a business name and description to the technical data element. To curate the technical data element with a glossary in the catalog which isn't already accepted for the data element, enter the name or reference ID of the glossary in the **Business Name** column.

To add a business name manually for the technical data element, select the `Disabled` value for the **Automatic Assignment** field. If you don't specify a value for the **Automatic Assignment** field, the system considers the input value as `Disabled`.

The following guidelines apply if you choose to automatically assign business names and descriptions to the technical data elements:

- If multiple glossaries are assigned the name that you specified in the **Glossary: Accepted** field, enter the reference ID of the glossary in the **Glossary: Accepted** field to enable the system to differentiate between duplicate glossaries.
- If you specify multiple glossaries in the **Glossary: Accepted** field, enter in the **Business Name** field the name of glossary that you want to use to assign a business name and description to the technical data element.
- If multiple glossaries are assigned the business name that you specified in the **Business Name** field, enter the reference ID of the glossary in the **Business Name** field to enable the system to differentiate between duplicate glossaries.
- In the **Glossary: Accepted** and the **Business Name** fields, enter the name of the glossary that isn't already rejected for the technical asset.
- If multiple glossaries are assigned the name that you specified in the **Glossary: Rejected** field, enter the reference ID of the glossary in the **Glossary: Rejected** field to enable the system to differentiate between duplicate glossaries.

Update stakeholder propagations in bulk

In the exported file, you can change how an asset propagates its stakeholders to its child assets and check how the stakeholders of each asset were added to it.

Stakeholder propagation settings

The propagation and append settings apply to assets that you can add as a parent of another asset.

The following table describes the columns that you can view and modify in the exported file:

Column	Type	Description
Propagate Stakeholders	Optional	Specify whether you want the inherited stakeholders of this asset to propagate to child assets that don't have stakeholders assigned. Select one of the following options: - `Enable`. Propagates the stakeholders of this asset to child assets that don't have stakeholders assigned. - `Disable`. Doesn't propagate the stakeholders of this asset to child assets. **Note:** If you disable this option in a later bulk import job, the child assets lose the stakeholders that they inherited from this asset. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Append Stakeholders	Optional	Specify whether you want the stakeholders of this asset to be appended to child assets that have stakeholders assigned. Select one of the following options: - `Enable`. Appends the stakeholders of this asset to child assets that already have stakeholders assigned. - `Disable`. Doesn't append the stakeholders of this asset to child assets that have stakeholders assigned. **Note:** If you disable this option after stakeholders were appended to child assets, the **Assigned** stakeholders replace the **Inherited** stakeholders. For more information about propagating and appending stakeholders, see "Update stakeholder propagations in bulk" on page 156.
Stakeholder Type	Optional	Indicates how stakeholders are associated with the asset and the types of stakeholder associations the asset can have. You can specify if the asset's stakeholders are directly assigned, inherited from a parent asset, or both. **Note:** The parent asset's **Propagate Stakeholders** and **Append Stakeholders** settings determine whether stakeholders propagate from the parent asset and how far the propagation continues. Check these settings on the parent assets before you import this file. Select one of the following options: - `Assigned`. The asset can have directly assigned stakeholders. - `Inherited`. The asset inherits stakeholders from a parent asset. - `Both`. The asset can have both assigned and inherited stakeholders.

Consider the following conditions when you modify the propagation columns :

- If **Propagate Stakeholders** is disabled, the child asset has only the stakeholders that you assigned.
- If **Propagate Stakeholders** is enabled and **Append Stakeholders** is disabled, the stakeholders that you assigned replace the stakeholders that the child asset inherited.
- If **Propagate Stakeholders** and **Append Stakeholders** are both enabled, the stakeholders that you assigned are added to the inherited stakeholders.

In an export file, you can view the **Stakeholder Type** column for assets associated with stakeholders. When you re-import assets after modifying the **Stakeholder Type** column, the values interacts with the **Propagate Stakeholders Append Stakeholders**.

To avoid errors when you re-import the file, follow these guidelines:

- Don't enable **Append Stakeholders** for an asset if **Propagate Stakeholders** is disabled.
- If the parent asset has both **Propagate Stakeholders** and **Append Stakeholders** enabled, enter `Both` in the **Stakeholders Type** column of the child asset, or leave the cell blank. With a `Both` or blank value, the child asset can receive both assigned and inherited stakeholders.
- If the parent asset has only **Propagate Stakeholders** enabled, enter `Inherited` in the **Stakeholder Type** column of the child asset.
- The stakeholders that you want to propagate also interact with the asset groups that an asset and its hierarchy is assigned to. If the asset belongs to one or more asset groups, a user that you add as a stakeholder requires access to those asset groups. If you add a user group as a stakeholder, the user group requires access to the asset groups associated with the asset.

For more information about how assets inherit their stakeholders, see *Stakeholder propagation* in the *Asset Management* help.

Manage asset groups in bulk

With template or an export file, you can assign and remove asset groups for business and technical assets.

In the **Asset Groups** column, enter the names of the asset groups you want to assign to an asset or remove.

Consider the following guidelines when you modify asset groups in an import file:

- You can't assign an asset group that you don't have access to.
- You can organize asset groups in a hierarchy. The following rules apply when you assign, or remove an asset group to an assets in a hierarchy:
  - Before you can assign an asset group to a child asset, assign that asset group, or an asset group above it in the hierarchy to every parent asset in its hierarchy.
  - Assign the parent asset an asset group at the same level as, or higher than, the asset groups assigned to its child assets.
  - Assign either a child asset group or its parent asset group to an asset, but not both.
  - Before you can remove an asset group from a parent asset, remove the asset group from every child asset that is assigned the asset group.
- The **Asset Groups** column is read-only for technical data elements, which inherit their asset group from their technical data sets. Manual data elements also inherit their asset group from an associated data set. You can't directly assign an asset group to either asset type.
- Asset group access also governs related associations. You can't associate a glossary with an asset if you don't have access to the asset group that the glossary belongs to. The same applies to business data sets.
- For a data quality rule occurrence, the primary data element is the parent of the data quality rule occurrence. Therefore, assign an asset group that is the same as the primary data element's asset group, or within that asset group's hierarchy. You can't add a secondary data element that belongs to an asset group you don't have access to.
- For a data quality rule template, you require the **Read** access to the asset group of any glossary that you assign as the primary or secondary glossary.

For more information about asset groups, see the *Metadata Access Control Handbook* help.

Associate reference data with data elements in bulk

In the exported file, modify the data elements to associate them with reference data from Reference 360.

You can then import the exported file back to Data Governance and Catalog to make the association between the data elements and the reference data.

The following table describes the two columns in the template to associate reference data with data elements.

Column	Type	Description
Reference Data	Optional	Associate reference data from Reference 360 with a data element by entering the path of a code list attribute from Reference 360. You can associate only one code list attribute with a data element. Example: `Reference360Catalog Source/Country/Enterprise Country/Code`
Referenced Glossary	Optional	Enter the name or reference ID of a Glossary asset that is associated with a reference data. The reference data that is associated with the Glossary asset gets associated with the data element. You can specify only one Glossary asset. Example: `TERM-102`


Update generated classifications in bulk

Use the bulk import process to promote, reject, or demote generated classifications for multiple data elements at once.

To bulk promote generated classifications to data element classifications, or to demote already promoted data classifications, search and export all generated classifications in a Microsoft Excel file. The **Generated Classifications: Recommended** field of the technical data element sheet shows generated classifications for data elements. You can perform the following actions:

- To reject the generated classifications that you don't wish to promote, use the **Generated Classification: Rejected** column of the technical data element sheet.
- To promote a generated classification to a data element classification, use the **Data Element Classification: Promoted** column of the generated classification sheet.
- Demote an already promoted data classification by using the **Data Element Classification: Demoted** column.

The following image shows the Generated Classification sheet that you can use to promote or demote generated classifications in bulk:



Create or delete asset relationships in bulk

Use the bulk re-import process to create or delete relationships between business assets in bulk.

If you include asset relationships in the exported file, you can create or delete relationships between business assets in bulk and re-import the file into Data Governance and Catalog.

The following table describes the columns that you can view in the exported file:


Column	Type	Description
Source Asset	Required	Name or Reference ID of the source asset of the relationship. If you have one or more source assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Source Asset Type	Required	Enter the exact name of the asset type of the source asset. Examples: `Business Term`, `Domain`
Target Asset	Required	Name or Reference ID of the target asset of the relationship. If you have one or more target assets with the same name, consider entering the **Reference ID** value for the assets to help the system to distinguish between them.
Target Asset Type	Required	Enter the exact name of the asset type of the target asset. Examples: `Business Term`, `Domain`

Column	Type	Description
Relationship Type	Required	Type of the relationship between the source asset and the target asset. Enter the exact type of the relationship. Examples: `Is related to`, `Parent Child Relationship` For more information about the predefined relationships that can be created between assets, see the *Types of direct relationships* topic in the *Working With Details* help.
Operation	Required	Select an operation for the relationship. You can select one of the following options: - `Create`. You want to create a relationship between assets. - `Delete`. You want to remove a relationship between assets.

Viewing import job status


When you import assets using the bulk import process, Data Governance and Catalog creates a job for the bulk import task. You can monitor the status of the job in Data Governance and Catalog to determine the completion status.

1. On the **Home** page, click the **Job Monitoring** icon.



The **Job Monitoring** page displays the list of all jobs.

2. View basic information such as job type, start and end date, and the status of each job on this page.



3. To download job log, click the **Action** menu for the job, and click **Download Log**.
4. To see more details of the job, click the job name to open the job on a new page.

Note: Irrespective of the import job status, verify the assets and asset details that you have imported by opening the assets in Data Governance and Catalog.

CHAPTER 4

Troubleshooting bulk import of assets

Consider the following troubleshooting tips when you export or import assets in bulk.

If you export data quality rule occurrences that are associated with data quality scorecards, Data Governance and Catalog does not export the primary data elements associated with the rule occurrences.

Also, if you update the rule occurrences and re-import them back into Data Governance and Catalog, the bulk import operation does not update the rule occurrences.

To make changes to these scorecard rule occurrences, use Cloud Data Profiling.

If you export assets that contain images and then re-import the exported file, the images are not re-imported back into Data Governance and Catalog.

You cannot import images using the bulk import process. Instead, use the user interface to update or add a new image.

The bulk import job fails if I create a glossary and assign it to an asset during the same job.

Creating the glossary and assigning it to an asset during the same bulk import job might cause the bulk import to fail with an error.

To associate a glossary with any asset, first create the glossary and then associate the glossary with the asset during the next bulk import job.

For the same asset, you cannot update one parent in the hierarchy and delete another parent in the hierarchy using the same bulk import job.

For example, you cannot delete the parent subdomain `Payroll` and update the parent domain `Finance` in the same bulk import job.

To work around this, first, delete the parent asset using the DELETE operation and run the bulk import operation. You can then add another parent asset using the UPDATE operation and run the bulk import operation again.

INDEX

A

asset
  importing assets 146

B

bulk import process
  preparing a predefined import file 150
  step 1:get template file 147
bulk import process *(continued)*
  step 2:populate template file 148
Bulk import template
  Stakeholders 144

O

overview
  bulk import 6