FlexNet License Server

User Guide

No Magic, Inc., a Dassault Systèmes company, 2021

All material contained herein is considered proprietary information owned by No Magic, Inc. and is not to be shared, copied, or reproduced by any means. All information copyright 1998-2021 by No Magic, Incorporated, a Dassault Systèmes company. All Rights Reserved.

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

Contents

Using the FlexNet license server 5

FlexNet server and modeling tools compatibility 5

FlexNet license server 11.17 6

- Choosing the Flexnet server manager 6
- Prerequisites 6
- Windows 7
- Linux 7
- Installing FlexNet 11.17 9
  - Installation procedure 9

FlexNet license server 11.12, 11.14, 11.16 11

- Choosing the Flexnet server manager 12
- Prerequisites 12
- For Windows users 12
- For Linux users 14
- Installing FlexNet license server 11.12, 11.14, 11.16 16
  - Installation procedure 16

Checking if the FlexNet server is running 18

Adding a license to the FlexNet server 19

- Prerequisites 19
- Procedure 19
- Determine the Host ID or Target ID of the machine on which the FlexNet license server is installed 20

Replacing a license key on the FlexNet license server 22

Uninstalling FlexNet license server 23

Moving or upgrading the FlexNet license server 23

Useful commands 24

Troubleshooting 25

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

JRE libraries are missing or not compatible 25

No such file or directory running lmadmin 26

lmadmin won't start 26

'Can't make directory' error running lmgrd 27

You have no permission to install lmadmin in that directory 27

A sample script that performs the automated installation of lmadmin 11.14 from nomagic.comhttp://nomagic.com in case you need it for reference purposes 29

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

Related resources

- License Administration Guide. FlexNet Publisher 2020 R2 (11.17.0)[1]
- License Administration Guide. FlexNet Publisher 2019 R2 (11.16.4)[2]
- License Administration Guide. FlexNet Publisher 2014 R1 (11.12.1)[3]

The FlexNet Publisher license server (the floating license server) from Flexera[4] is used for managing floating licenses. The basic components of the FlexNet Publisher license server are these:

- license server administrator
- license key file
- vendor daemon[5]

A floating license allows you to install and use the same license on multiple machines. The licenses are managed by the floating license server. The floating license server has information on the total number of products and editions you have and how many of these licenses are currently in use.

Using the FlexNet license server

To use the FlexNet server

1. Install the server.(see page 6)
2. Add the license key to the server(see page 19).

FlexNet server and modeling tools compatibility

You need to choose the version of the FlexNet license server and vendor daemon - Cameo according to the modeling tool version you use:

Modeling tool\FlexNet version	11.12.0 and below	11.14.0	11.16.4	11.17.0
2021x	not compatible	X [1]	X [1]	X
19.0 and below	X	X [1]	X [1]	X [1]

1 https://docs.nomagic.com/download/attachments/70388394/fnp_LicAdmin_11_17_0.pdf?api=v2&modificationDate=1611149745747&version=1
2 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11.16.4.pdf?api=v2&modificationDate=1611149745448&version=1
3 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11_12_1.pdf?api=v2&modificationDate=1611149745409&version=1
4 https://www.flexera.com/
5 https://docs.nomagic.com/display/NMDOC/Basic+concepts#Basicconcepts-vendordaemon

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

[1] except Windows 64-bit, Linux 64-bit, and MAC 64-bit *lmadmin\lmgrd* with a vendor daemons – *cameo* of 64-bit. These utilities are incompatible.

Related pages

- FlexNet license server 11.17(see page 6)
- FlexNet license server 11.12, 11.14, 11.16(see page 11)
- Checking if the FlexNet server is running(see page 18)
- Adding a license to the FlexNet server(see page 19)
- Replacing a license key on the FlexNet license server(see page 22)
- Uninstalling FlexNet license server(see page 23)
- Moving or upgrading the FlexNet license server(see page 23)
- Useful commands(see page 24)
- Troubleshooting(see page 25)

FlexNet license server 11.17

On this page

- Choosing the Flexnet server manager(see page 6)
- Prerequisites(see page 6)
- Windows(see page 7)
- Linux(see page 7)

For more information about FlexNet, see:

- License Administration Guide. FlexNet Publisher 2020 R2 (11.17.0)[6]

Choosing the Flexnet server manager

There are three types of FlexNet server managers:

- *lmadmin* – a web-based license server manager with GUI (recommended).
- *lmgrd* – a license server manager with a command-line interface.
- *lmtools* – the old Windows-based server manager (replaced by *lmadmin*).

We recommend using *lmadmin*.

Prerequisites

- You have downloaded[7] the installation files of:
  - the FlexNet license server manager.
  - the vendor daemon - Cameo.

6 https://docs.nomagic.com/download/attachments/70388394/fnp_LicAdmin_11_17_0.pdf?api=v2&modificationDate=1611149745747&version=1

7 https://docs.nomagic.com/display/NMDOC/Downloading+installation+files

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

⚠ The license server manager (e.g., *lmadmin*) should be of the same or later version as a vendor daemon - Cameo you use.

Windows

⚠ To use *lmadmin* on Windows platforms, the Microsoft Visual C++ 2013 Redistributable Package must be installed. You have an option to install this package during the FlexNet Publisher License Server Installer process.

You can run *lmadmin* (11.17.0) on these officially supported platforms:

- Windows 10
- Windows Server 2008, including SP1, SP2, and R2
- Windows 8
- Windows 8.1
- Windows 7, including SP1
- Windows Server 2012 R2
- Windows Server 2012

Modeling tool version	**32-bit system**	**64-bit system**
2021x	We recommend using 32-bit *lmadmin* or 32-bit *lmgrd* with a 32-bit Cameo daemon vendor file.	We recommend using 64-bit *lmadmin* or 64-bit *lmgrd* with a 64-bit Cameo daemon vendor file.
19.0 and earlier	We recommend using 32-bit *lmadmin* or 32-bit *lmgrd* with a 32-bit Cameo daemon vendor file.	We recommend using 64-bit *lmadmin or 64-bit lmgrd with a 64-bit Cameo daemon vendor file.*

Linux

- You need to have the *glibc* libraries installed corresponding to your operating system architecture.
- You need to create a non-root system user with root privileges and install/run the server tools(lmadmin/lmgrd) using it:

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

This can be achieved either by:
1. Adding the user to the 'sudo' group
2. Editing the file /etc/sudoers using visudo.

Method 1 (Ubuntu based)

```
sudo adduser newuser
sudo usermod -aG sudo newuser
```

Method 2 (Ubuntu based)

```
Modify '/etc/sudoers' with the editor "visudo".

#Create a user called "newuser"
[root@mylinux~]#useradd newuser
[root@mylinux~]#passwd newuser

#Edit the file with visudo:
[root@mylinux~]# visudo

#Find a line 'User privilege specification' and add the following.
newuser ALL=(ALL) ALL
```

Method 1 (Redhat/Fedora/CentOS)

```
sudo adduser newuser
sudo passwd newuser
sudo usermod -aG wheel newuser
```

- You have to install the Linux Standard Base (LSB) library.

For Ubuntu

```
sudo apt-get install lsb-core
```

For Redhat/CentOS/Fedora

```
sudo yum install redhat-lsb-core
```

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

Modeling tool version	32-bit system	64-bit system
2021x	• We recommend using 32-bit *lmadmin* installer or 32-bit *lmgrd.*	We recommend using 64-bit *lmadmin* or 64-bit *lmgrd* with a 64-bit Cameo daemon vendor file.
19.0 and earlier	• We recommend using 32-bit *lmadmin* installer or 32-bit *lmgrd.*	• **Please use 32-bit *lmadmin* installer.** Additional 32-bit libraries need to be installed in the 64-bit multi-arch system to execute them. • Alternatively, you can use 64-bit *lmgrd* version 11.12.1. Learn more about 11.12.1 installation >>(see page 11)

Check if LSB was successfully installed using:

```
lsb_release -a
```

⚠ In order to query which lsb library is required for a particular Centos version, the following command can be executed:

```
sudo yum provides /lib/ld-lsb.so.3
```

ⓘ It is the best practice to run license servers on a server-based OS.

Related pages

- Installing FlexNet 11.17(see page 9)
- Troubleshooting(see page 25)
- Useful commands(see page 24)


Installing FlexNet 11.17

Installation procedure

1. Install the FlexNet license server manager.

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

We highly recommend running the FlexNet license server (*lmadmin*) as a service (on Windows) or a daemon (on OS X or Linux).
As a result, the server can start automatically after the machine boots. Starting the server manually is not user-friendly – there is no GUI for this action.
If your operating system is Windows, you only need to select the **Run as a service** check box when prompted during the *lmadmin* installation.



For the instructions on how to create a daemon, refer to Automatic Start in:
- License Administration Guide. FlexNet Publisher 2020 R2 (11.17.0)[8]


2. Place the vendor daemon - Cameo into the FlexNet server install folder. If you use *lmadmin*, do the following:
   a. Open the FlexNet server install folder.

   For OS X and Linux users
   If you don't have permission to open the FlexNet server data folder, execute the following command from the root:
   - On OS X
     ```
     chmod g+x FNPLicenseServerManager/
     chmod –R g+w ./*
     ```
   - On Linux
     ```
     chmod g+x FNPLicenseServerManager/
     ```

   b. In the install folder, create the *licenses\cameo* folder.
   c. Place the Vendor daemon in *<FlexNet server data folder>\licenses\cameo*.

8 https://docs.nomagic.com/download/attachments/70388394/fnp_LicAdmin_11_17_0.pdf?api=v2&modificationDate=1611149745747&version=1

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.



⚠ Note that all files in *install* and *data (for Windows)* dirs must have read/write permissions. *lmadmin* or cameo daemon may not start even if a log file or cameo daemon does not have r/w permissions.
Use this command to set permissions for all files within the directory recursively.
chmod -R 755 FNPLicenseServerManager

3. Start the server (as a service), or using the command line manually by running the *lmadmin* file from the FlexNet server installation directory.

⚠ **Running lmadmin using command line on Windows**
If a service was not installed and you want to run your lmadmin using command line, you will have to define the additional required parameters. e.g. -configDir. The dir is located in your *data* dir (for example *C:\ProgramData\FLEXlm\lmadmin or any other location you defined while installing).*

If you come across any issues while installing/running the software, please refer to Troubleshooting(see page 25).

FlexNet license server 11.12, 11.14, 11.16

On this page

- Choosing the Flexnet server manager(see page 12)
- Prerequisites(see page 12)
- For Windows users(see page 12)
- For Linux users(see page 14)

For more information about FlexNet, see:

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

- License Administration Guide. FlexNet Publisher 2014 R1 (11.12.1)[9]
- License Administration Guide. FlexNet Publisher 2019 R2 (11.16.4)[10]

Choosing the Flexnet server manager

There are three types of FlexNet server managers:

- *lmadmin* – a web-based license server manager with GUI (recommended).
- *lmgrd* – a license server manager with a command-line interface.
- *lmtools* – the old Windows-based server manager (replaced by *lmadmin*).

We recommend using *lmadmin*.

- *lmadmin* installer comes in 32-bit architecture (regardless of the version) only.
- 11.12.1 version license server utilities (except the *lmadmin* installer) come in 32/64-bit architectures.
- 11.14 version license tools are not available in 64-bit binaries. Only 32-bit tools are available (additional 32-bit libraries need to be installed in the 64-bit multi-arch system to execute them).

Prerequisites

- You have downloaded[11] the installation files of:
  - the FlexNet license server manager.
  - the vendor daemon - Cameo.

The license server manager (e.g., *lmadmin*) should be of the same or later version as a vendor daemon - Cameo you use.

For Windows users

To use *lmadmin* on Windows platforms, the Microsoft Visual C++ 2013 Redistributable Package must be installed. You have an option to install this package during the FlexNet Publisher License Server Installer process.

9 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11_12_1.pdf?api=v2&modificationDate=1611149745409&version=1
10 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11.16.4.pdf?api=v2&modificationDate=1611149745448&version=1
11 https://docs.nomagic.com/display/NMDOC/Downloading+installation+files

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

Windows	32-bit system	64-bit system
• You can run *lmadmin* (11.12.1) on these officially supported platforms: • Windows 8 • Windows Server 2012 • Windows Server 2008 • Windows 7 (Ultimate) • Windows Vista (Ultimate) • You can run *lmadmin* (11.14) on these officially supported platforms: • Windows 10 • Windows Server 2008, including SP1, SP2, and R2 • Windows 8 • Windows 8.1 • Windows 7, including SP1 • Windows Server 2012 R2 • Windows Server 2012	We recommend using 32-bit *lmadmin* or 32-bit *lmgrd* with a 32-bit Cameo daemon vendor file.	We recommend using 32-bit *lmadmin*. Additional 32-bit libraries need to be installed in the 64-bit multi-arch system to execute them.

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

For Linux users

Linux

- You need to have the *glibc* libraries installed corresponding to your operating system architecture.
- You need to create a non-root system user with root privileges and install/run the server tools using it:

⚠ This can be achieved either by:

1. Adding the user to the 'sudo' group

2. Editing the file /etc/sudoers using visudo.

Method 1 (Ubuntu based)

```
sudo adduser newuser
sudo usermod -aG sudo newuser
```

Method 2 (Ubuntu based)

```
Modify '/etc/sudoers' with the editor "visudo".

#Create a user called "newuser"
[root@mylinux ~]#useradd newuser
[root@mylinux ~]#passwd newuser
```

32-bit system

- We recommend using the 32-bit *lmadmin* installer or 32-bit *lmgrd.*
- You need to install the Linux Standard Base (LSB) library.

⚠ **For Ubuntu**

```
sudo apt-get install lsb-core
```

For Redhat/CentOS/ Fedora

```
sudo yum install redhat-lsb-core
```

64-bit system

- We recommended using 32-bit *lmadmin* and 64-bit *lmgrd* for 64-bit multi-arch systems.
- For version **11.12.1** we recommend either using the 32-bit *lmadmin* installer (for multi-arch systems), or the 64-bit *lmgrd*:

⚠ Installing 32-bit *lmadmin* on a multi-arch machine will require 32-bit libraries.

For recent Ubuntu

```
sudo apt-get install libc6-i386
apt-get update
sudo apt-get install lsb-core
```

For older Ubuntu use

```
sudo dpkg --add-architecture i386
apt-get update
sudo apt-get install libc6:i386 libncurses5:i386 libstdc++6:i386
sudo apt-get install lsb-core
```

For Redhat/CentOS/Fedora

```
sudo yum install redhat-lsb-core.i686
```

Running 64-bit *lmgrd* on 64-bit systems requires 64-bit Linux Standard Base (LSB) library.

For Ubuntu

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

Linux	32-bit system	64-bit system

```
#Edit the file with visudo:
[root@mylinux ~]# visudo

#Find a line 'User privilege specification' and add the following.
newuser ALL=(ALL) ALL
```

Method 1 (Redhat/ Fedora/CentOS)

```
sudo adduser newuser
sudo passwd newuser
sudo usermod -aG wheel newuser
```

```
sudo apt-get install lsb-core
```

For Redhat/CentOS/Fedora

```
sudo yum install redhat-lsb-core
```

- For version **11.14** we recommend either using the 32-bit *lmadmin* in staller, or the 32-bit *lmgrd* for multi-arch systems. **64-bit 11.14 lmadmin/lmgrd binaries are not available.**

⚠ Both of them require 32-bit libraries. Install it using:

For recent Ubuntu

```
sudo apt-get install libc6-i386
apt-get update
sudo apt-get install lsb-cor
```

For older Ubuntu

```
sudo dpkg --add-architecture i386
apt-get update
sudo apt-get install libc6:i386 libncurses5:i386 libstdc++6:i386
sudo apt-get install lsb-core
```

For Redhat/CentOS/Fedora

```
sudo yum install redhat-lsb-core.i686
```

lmadmin 11.14 comes with libssl.so[12].1.0.0 in its

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

Linux	32-bit system	64-bit system
		installation directory. You need to add these libraries in lmadmin directory to the LD_LIBRARY_PATH in order to run *lmadmin*. e.g. if your *lmadmin* installation is at /opt/FNPLicenseServerManager then adding it to the path would look like this: `export LD_LIBRARY_PATH=$LD_LIBRARY_PATH:/opt/FNPLicenseServerManager`

Check if LSB was installed successfully using:

```
lsb_release -a
```

⚠ In order to query which lsb library is required for a particular Centos version, the following command can be executed:

```
sudo yum provides /lib/ld-lsb.so.3
```

ⓘ It is the best practice to run license servers on a server-based OS.

Related pages

- Installing FlexNet license server 11.12, 11.14, 11.16(see page 16)
- Troubleshooting(see page 25)
- Useful commands(see page 24)


Installing FlexNet license server 11.12, 11.14, 11.16

Installation procedure

1. Install the FlexNet license server manager.

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

We highly recommend running the FlexNet license server (*lmadmin*) as a service (on Windows) or a daemon (on OS X or Linux).
As a result, the server can start automatically after the machine boots. Starting the server manually is not user-friendly – there is no GUI for this action.
If your operating system is Windows, you only need to select the **Run as a service** check box when prompted during the *lmadmin* installation.



For the instructions on how to create a daemon, refer to Automatic Start in:
- License Administration Guide. FlexNet Publisher 2014 R1 (11.12.1)[13]
- License Administration Guide. FlexNet Publisher 2019 R2 (11.16.4)[14]

2. Place the vendor daemon - Cameo into the FlexNet server install folder. If you use *lmadmin*, do the following:
   a. Open the FlexNet server installation folder.


> **For OS X and Linux users**
> If you don't have permission to open the FlexNet server installation folder, execute the following command from the root:
> - On OS X
>
> ```
> chmod g+x FNPLicenseServerManager/
> chmod –R g+w ./*
> ```
>
> - On Linux
>
> ```
> chmod g+x FNPLicenseServerManager/
> ```

   b. In the open folder, create the *licenses\cameo* folder.

13 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11_12_1.pdf?api=v2&modificationDate=1611149745409&version=1
14 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11.16.4.pdf?api=v2&modificationDate=1611149745448&version=1

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

c. Place the vendor daemon in *<FlexNet server installation folder>\licenses\cameo*.



> ⚠ Note that all files in FNPLicenseServerManager must have read/write permissions. *lmadmin* or cameo daemon may not start even if a log file or cameo daemon does not have r/w permissions.
> Use this command to set permissions for all files within the directory recursively.
> chmod -R 755 FNPLicenseServerManager

3. Start the server by running the *lmadmin* file from the FlexNet server installation directory.

If you come across any issues while installing/running the software, please refer to Troubleshooting(see page 25).

Checking if the FlexNet server is running

There are three ways to check if the FlexNet server is running:

1. Log on to the FlexNet License Server management Web interface. The default address is http://localhost:8090[15] or use your server name (*http://<server name>:8090*). If connection is established, the FlexNet server is running.
2. Check the *lmadmin* task status in:
   - Task Manager on Windows
   - Activity Monitor on OS X
   - System Monitor on Linux

   If the status is *Running*, the FlexNet server is running.
3. Open the *lmadmin.log* file which can be found in *<lmadmin installation directory>\logs*. Lines in the following example identify that *lmadmin* is successfully started and the FlexNet server is running:

```
2015-12-09 20:28:31,781 root.LicenseEngine started without redundancy.

2015-12-09 20:28:31,958 root.Vendor (cameo) started.

2015-12-09 20:28:31,778 root Version: 11.13.1.0 build 166859
(2015.06.16-10.40.53)
```

15 http://localhost:8090/

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

If the FlexNet server is not running, open the *lmadmin.log* file, found in *<lmadmin installation directory>\logs.* The installation error codes are listed there. Use the error codes to try to find a solution in the FlexNet server License Administration Guide:

- License Administration Guide. FlexNet Publisher 2014 R1 (11.12.1)[16]
- License Administration Guide. FlexNet Publisher 2019 R2 (11.16.4)[17]
- License Administration Guide. FlexNet Publisher 2020 R2 (11.17.0)[18]

If you still can't identify the server starting problem, please contact our support team[19].

Adding a license to the FlexNet server

Prerequisites

- The FlexNet license server is installed.
- You have the license key.

Procedure

1. Start the FlexNet license server.
2. Import the license key to the FlexNet license server.

To import the license key to the FlexNet license server:


---

1. Connect to the FlexNet License Server management Web interface. Use the default address (http://localhost:8090[20]) or your server name (http://<server name>:8090).
2. Click **Administration** at the top-right corner of the webpage. When prompted to sign in, enter the default administrator's credentials (admin/admin).
3. In the FlexNet License Administrator's webpage, click **Vendor Daemon Configuration** on the left.
4. Click **Import License** and select the received license key file.
5. Click the **Import License** button.

   If you want to re-import the license key file, select the **Overwrite License File on License Server** check box.

16 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11_12_1.pdf?api=v2&modificationDate=1611149745409&version=1
17 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11.16.4.pdf?api=v2&modificationDate=1611149745448&version=1
18 https://docs.nomagic.com/download/attachments/70388394/fnp_LicAdmin_11_17_0.pdf?api=v2&modificationDate=1611149745747&version=1
19 https://docs.nomagic.com/display/NMDOC/Support
20 http://localhost:8090/

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.



1.

Related pages

- Determine the Host ID or Target ID of the machine on which the FlexNet license server is installed(see page 20)

Determine the Host ID or Target ID of the machine on which the FlexNet license server is installed

You can determine the Host ID/Target ID of the machine on which the FlexNet license server is installed:

- using *lmadmin.*
- using *lmhostid.*

To determine the Host ID/Target ID of the machine on which the FlexNet license server is installed (using *lmadmin*)


---

1. Connect to the FlexNet License Server management Web interface.

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

The default address is http://localhost:8090[21] or use your server name (*http://<server name>:8090*).

2. Click **Administration** at the top-right corner of the webpage. When prompted to sign in, enter the default administrator's credentials (*admin/admin)*.
3. Copy the Host ID/Target ID displayed as Ethernet Address (as in the following figure).



The *lmhostid* is a command line utility, which prints the Host ID/Target ID that a FlexNet license server requires on any supported system. The *Lmhostid* utility is available as an executable called *lmutil*.

To determine the Host ID/Target ID of the machine on which the FlexNet license server is installed (using *lmhostid*)

---

1. Locate *lmutil* for a particular OS in the downloaded[22] ***<product folder>*\Flex_Utilities_User_Guides_Vendor_Daemons\<*FlexNet version*>\Server utilities** folder.
2. Run *lmutil* with *lmhostid* parameter from the command line. *Lmhostid* displays the default Host ID/Target ID for the current platform.

For the exact commands for a specific OS refer to: License Administration Guide (Obtaining System Hostids):

---

21 http://localhost:8090/
22 https://docs.nomagic.com/display/NMDOC/Downloading+installation+files

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

- License Administration Guide. FlexNet Publisher 2014 R1 (11.12.1)[23]
- License Administration Guide. FlexNet Publisher 2019 R2 (11.16.4)[24]
- License Administration Guide. FlexNet Publisher 2020 R2 (11.17.0)[25]

⚠ If two or more Ethernet addresses are available on the particular machine, the first one printed by the Host ID command should be used.

Replacing a license key on the FlexNet license server

You must replace the old floating license key with a new one if:

- You upgrade products to the new version that uses the floating license.
- The Ethernet Address (Host ID/Target ID(see page 20)) of the machine on which the FlexNet license server is installed changes.

To replace a license key

---

1. Add the license key to the FlexNet license server(see page 19) (or use the alternative*).
2. Restart the Vendor Daemon - Cameo:
   a. Connect to the FlexNet License Server management Web interface.

      ⚠ The default address is http://localhost:8090/ or use your server name (*http://<server name>:8090*)

   b. Click the **Vendor Daemon Configuration** tab.
   c. In the **Vendor Daemons** list, click the desired daemon and start in again.
   d. Save changes.

* You can copy the new license key directly to a specific location in the floating license server installation folder rather than importing the file by using *lmadmin*. Use this method as an alternative if you cannot import the license key.

To add a new license file to the floating license server by copying it directly to a specific location

---

1. Go to the folder the new license file is stored in and copy the file.
2. Go to *<floating license server installation directory>\licenses\cameo* and paste the file.
3. Connect to the FlexNet License Server management Web interface. Use the default address (http://localhost:8090[26]) or your server name (http://<server name>:8090).
4. Sign in as the administrator.
5. On the left side menu, click **Vendor Daemon Configuration**.
6. In the appropriate cameo vendor daemon row, click the **Administer** button.
7. Click the **Reread License Files** button. If the license file is successfully imported, you will see an appropriate message on the webpage.

---

23 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11_12_1.pdf?api=v2&modificationDate=1611149745409&version=1
24 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11.16.4.pdf?api=v2&modificationDate=1611149745448&version=1
25 https://docs.nomagic.com/download/attachments/70388394/fnp_LicAdmin_11_17_0.pdf?api=v2&modificationDate=1611149745747&version=1
26 http://localhost:8090/

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

8. Check the active licenses (see the following procedure).
9. If the active licenses are not updated, please restart the floating server.

To check active licenses

1. Connect to the FlexNet License Server management Web interface. The default address is *http://localhost:8090/* or use your server name (*http://<server name>:8090*).
2. Open the **Dashboard.**
3. Click Concurrent. All active licenses are listed in a table.

Uninstalling FlexNet license server

To uninstall the FlexNet license server

1. Go to the FlexNet Server Publisher web interface.

   ⚠ Use the default address (http://localhost:8090[27]) or your server name (http://[28]<server name>:8090).

2. Stop the server process:
   - Click the **Stop Server** button in the Administration section to stop the license manager and the vendor daemon.
   - End the *lmadmin* task process in:
     - Task Manager on Windows
     - Activity Monitor on OS X
     - System Monitor on Linux
3. Uninstall the server with an uninstaller specific to your operating system.

For more information about uninstalling the FlexNet license server, see:

- License Administration Guide. FlexNet Publisher 2020 R2 (11.17.0)[29]
- License Administration Guide. FlexNet Publisher 2019 R2 (11.16.4)[30]
- License Administration Guide. FlexNet Publisher 2014 R1 (11.12.1)[31]

Moving or upgrading the FlexNet license server

Prerequisites

- You have a license key dedicated for a new machine.

⚠ Request a new license key for a new machine from your sales representative. Determine the Host ID/Target ID(see page 20) of the new machine and provide it to sales representative.

27 http://localhost:8090/
28 http://docs.nomagic.com/
29 https://docs.nomagic.com/download/attachments/70388394/fnp_LicAdmin_11_17_0.pdf?api=v2&modificationDate=1611149745747&version=1
30 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11.16.4.pdf?api=v2&modificationDate=1611149745448&version=1
31 https://docs.nomagic.com/download/attachments/70388387/fnp_LicAdmin_11_12_1.pdf?api=v2&modificationDate=1611149745409&version=1

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

To move the FlexNet license server to another machine

1. Uninstall the server(see page 23) from the current machine.
2. Install a new FlexNet(see page 9) server on a new machine.
3. Add a license(see page 19) to the FlexNet server.

To upgrade the FlexNet license server to a new version

1. Uninstall the server(see page 23) from the current machine.
2. Install a new FlexNet(see page 9) server version on the machine.
3. Add a license(see page 19) to the FlexNet server.

Useful commands

- Find out the shared object dependencies in Linux. The result can show what files are missing libraries to run that file.

```
ldd <file_name>
```

- File information in Linux

```
file <file_name>
```

- Launching *lmgrd* manually via command line. *lmgrd*, cameo, and license file must be in the same directory:

```
lmgrd -c <license_file_name> -l <logfile_name>
```

license_file_name - the path to the license file. Can use only the license file name if all files are in the same directory.

logfile_name - the path to the log file. Can use only the license file name if all files are in the same directory. Make sure the files have read/write privileges.

- Checking server status:

```
lmutil lmstat -a -c <server_port>@<server_host_or_ip_address>
```

server_port - the port the server is operating on (Not the cameo daemon port)

server_host_or_ip_address - the host/address the server is hosted on

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

Prior to using the command, locate *lmutil* for a particular OS in the downloaded[32] ***<product folder>*\Flex_Utilities_User_Guides_Vendor_Daemons\<*FlexNet version*>\Server utilities** folder. Navigate to the file via the command line and then execute the command above.

Troubleshooting

On this page

- JRE libraries are missing or not compatible(see page 25)
- No such file or directory running lmadmin(see page 26)
- lmadmin won't start(see page 26)
- 'Can't make directory' error running lmgrd(see page 27)
- You have no permission to install lmadmin in that directory(see page 27)
- A sample script that performs the automated installation of lmadmin 11.14 from nomagic.comhttp://nomagic.com in case you need it for reference purposes(see page 29)

JRE libraries are missing or not compatible

Error message while installing 32-bit *lmadmin* on 64-bit multi-arch Linux system.

The error message is misleading, the solution to fix it, is to install the 32-bit libraries.

In **Redhat/CentOS/Fedora**:

```
sudo yum install redhat-lsb-core.i686
```

In **recent Ubuntu** use:

```
sudo apt-get install libc6-i386
apt-get update
sudo apt-get install lsb-core
```

In **older Ubuntu** use:

32 https://docs.nomagic.com/display/NMDOC/Downloading+installation+files

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

```
sudo dpkg --add-architecture i386
apt-get update
sudo apt-get install libc6:i386 libncurses5:i386 libstdc++6:i386
sudo apt-get install lsb-core
```

No such file or directory running *lmadmin*

That may mean that you are missing the correct Linux Standard Base (LSB) library.

Also, it may mean that you are using a 64-bit executable in a 32-bit system and vice versa.

Install the Linux Standard Base (LSB) libraries to fix it.

libssl.so[33].1.0.0 library required running *lmadmin*

lmadmin 11.17.0 comes with libssl.so[34].* in its installation directory.
You need to add these libraries in *lmadmin* directory to the LD_LIBRARY_PATH.

e.g. if your *lmadmin* installation is at /opt/FNPLicenseServerManager then adding it to the path would look like this:

```
export LD_LIBRARY_PATH=$LD_LIBRARY_PATH:/opt/FNPLicenseServerManager
```

lmadmin won't start

If you install *lmadmin* on a Linux-based system when logged on as root, you may encounter various issues. For example:

- When you try to launch the Web server (http://localhost:port[35]) on the license server, you encounter an "Unable to connect" error.
- When you attempt to run the license server, you may encounter the following errors:

```
  10:43:19 (cameo) Vendor daemon can't talk to lmgrd (Cannot read data from
license server system. (-16,287))
  10:43:20 (cameo) EXITING DUE TO SIGNAL 37 Exit reason 5
```

In Web.log:

33 http://libssl.so
34 http://libssl.so
35 http://localhostport

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

```
[08:08:08 2018] [warn] pid file /opt/FNPLicenseServerManager/logs/
lmadmin.pid overwritten -- Unclean shutdown of previous Apache run?
[08:08:08 2018] [alert] getpwuid: couldn't determine user name from uid
4294967295, you probably need to modify the User directive
```

- A process listing for *lmadmin* ('ps aux | grep *lmadmin*') returns no results.
- A process listing for cameo ('ps aux|grep cameo') returns results if run right after *lmadmin* is started but then fails after a few seconds. If you view the cameo.log file in the logs directory (the default location is /opt/FNPLicenseServerManager/logs), you see that the process failed with the following error messages:

```
 07:55:17 (cameo) Report log started (cameo/report.log).
 07:55:27 (cameo) Vendor daemon can't talk to lmgrd (Cannot read data from
license server system. (-16,287))
 07:55:27 (cameo) EXITING DUE TO SIGNAL 37 Exit reason 5
```

Therefore, when you are installing *lmadmin* on a Linux-based system, it is recommended that you avoid installing as root. If you have already installed *lmadmin* when logged on as root and you do not want to reinstall *lmadmin*, change the ownership of all of the files in the installed folder from root to another user

'Can't make directory' error running *lmgrd*

Can't make directory /usr/tmp/.flexlm, errno: 2(No such file or directory).

This means that directory /usr/tmp used by *lmgrd* is missing on your system (usually on Ubuntu systems). This error does not impact license checkout.

The solution to fix it is to create a symbolic link /usr/tmp pointing to /tmp:

```
ln -s /tmp /usr/tmp
```

You have no permission to install *lmadmin* in that directory

Make sure the *lmadmin* installer has read/write access.

```
chmod 755 lmadmin
```

or

```
chmod -R 755 folder_containing_lmadmin
```

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

to give read/write privileges to all files within a folder.

Then run *lmadmin* using sudo:

```
sudo ./<lmadmin_installer>
```

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

A sample script that performs the automated installation of *lmadmin 11.14 from* nomagic.com[36] in case you need it for reference purposes

A script is intended for CentOS and RedHat

```
#!/bin/bash
echo "==============="
echo "Installing wget"
echo "==============="
sudo yum install -y wget
echo "=================="
echo "Installing lmadmin"
echo "=================="
sudo getent group lmadmin >/dev/null || groupadd -r lmadmin
sudo getent passwd lmadmin >/dev/null || useradd -d /home/lmadmin -g lmadmin -m -r
lmadmin
sudo yum install -y ld-linux.so.2
LSB=$(yum provides /lib/ld-lsb.so.3 | grep lsb-core | tail -1 | cut -f 1 -d ' ')
sudo yum install -y $LSB
sudo echo "lmadmin ALL=(ALL) NOPASSWD:ALL " >> /etc/sudoers
# If Web GUI to Flex licensing is not a must - lmgrd can be used, can be placed in
rc.local to startup on boot
# usage - ./lmgrd -c PATH_TO_KEY_FILE -l PATH_TO_LOG_FILE
# RW rights needed to both files
echo "============================================================"
echo "Getting Linux 32-bit IPv6 version 11.14 from AWS FrontCloud"
echo "============================================================"
wget http://d1g91r27pzl568.cloudfront.net/Cameo_daemon/FlexNet_11_14/ipv6/linux/
lnx_32/cameo
chmod +x cameo
echo "======================================="
echo "Getting Linux 32-bit lmgrd version 11.14"
echo "======================================="
wget https://d1oqhepk9od1tu.cloudfront.net/Flex_License_Server_Utilities/v11.14/
linux32/lmgrd
chmod +x lmgrd
echo "======================================="
echo "Making flex log file named FlexLog.log"
echo "======================================="
touch FlexLog.log
chmod 664 FlexLog.log
echo "=========================================="
echo "Getting Linux 32-bit lmadmin version 11.14"
echo "=========================================="
wget https://d1oqhepk9od1tu.cloudfront.net/Flex_License_Server_Utilities/v11.14/
linux32/lmadmin-i86_lsb-11_14_0_0.bin
chmod +x lmadmin-i86_lsb-11_14_0_0.bin
echo "=========================================="
```

36 http://nomagic.com

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

```
echo "Executing lmadmin version 11.14 installer"
echo "IMPORTANT: Install into directory /opt/local/FNPLicenseServerManager"
echo ""
echo " Note:  Accept all defaults for script to work properly!!!"
read -p -"Press any key to continue ...: " -n1 -s
echo "========================================="
sudo ./lmadmin-i86_lsb-11_14_0_0.bin
sudo mkdir -p /opt/local/FNPLicenseServerManager/licenses/cameo/
sudo cp cameo /opt/local/FNPLicenseServerManager/cameo
sudo mv cameo /opt/local/FNPLicenseServerManager/licenses/cameo/cameo
sudo mv lmgrd /opt/local/FNPLicenseServerManager/lmgrd
sudo mv FlexLog.log /opt/local/FNPLicenseServerManager/FlexLog.log
sudo chown -R lmadmin:lmadmin /opt/local/FNPLicenseServerManager/
sudo chmod +x /opt/local/FNPLicenseServerManager/lib*
sudo cp /opt/local/FNPLicenseServerManager/lib* /usr/lib/
echo "======================"
echo "Opening firewall ports"
echo "======================"
FWZONE=$(sudo firewall-cmd --get-default-zone)
cat <<EOF | sudo tee /etc/firewalld/services/lmadmin.xml
<?xml version="1.0" encoding="utf-8"?>
<service version="1.0">
    <short>lmadmin</short>
    <description>lmadmin</description>
    <port port="8090" protocol="tcp"/>
    <port port="1101" protocol="tcp"/>
</service>
EOF
sleep 5
sudo firewall-cmd --zone=public --remove-port=8090/tcp --permanent
sudo firewall-cmd --zone=public --remove-port=1101/tcp --permanent
sudo firewall-cmd --zone=public --remove-port=27000-27009/tcp --permanent
sudo firewall-cmd --zone=internal --remove-port=8090/tcp --permanent
sudo firewall-cmd --zone=internal --remove-port=1101/tcp --permanent
sudo firewall-cmd --zone=internal --remove-port=27000-27009/tcp --permanent
sudo firewall-cmd --zone=$FWZONE --add-service=lmadmin --permanent
sudo firewall-cmd --reload
IP_ADDRESS=$(ip route get 1 | awk '{print $NF;exit}')
HOSTNAME=$(hostname)
echo "$IP_ADDRESS     $HOSTNAME" >> /etc/hosts
echo "========================================="
echo "Creating systemd service - lmadmin"
echo "========================================="
sudo echo "[Unit]" > /etc/systemd/system/lmadmin.service
sudo echo "Description=Flexnet License Daemon" >> /etc/systemd/system/lmadmin.service
sudo echo "After=network.target network.service" >> /etc/systemd/system/
lmadmin.service
sudo echo "" >> /etc/systemd/system/lmadmin.service
sudo echo "[Service]" >> /etc/systemd/system/lmadmin.service
sudo echo "User=lmadmin" >> /etc/systemd/system/lmadmin.service
sudo echo "WorkingDirectory=/opt/local/FNPLicenseServerManager/" >> /etc/systemd/
system/lmadmin.service
```

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

```
sudo echo "ExecStart=/opt/local/FNPLicenseServerManager/lmadmin -allowStopServer yes"
 >> /etc/systemd/system/lmadmin.service
sudo echo "Restart=always" >> /etc/systemd/system/lmadmin.service
sudo echo "RestartSec=30" >> /etc/systemd/system/lmadmin.service
sudo echo "Type=forking" >> /etc/systemd/system/lmadmin.service
sudo echo "" >> /etc/systemd/system/lmadmin.service
sudo echo "[Install]" >> /etc/systemd/system/lmadmin.service
sudo echo "WantedBy=multi-user.target" >> /etc/systemd/system/lmadmin.service
sudo echo "" >> /etc/systemd/system/lmadmin.service
sudo chown root:root /etc/systemd/system/lmadmin.service
sudo chmod 755 /etc/systemd/system/lmadmin.service
sudo systemctl daemon-reload
sudo systemctl enable lmadmin.service
echo "========================================="
echo "lmadmin service installation complete"
echo "  usage: systemctl start|stop lmadmin"
echo "========================================="
```

If you run into any further problems with installation, please try:

- checking the FAQ section[37] for the known problems
- checking the No Magic Community forum[38]
- contacting customer support[39]

37 http://www.nomagic.com/support/faq.html
38 https://community.nomagic.com/
39 https://docs.nomagic.com/display/NMDOC/Support

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.

L

Lmadmin 6
Lmadmin_run_as_service 6

Copyright © 1998 – 2021 No Magic, Incorporated, a Dassault Systèmes company.