Roundabouts

MCrafterzz edited this page on Sep 13, 2019 · 28 revisions

Roundabouts

Roundabouts are generated procedurally similarly to intersections. For documentation regarding Intersections click this.

Roundabouts

`[Roundabout Radius]` The roundabout radius which defaults to 5. When a road is connected, the max value is determined by the current radius. When all roads are deconnected the max is resetted to 100. This is to prevent the roundabout going through the roads causing strange results.

`[Roundabout Width]` Default value is 2. Changes how wide the roundabout mesh is. Widths are the same as roads, so a 2 wide roundabout is as wide as a 2 wide road.

`[Physics Material]` The physics material used.

`[Y Offset]` Increase this value to make the intersection generate heigher up. This can be used to hide uneven terrain under the intersection. It will create a gap under tho. 0,02 is the default value.

`[Stretch Connection Texture]` Should the connection texture be stretched or repeated? Is false by default which gives the best result for the asphalt intersection. Enable this when for example using the grid intersection texture.

`[Texture Scale]` Has a default value of 1. The x-scale of the texture, change this so that it fits the thickness of the roads' lines.

`[Texture Tiling Y Multiplier]` Default value is one. What should the y repeations be multiplied with? If the value is set to 2 for example the texture will repeat twice as many times. Also affects extra meshes.

`[Resolution Multiplier]` Default value is 1. Multiplies with the global resolution, so use this if you want this specific road to be more or less detailed than the rest.

`[Reset Curve Points On Update]` True is the default value. Determines if the curve positions should be placed automatically or manually.

Materials

`[Base Material]` The base material used. Use one of the included materials or create your own. Default is controlled by Settings.

`[Overlay Material]` Renders above the other material. Default is controlled by Settings.

`[Connection Base Material]` The base material used for the road connection parts. Use one of the included materials or create your own. Default is controlled by Settings.

`[Connection Overlay Material]` Renders above the base connection material. Default is controlled by Settings.

`[Connection Section Material]` Renders above the connection parts of the roundabout, this is what makes the center line go round the whole roundabout and not just between connections. Default is controlled by Settings.

Bridge

`[Generate Bridge]` Is false by default. If true it will generate a bridge that looks like this:



These options are only showed if generate bridge is true:

`[Bridge Materials]` This is a list of materials used for the bridge. The materials overlay eachover. Defaults are controlled by Settings.

`[Y Offset First Step]` Determines how far down the first "step" should be. Default is 0.25.

`[Y Offset Second Step]` Determines how far down the second "step" should be. Default is 0.5.

`[Width Percentage First Step]` Determines how wide the first "step" should be relative to the roads width (extra meshes included). Default is 0.6.

`[Width Percentage Second Step]` Determines how wide the second "step" should be relative to the first step. Default is 0.6.

`[Extra Width]` How much wider should the bridge base be than the road? Default is 0.2

Pillar Placement

This option is only showed if generate bridge is true:

`[Place Pillars]` Should pillars be placed? Default is true

These options are only showed if place pillars is true:

`[Prefab]` The pillar prefab. Default is controlled by Settings.

`[Gap]` The gap between pillars. Defaults to 5.

`[Placement Offset]` The gap between the segments start and the first pillar. Is 5 by default.

`[X Scale]` The X scale of the pillar. 1 is default.

`[Z Scale]` The Z scale of the pillar. Defaults to 1.

`[Rotation Direction]` Determines what direction the pillar is rotated toward. Default is forward, for example, left is towards the roundabout center.

Extra Meshes

`[Outer Extra Meshes Controlled By Roads]` Defaults to false. When true, the outer extra meshes are automatically created every time you generate the roundabout, to match the connected roads. You will not be able to edit those extra meshes or add new ones. The only roundabout extra meshes that you can still control are the center ones (index of 0). This option was added so that you don't have to manually create 5-15 extra meshes and modify them to fit the connected roads.

These options are configured per extra mesh:

`[Index]` Determines where the extra mesh should generate. The default value of 0 will generate it in the center of the roundabout. 1 will generate between road connection one and two. 2 will generate on the left side of the first connection. 3 will generate on the right side. The indexes then continue with those three positions for each connection.

`[Base Material]` The base material of the extra mesh. Default is controlled by Settings.

`[Overlay Material]` The overlay material of the extra mesh. Default is controlled by Settings.

`[Physic Material]` The extra mesh's physic material. Is none by default.

The following two options are only shown if index is set to 0:

`[Start Width]` The start width of the extra mesh. All points will loop between these values depending on how near they are to the end point. Defaults to 1.

`[End Width]` The end width of the extra mesh. Default value is 1.

`[Flipped]` Defaults to false. Should the extra mesh's uvs be flipped? Setting this to true will make the texture's right side be on the outer edge.

The following option is only shown if index isn't 0:

`[Width]` The width of the extra mesh. Default value is 1.

`[Y Offset]` How far up should the extra mesh generate? This is added to the roads y offset so that moving the roads keeps the right proportion. 0 is default.

`[Duplicate Extra Mesh]` Duplicates the extra mesh. Useful when you for example want the same mesh on all connections.

`[Remove Extra Mesh]` Removes the extra mesh.

Buttons

`[Add Extra Mesh]` Adds another extra mesh to the intersection.

`[Reset Curve Points]` Resets the position of the intersection's curve points.

`[Generate Intersection]` Regenerates the intersection mesh. This is done automaticly so this shouldn't be used much.

Pages 12

Tutorials:

- Getting Started/Controls
- Using The Creation Gui
- Using The Tool in SRP

Customization:

- Roads
- Road Segments
- Prefab Lines
- Intersections
- Roundabouts
- Road Systems
- Traffic Lights
- Settings

Report A Bug/Post A Suggestion

Clone this wiki locally

https://github.com/MCrafterzz/ro