# Segments

MCrafterzz edited this page on Sep 13, 2019 · 43 revisions

## Road Segment

Here nearly all your road options are configured. The only exception is the y-offset and smoothness amount that is configured per road and not per segment.

`[Base Road Material]` This is the base texture of the road. A lot are included like the 3 lane asymetrical road and the 4 lane road. The default material is controlled by Settings, if a preset hasen't been used on creation. You can also create your own roads by simply assigning a custom material.

`[Overlay Road Material]` This is the road's second material that is drawn on top of the other one. Default is controlled by Settings.

`[Road Physic Material]` Which physic material should the road have. A physics material determined physic settings such as friction and bounceness. By default no material is selected so you'll have to create your own if you don't want the default unity settings.

`[Start Road Width]` The width of the road in the beggining of the segment. Has a default value of 2.

`[End Road Width]` The width of the road in the end of the segment. The width is lerped between the start and end values so if the start width is 1 and the end width is 2 then the width in the middle would be 1,5. Has a default value of 2.

`[Road Flipped]` Should the road texture be flipped on the x-axis? This is useful when using the 3 lane asymetrical road two determine which direction has 2 lanes. Is false by default.

`[Texture Tiling Y Multiplier]` Multiplies the textures y-tiling value. A higher value makes the texture repeat itself more times and a lower value will make it repeat less times and therefore look more stretched. Default is 1.

The following option will only be shown if generate simple bridge and generate custom bridge are false:

`[Terrain Option]` This determines how the segment should treat terrain. The avaliable options are ignore, adapt and deform. Ignore simply ignores the terrain, use this for bridges. Adapt is the default value makes the road go over the terrain. As the road never will tilt on the x-axis uneven terrain may create gaps. Deform will deform the terrain under if it's a Unity terrain but this isn't yet implemented so at the moment it's the same as ignore.

### Y Offsets

Like road width the values are interpolated between the start and end values. The following options are only showed if terrain option is set to ignore:

`[Left Start Y Offset]` Default is 0. The determines how much the left side of the start of the road should be offseted in the y axis.

`[Left End Y Offset]` Default is 0. The determines how much the left side of the end of the road should be offseted in the y axis.

`[Right Start Y Offset]` Default is 0. The determines how much the right side of the start of the road should be offseted in the y axis.

`[Right End Y Offset]` Default is 0. The determines how much the right side of the end of the road should be offseted in the y axis.

### Bridge

`[Extra Width]` How much wider should the bridge base be than the road? Default is 0.2

`[Generate Simple Bridge]` Defaults to false and when true generates a bridge that looks like this:



These options are only showed if generate simple bridge is true:

`[Bridge Materials]` This is a list of materials used for the bridge. The materials overlay eachover. Default is controlled by Settings.

`[Y Offset First Step]` Determines how far down the first "step" should be. Default is 0.25.

`[Y Offset Second Step]` Determines how far down the second "step" should be. Default is 0.5.

`[Width Percentage First Step]` Determines how wide the first "step" should be relative to the roads width (extra meshes included). Default is 0.6.

`[Width Percentage Second Step]` Determines how wide the second "step" should be relative to the first step. Default is 0.6.

These options are only showed when generate simple bridge or generate custom bridge is set to true:

### Custom Bridge Mesh

`[Generate Custom Bridge]` Determines if a custom bridge should be generated. Is false by default.

These options are only shown if generate custom bridge is true:

`[Bridge Mesh]` The bridge to generate. There are currently 12 bridge meshes included in the package but you can select your own bridge mesh as well. Default is controlled by Settings.

`[Sections]` How many sections should the mesh have or if you prefer, how many times should the mesh repeat itself? Default value is 1.

`[Y Scale]` Determines the height of the bridge. Change it depending on how long each section is so that they are proportional. 1 is the default value.

`[X Offset]` Is 0.3 by default which means that it generates 0.3 units inwards towards the road. If 0 it will generate exactly on the edge of the road which often looks strange. This value can also be negative if you want it to generate outside the road mesh for some reason.

`[Adapt Bridge To Terrain]` Is false by default. When true the lowest vertices of the bridge mesh are moved to ground level. Enable this when using for example the simple arch bridge as it otherwise floats in mid-air.

### Pillar Placement

This option is only shown if generate simple bridge or generate custom bridge is true:

`[Place Pillars]` Determines if pillars should be placed or not. Is true by default.

These options are only shown if place pillars is true:

`[Prefab]` The pillar prefab. Default is controlled by Settings.

This option is only shown if generate custom bridge is true:

`[Adapt To Custom Bridge]` Automatically adapts the gap to the custom bridge mesh so that they always match. It also scales the mesh in the x-axis. Default is false.

The following two options are only shown if generate custom bridge is false or adapt gap to custom bridge is false:

`[Gap]` The gap between pillars. Defaults to 5.

`[Placement Offset]` The gap between the segments start and the first pillar. Is 5 by default.

`[Extra Height]` How much higher should the pillar be than the distance between the ground and the bottom of the bridge mesh. Increase this to avoid the pillars not connection to the bridge mesh on both sides. A too large value will make the pillar go though the top. 0.2 is the default.

This following option is only showed if adapt to custom bridge is false:

`[X Scale]` The X scale of the pillars. Change this to match the bridge mesh. 1 is the default value.

This following option is only showed if adapt to custom bridge is true:

`[X Scale Multiplier]` Determines what the x scale of the pillars should be multiplied with. Change this to match the bridge mesh as the automatic x-scaling system isn't optimal for all pillars, for example the suspension bridge pillar. Defaults to 1.

`[Z Scale]` The Z scale of the pillars. Defaults to 1.

`[Rotation Direction]` Determines which direction the pillars are pointing. Available options are Left, Right, Forward and Backward. Forward is the default one.

### Extra Meshes

These options are configured per extra mesh:

`[Left]` Determines if the extra mesh is on the left or right side of the road. Defaults to true.

`[Base Material]` The base material of the extra mesh. Default is controlled by Settings.

`[Overlay Material]` Determines the overlay material of the extra mesh. Default is controlled by Settings.

`[Physic Material]` The extra mesh's physic material. Is none by default.

`[Start Width]` The start width of the extra mesh. All points will loop between these values depending on how near they are to the end point. Defaults to 1.

`[End Width]` The end width of the extra mesh. Default value is 1.

`[Flipped]` Defaults to false. Should the extra mesh's uvs be flipped? Setting this to true will make the texture's right side be on the outer edge.

`[Y Offset]` How far up should the extra mesh generate? This is added to the roads y offset so that moving the roads keeps the right proportion. 0 is default.

`[Duplicate Extra Mesh]` Duplicates the extra mesh. Useful when you for example want the same mesh on both sides.

`[Remove Extra Mesh]` Removes the extra mesh.

### Buttons

`[Add Extra Mesh]` Adds another extra mesh to the road segment.

`[Detatch Connections]` This will remove the segments connections to intersections. The points will be moved away from the intersection so that they easly can be grabbed.

Pages 12

**Tutorials:**

- Getting Started/Controls
- Using The Creation Gui
- Using The Tool in SRP

**Customization:**

- Roads
- Road Segments
- Prefab Lines
- Intersections
- Roundabouts
- Road Systems
- Traffic Lights
- Settings

Report A Bug/Post A Suggestion

Clone this wiki locally

`https://github.com/MCrafterzz/roa`

© 2021 GitHub, Inc.