AMARE CAPITAL MANAGEMENT

EWMAC Trading System

Exponentially weighted moving average crossover on MetaTrader 5, hosted on AWS EC2

EA v4.14 | Forecast indicator v1.09 | Overlay indicator v1.05

How the EWMAC signal is built

1. Crossover

Fast EMA minus slow EMA of the close

2. Volatility

Divide by the standard deviation of bar changes (50 bars)

3. Forecast

Multiply by the pair scalar, cap at -20 to +20

4. Direction

Above 0 is long, below 0 is short

The EA trades the sign of the forecast. Scalar, volatility window and caps change the displayed value, not the entries.

Six pairs, any timeframe

Pair	Scalar	M5	M15	H1
2/8	10.6	10m / 40m	30m / 2h	2h / 8h
4/16	7.5	20m / 80m	1h / 4h	4h / 16h
8/32	5.3	40m / 2.7h	2h / 8h	8h / 32h
16/64	3.75	1.3h / 5.3h	4h / 16h	16h / 2.7d
32/128	2.65	2.7h / 10.7h	8h / 32h	32h / 5.3d
64/256	1.87	5.3h / 21h	16h / 2.7d	2.7d / 10.7d

Fast / slow EMA span in real time. Periods count bars, so one pair is faster on M5 than on H1.

Trading styles and combinations

Fast

M1 to M5

Pair 4/16 or 8/32

ATR off or 1.5 x 14

Intraday

M15

Pair 8/32 or 16/64

ATR 2.0 x 14

Swing

H1 to H4

Pair 16/64 or 32/128

ATR 3.0 x 14 to 21

Trend

H4 to D1

Pair 32/128 or 64/256

ATR 3 to 4 x 20, or off

Starting points to test on demo, not validated settings. Faster means more trades and more cost drag.

How the EA trades

Stop-and-reverse

Reads the last closed bar on SignalTimeframe

Flip in forecast sign closes one side, opens the other

One position per symbol and magic number

TradeCurrentTrend

True: enter at once in the current direction on attach

False: wait for the next zero cross

Restarts reset memory

Wait for cross

A stop-out or manual close blocks that side

Dashboard shows WAIT CROSS

Trading resumes on the next cross

ATR trailing stop

Distance = ATR x multiplier, on SignalTimeframe.

Initial stop is set at entry.

It trails only after price is one distance in profit, and never moves back.

The stop sits at the broker, so it protects the trade if the server goes offline.

Line style: colour, width, solid, dash or dot, plus a 100-point history path.

Style	Period	Multiple
Tight	7 to 10	1.0 to 1.5
Standard	14	2.0
Wide	14 to 21	3.0
Very wide	20 to 30	4.0+
Off	n/a	n/a

What you can change

Group	Inputs
EWMAC	EWMACPair, SignalTimeframe, WarmupBars, TradeCurrentTrend, StdevWindow, caps, UseCarverScalar
Sizing	FixedLots
ATR trail	UseATRTrail, ATR_Period, ATR_Multiplier, plot, colour, width, style, history
Execution	MagicNumber, SlippagePts
Alerts	SendPush, SendPopup, ShowComment
Indicators	Pair, thresholds (keep 0), ArrowOffsetPts, ShowHUD, HUD_Y

Match indicator timeframe, pair and scalar to the EA.

AWS EC2 and MetaTrader 5

Server

Windows Server base image, free-tier eligible micro

RDP port 3389 from your IP only

Set a billing budget alert

Close the RDP window; never sign out

MetaTrader 5

Install broker MT5, log in with trading password

Tools, Options: allow algo trading

Copy files, compile in MetaEditor

Attach indicators, then the EA with a unique magic number

Mobile access and daily checks

Windows App (iOS, Android)

Add PC, enter the server public IP

User Administrator, then password

Disconnect, never sign out

Allow your phone IP in the security group

Daily check

Algo Trading button green, smiley on chart

Forecast and position agree with the indicator

No repeated BLOCKED lines in Experts log

Free margin comfortable

Trend following loses in ranges. Fixed lots, no drawdown stop. Test before live.