
Nexidia Real-Time Grid Daily Monitoring

Nexidia Real-Time Grid Daily Monitoring Guide

Version 12.5.1

Table of Contents

Copyright

Install the Application Components

Overview

Monitor the RTG Artemis ActiveMQ Message Broker (MB) Service

- Check the Artemis ActiveMQ Message Broker Service

- Check the Message Broker ActiveMQ Web Console

- Check the Artemis ActiveMQ Message Broker logs

Monitor the RTG Telephony Proxy

- Check the Nexidia Real-Time Grid Telephony Proxy Service

- Check the RTG Telephony Proxy Service log

Monitor the RTG Config Service

- Check the Nexidia Real-Time Grid Config Service

- Check the Config Service log

Monitor the RTG Gateway Service

- Check the Nexidia Real-Time Grid Gateway Service

- Check the Gateway Service log

Monitor the RTG Scan Service

- Check the Nexidia Real-Time Grid Scan Service

- Check the Scan Service log

Copyright

PROPRIETARY AND CONFIDENTIAL INFORMATION

Information herein is proprietary information and trade secrets of NICE Ltd. and/or its affiliated companies (Affiliates). This document and the information herein is the exclusive property of NICE and its Affiliates and shall not be disclosed, in whole or in part, to any third party or utilized for any purpose other than the express purpose for which it has been provided.

https://wem-dochub.mindtouch.us/Nexidia_Analytics_and_Data_Exchange_Framework/NXQC_12.5/Grid_Documentati...

Updated: Thu, 30 Apr 2026 18:11:45 GMT

IMPORTANT NOTICE

Subject always to any existing terms and conditions agreed between you and NICE or any Affiliate with respect to the products which are the subject matter of this document, neither NICE nor any of its Affiliates shall bear any responsibility or liability to a client or to any person or entity with respect to liability, loss or damage caused or alleged to be caused directly or indirectly by any product supplied or any reliance placed on the content of this document. This includes, but is not limited to, any interruption of service, loss of business or anticipatory profits or consequential damage resulting from the use or operation of any products supplied or the content of this document. Information in this document is subject to change without notice and does not represent a commitment on the part of NICE or any Affiliate.

All information included in this document, such as text, graphics, photos, logos and images, is the exclusive property of NICE or in Affiliate and is protected by United States and international copyright laws. Permission is granted to use, view and photocopy (or print) materials from this document only in connection with the products to which this document relates and subject to the terms of license applicable to such products. Any other use, copying, distribution, retransmission or modification of the information in this document without the express prior written permission of NICE or an Affiliate is strictly prohibited. In the event of any permitted copying, redistribution or publication of copyrighted material, no changes in, or deletion of, author attribution, trademark legend or copyright notice shall be made.

Products supplied may be protected by one or more of the US patents listed at www.nice.com/Patents. For the full list of trademarks of NICE and its Affiliates, visit www.nice.com/Nice-Trademarks. All other marks used are the property of their respective proprietors.

All contents of this document are: Copyright © 2025 NICE Ltd. All rights reserved.

For assistance, contact your local supplier or nearest NICE Customer Service Center:

EMEA Region (Europe, Middle East, Africa) Tel: +972-9-775-3800 Fax: +972-9-775-3000 email: support@nice.com	APAC Region (Asia/Pacific) Tel: +852-8338-9818 Fax: +852-2802-1800 email: support.apac@nice.com	North America Tel: 1-800-663-5601 Fax: +201-356-2197 email: na_sales@nice.com	International Headquarters- Israel Tel: +972-9-775-3100 Fax: +972-9-775-3070 email: info@nice.com
The Americas Region (North, Central, South America) Tel: 1-800-6423-611 Fax: +720-264-4012 email: support.americas@nice.com	Israel Tel: 09-775-3333 Fax: 09-775-3000 email: support@nice.com	France Tel: +33-(0)1-41-38-5000 Fax: +33-(0)1-41-38-5001	Hong-Kong Tel: +852-2598-3838 Fax: +852-2802-1800
United Kingdom Tel: +44-8707-22-4000 Fax: +44-8707-22-4500	Germany Tel: +49-(0)-69-97177-0 Fax: +49-(0)-69-97177-200		

NICE invites you to join the NICE User Group (NUG).

All queries, comments, and suggestions are welcome! Please email: nicebooks@nice.com.

For more information about NICE, visit www.nice.com

Install the Application Components

Overview

This guide documents how to perform a daily health check on the Nexidia Real-Time Grid (RTG) in a distributed deployment such as the on-demand environment. The reader should have access to the on-demand environment.

Instructions are provided for resolution of basic issues, such as a Windows Service that is not running. To resolve more complicated issues, please consult the appropriate RTG sections of the Nexidia Analytics Troubleshooting Guide at:

<https://www.extranice.com/EIS/ProductDocumentation/Nexidia/Nexidia/Nexidia%20Analytics%20Troubleshooting%20Guide.html>

Monitor the RTG Artemis ActiveMQ Message Broker (MB) Service

Check the Artemis ActiveMQ Message Broker Service

Navigate to Control Panel→Administrative Tools→Services. Verify that the ActiveMQ Artemis: rtg-<version>.mb @ 0.0.0.0 Service is running. If not, start the Windows Service.

If any Service log below contains the following error:

Could not refresh JMS Connection for destination Cause: Failed to create session factory; nested exception is ActiveMQNotConnectedException[errorType=NOT_CONNECTED message=AMQ219007: Cannot connect to server(s). Tried with all available servers.

and the Artemis message broker is running, verify that the timestamp is within 10 seconds or the error is continuously being added to the log, create a Wiser ticket assigned to the Infinity group and attach the appropriate Service log file. If the Artemis message broker is down, start it back up and see if the error persists.

Check the Message Broker ActiveMQ Web Console


The Artemis ActiveMQ Web Console can provide information related to stale client connections that can cause errors in client applications.

1. Open a web browser on the MB VM and navigate to <http://localhost:8161>
2. Log in with user and password
3. Click "Management Console"
4. Click the "addresses" in the left pane.
5. Select the "Queues" tab.


https://wem-dochub.mindtouch.us/Nexidia_Analytics_and_Data_Exchange_Framework/NXQC_12.5/Grid_Documentati...

Updated: Thu, 30 Apr 2026 18:11:45 GMT

6. Search for "Address Contains Updates" as below.



1. Scroll to the bottom of the Queues tab search. In the Filter column, one of the entries will contain a JMSType that does not include "NXRTSAgentId." This is the entry for the NIA Scan Monitoring Service. Select its "attributes" in the "Actions" column.



1. Scroll toward the bottom of the Attributes tab, where you will find Message statistics.
2. A healthy connection to the NIA Scan Monitoring Service will show a "Message count" of 0, and equal values for "Messages acknowledged" and "Messages added."

Check the artemis-service.err.log. The log should be empty or contain only messages logged at WARN level.

There should not be repeated ERROR log messages or exceptions in any of the three logs mentioned above. If these errors appear in the logs, collect all logs in the log directory. Create a new Wiser ticket assigned to the Infinity group and attach the logs to the ticket.

Monitor the RTG Telephony Proxy

Check the Nexidia Real-Time Grid Telephony Proxy Service

Navigate to Control Panel→Administrative Tools→Services. Verify that the Nexidia Real-Time Grid Telephony Proxy Service is running. If not, start the Windows Service.

Check the RTG Telephony Proxy Service log

The RTG Telephony Proxy Service log is located at: C:\ProgramData\Nexidia\Real-Time Grid\encrypted\telephony-proxy\logs\telephony-proxy.log

Some errors may occur occasionally as part of normal operation, such as:

https://wem-dochub.mindtouch.us/Nexidia_Analytics_and_Data_Exchange_Framework/NXQC_12.5/Grid_Documentati...

Updated: Thu, 30 Apr 2026 18:11:45 GMT

```
<c:Value i:type="d:string" xmlns:d="http://www.w3.org/2001/XMLSchema">MBR_MAX_ERROR</c:Value>
```

```
<c:Value i:type="d:string" xmlns:d="http://www.w3.org/2001/XMLSchema">MO_DEFAULT_ERROR</c:Value>
```

Search the log for errors such as the following:

- Error processing Start Call event
- Failed login
- Error reading credentials file
- Invalid client login method

If these errors appear in the log, collect all logs in the log directory. Create a new Wiser ticket assigned to the Infinity group and attach the logs to the ticket.

Monitor the RTG Config Service

Check the Nexidia Real-Time Grid Config Service

Navigate to Control Panel→Administrative Tools→Services. Verify that the Nexidia Real-Time Grid Config Service is running. If not, start the Windows Service.

Check the Config Service log

The RTG Config Service log is located at: C:\ProgramData\Nexidia\Real-Time Grid\encrypted\config\logs\rtgconfig.log

Search the log for errors such as the following:

- Could not access configuration for status

If these errors appear in the log, consult the appropriate section of the Nexidia Analytics Troubleshooting Guide to attempt to resolve the issue. If the troubleshooting steps fail to correct the issue, collect all logs in the log directory. Create a new Wiser ticket assigned to the Infinity group and attach the logs to the ticket.

Monitor the RTG Gateway Service

Check the Nexidia Real-Time Grid Gateway Service

Navigate to Control Panel→Administrative Tools→Services. Verify that the Nexidia Real-Time Grid Gateway Service is running. If not, start the Windows Service.

Check the Gateway Service log

The RTG Gateway Service log is located at: C:\ProgramData\Nexidia\Real-Time Grid\encrypted\gateway\logs\rtggateway.log

Search the log for errors such as the following:

- Currently no scan node is processing the call
- No scan nodes available
- Scan Node <Scan Node GUID identifier> is over capacity.

If these errors appear in the log, consult the appropriate section of the Nexidia Analytics Troubleshooting Guide to attempt to resolve the issue. If the troubleshooting steps fail to correct the issue, collect all logs in the log directory. Create a new Wiser ticket assigned to the Infinity group and attach the logs to the ticket.

Monitor the RTG Scan Service

There will likely be multiple RTG Scan nodes to account for call volume. Please perform the described health checks for each RTG Scan node.

Check the Nexidia Real-Time Grid Scan Service

Navigate to Control Panel→Administrative Tools→Services. Verify that the Nexidia Real-Time Grid Scan Service is running. If not, start the Windows Service.

Check the Scan Service log

The RTG Scan Service log is located at: C:\ProgramData\Nexidia\Real-Time Grid\encrypted\scan\logs\rtgscan.log

Search the log for warnings such as the following:

- Time between packets has exceeded maximum interval

Several (less than 20) of these warnings may appear as part of normal operation. If more than 20 appear in the log, or if recent log entries show the warning occurring repeatedly, it should be considered an error.

Search the log for errors or warnings such as the following:

- Setup of JMS message listener invoker failed for destination
- Could not send status message: The producer is closed
- message=Unknown payload type

If these errors appear in the log, consult the appropriate section of the Nexidia Analytics Troubleshooting Guide to attempt to resolve the issue. If the troubleshooting steps fail to correct the issue, collect all logs in the log directory. Create a new Wiser ticket assigned to the Infinity group and attach the logs to the ticket.