IBM® Security Access Manager for Enterprise Single Sign-On
Version 8.2.1

Policies Definition Guide

SC23-9694-04

IBM® Security Access Manager for Enterprise Single Sign-On
Version 8.2.1

Policies Definition Guide

SC23-9694-04

Note

Before using this information and the product it supports, read the information in "Notices" on page 137.

Edition notice

Note: This edition applies to version 8.2.1 of IBM Security Access Manager for Enterprise Single Sign-On, (product number 5724–V67) and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright IBM Corporation 2002, 2014.
US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this publication v
Access to publications and terminology v
Accessibility viii
Technical training viii
Support information viii
Statement of Good Security Practices ix

Chapter 1. Policies in AccessAdmin. . . 1

Chapter 2. Policy legends 3

Chapter 3. Viewing and setting policy priorities 5
Viewing policy priorities 5
Setting policy priorities 5

Chapter 4. Policies for Authentication Factors 7
Authentication policies 7

Chapter 5. Policies for Password Management. 9
Password aging policies 9
Password change policies. 11
Password strength policies 12

Chapter 6. Policies for Sign up and Password Reset. 15
Self-service password reset policies 15
Self-service registration and bypass of second factor policies 16
Sign up policies 17

Chapter 7. Policies for Configurable Text and Accessibility 21
Configurable text policies. 21
ESSO GINA text policies 21
Unlock text policies. 25
Sign up text policies 34
AccessAssistant and Web Workplace text policies 35
Accessibility policy 35

Chapter 8. Policies for Private and Shared desktops 37
Shared workstation policies 37

Chapter 9. Policies for Citrix and Terminal Server 43
Lightweight mode policy 43

Chapter 10. Policies for Debugging Management and Control. 45
Auditing policies 45
Troubleshooting policies 45
Temporary file policy 47
Log policies 47

Chapter 11. Policies for Wallet and AccessAgent 49
Wallet policies 49
AccessAgent policies 56
Display policies 57
ESSO GINA policies 59
Desktop inactivity policies 63
Lock and Unlock policies. 66
Smart card policies 74
Hybrid smart card policies 75
RFID policies. 79
Fingerprint policies. 85
Terminal Server policies 88
Roaming session policies 94
Log on/Log off policies 95
Hot Key policies 101
Emergency Hot Key policies 105
Audit logging policies 107
Background authentication policies 107
Network policies 108

Chapter 12. Policies for AccessAssistant 111
AccessAssistant and Web Workplace policies . . . 111

Chapter 13. Policies for Applications and Authentication Services 115
Application policies 115
Authentication service policies. 117
Password policies 117
Authentication policies 121

Chapter 14. Policies for ActiveCode 125
ActiveCode policies 125

Chapter 15. Policies for Privileged Identity Management 129
IBM Security Privileged Identity Manager configuration policies. 129

© Copyright IBM Corp. 2002, 2014

Chapter 16. Other policies 133

Chapter 17. Policy limitations in Windows 7 135

Notices 137

Glossary 141
A 141
B 142
C 142
D 143
E 144
F 144
G 144
H 144
I. 145
J. 145
K 145
L 145
M 145
N 146
O 146
P 146
R 147
S 147
T 149
U 149
V 149
W 150

Index 151

About this publication

IBM Security Access Manager for Enterprise Single Sign-On Policies Definition Guide provides detailed descriptions of the different user, machine, and system policies that Administrators can configure in AccessAdmin. Use this guide along with the IBM® Security Access Manager for Enterprise Single Sign-On Administrator Guide.

Access to publications and terminology

This section provides:

- A list of publications in the "IBM Security Access Manager for Enterprise Single Sign-On library."
- Links to "Online publications" on page viii.
- A link to the "IBM Terminology website" on page viii.

IBM Security Access Manager for Enterprise Single Sign-On library

The following documents are available in the IBM Security Access Manager for Enterprise Single Sign-On library:

- *IBM Security Access Manager for Enterprise Single Sign-On Quick Start Guide*, CF3T3ML

  IBM Security Access Manager for Enterprise Single Sign-On Quick Start Guide provides a quick start on the main installation and configuration tasks to deploy and use IBM Security Access Manager for Enterprise Single Sign-On.
- *IBM Security Access Manager for Enterprise Single Sign-On Planning and Deployment Guide*, SC23995206

  IBM Security Access Manager for Enterprise Single Sign-On Planning and Deployment Guide contains information about planning your deployment and preparing your environment. It provides an overview of the product features and components, the required installation and configuration, and the different deployment scenarios. It also describes how to achieve high availability and disaster recovery. Read this guide before you do any installation or configuration tasks.
- *IBM Security Access Manager for Enterprise Single Sign-On Installation Guide*, GI11930904

  IBM Security Access Manager for Enterprise Single Sign-On Installation Guide provides detailed procedures on installation, upgrade, or uninstallation of IBM Security Access Manager for Enterprise Single Sign-On.

  This guide helps you to install the different product components and their required middleware. It also includes the initial configurations that are required to complete the product deployment. It covers procedures for using WebSphere® Application Server Base editions, and Network Deployment.
- *IBM Security Access Manager for Enterprise Single Sign-On Configuration Guide*, GC23969204

  IBM Security Access Manager for Enterprise Single Sign-On Configuration Guide provides information about configuring the IMS Server settings, the AccessAgent user interface, and its behavior.
- *IBM Security Access Manager for Enterprise Single Sign-On Administrator Guide*, SC23995105

© Copyright IBM Corp. 2002, 2014

This guide is intended for the Administrators. It covers the different Administrator tasks. *IBM Security Access Manager for Enterprise Single Sign-On Administrator Guide* provides procedures for creating and assigning policy templates, editing policy values, generating logs and reports, and backing up the IMS Server and its database. Use this guide together with the IBM Security Access Manager for Enterprise Single Sign-On Policies Definition Guide.

- *IBM Security Access Manager for Enterprise Single Sign-On Policies Definition Guide*, SC23969404

  IBM Security Access Manager for Enterprise Single Sign-On Policies Definition Guide provides detailed descriptions of the different user, machine, and system policies that Administrators can configure in AccessAdmin. Use this guide along with the IBM Security Access Manager for Enterprise Single Sign-On Administrator Guide.

- *IBM Security Access Manager for Enterprise Single Sign-On Help Desk Guide*, SC23995304

  This guide is intended for Help desk officers. *IBM Security Access Manager for Enterprise Single Sign-On Help Desk Guide* provides Help desk officers information about managing queries and requests from users usually about their authentication factors. Use this guide together with the IBM Security Access Manager for Enterprise Single Sign-On Policies Definition Guide.

- *IBM Security Access Manager for Enterprise Single Sign-On User Guide*, SC23995005

  This guide is intended for the users. *IBM Security Access Manager for Enterprise Single Sign-On User Guide* provides instructions for using AccessAgent and Web Workplace.

- *IBM Security Access Manager for Enterprise Single Sign-On Troubleshooting and Support Guide*, GC23969303

  IBM Security Access Manager for Enterprise Single Sign-On Troubleshooting and Support Guide provides information about issues with regards to installation, upgrade, and product usage. This guide covers the known issues and limitations of the product. It helps you determine the symptoms and workaround for the problem. It also provides information about fixes, knowledge bases, and support.

- *IBM Security Access Manager for Enterprise Single Sign-On Error Message Reference Guide*, GC14762402

  IBM Security Access Manager for Enterprise Single Sign-On Error Message Reference Guide describes all the informational, warning, and error messages that are associated with IBM Security Access Manager for Enterprise Single Sign-On.

- *IBM Security Access Manager for Enterprise Single Sign-On AccessStudio Guide*, SC23995605

  IBM Security Access Manager for Enterprise Single Sign-On AccessStudio Guide provides information about creating and using AccessProfiles. This guide provides procedures for creating and editing standard and advanced AccessProfiles for different application types. It also covers information about managing authentication services and application objects, and information about other functions and features of AccessStudio.

- *IBM Security Access Manager for Enterprise Single Sign-On AccessProfile Widgets Guide*, SC27444401

  IBM Security Access Manager for Enterprise Single Sign-On AccessProfile Widgets Guide provides information about creating and using widgets.

- *IBM Security Access Manager for Enterprise Single Sign-On Tivoli Endpoint Manager Integration Guide*, SC27562000

IBM Security Access Manager for Enterprise Single Sign-On Tivoli Endpoint Manager Integration Guide provides information about how to create and deploy Fixlets for AccessAgent installation, upgrade or patch management. It also includes topics about using and customizing the dashboard to view information about AccessAgent deployment on the endpoints.

- *IBM Security Access Manager for Enterprise Single Sign-On Provisioning Integration Guide*, SC23995704

  IBM Security Access Manager for Enterprise Single Sign-On Provisioning Integration Guide provides information about the different Java™ and SOAP API for provisioning. It also covers procedures for installing and configuring the Provisioning Agent.

- *IBM Security Access Manager for Enterprise Single Sign-On Web API for Credential Management Guide*, SC14764601

  IBM Security Access Manager for Enterprise Single Sign-On Web API for Credential Management Guide provides information about installing and configuring the Web API for credential management.

- *IBM Security Access Manager for Enterprise Single Sign-On Serial ID SPI Guide*, SC14762601

  IBM Security Access Manager for Enterprise Single Sign-On Serial ID SPI Guide describes how to integrate any device with serial numbers and use it as a second authentication factor with AccessAgent.

- *IBM Security Access Manager for Enterprise Single Sign-On Epic Integration Guide*, SC27562300

  IBM Security Access Manager for Enterprise Single Sign-On Epic Integration Guide provides information about the IBM Security Access Manager for Enterprise Single Sign-On and Epic integration, including supported workflows, configurations, and deployment.

- *IBM Security Access Manager for Enterprise Single Sign-On Context Management Integration Guide*, SC23995404

  IBM Security Access Manager for Enterprise Single Sign-On Context Management Integration Guide provides information about installing, configuring, and testing the Context Management integrated solution in each client workstation.

- *IBM Security Access Manager for Enterprise Single Sign-On AccessAgent on Mobile Guide*, SC27562101

  IBM Security Access Manager for Enterprise Single Sign-On AccessAgent on Mobile Guide provides information about the deployment and use of single sign-on on mobile devices.

- *IBM Security Access Manager for Enterprise Single Sign-On AccessAgent on Virtual Desktop Infrastructure Guide*, SC27562201

  IBM Security Access Manager for Enterprise Single Sign-On AccessAgent on Virtual Desktop Infrastructure Guide provides information about setting up single sign-on support on a Virtual Desktop Infrastructure, and the different user workflows for accessing the virtual desktop.

- *IBM Security Access Manager for Enterprise Single Sign-On AccessAgent on Terminal Server and Citrix Server Guide*, SC27566801

  IBM Security Access Manager for Enterprise Single Sign-On AccessAgent on Terminal Server and Citrix Server Guide provides information about the required configurations and supported workflows in the Terminal and Citrix Servers.

Online publications

IBM posts product publications when the product is released and when the publications are updated at the following locations:

IBM Security Access Manager for Enterprise Single Sign-On library
The product documentation site (http://pic.dhe.ibm.com/infocenter/tivihelp/v2r1/index.jsp?topic=/com.ibm.itamesso.doc_8.2.1/kc-homepage.html) displays the welcome page and navigation for the library.

IBM Security Systems Documentation Central
IBM Security Systems Documentation Central provides an alphabetical list of all IBM Security Systems product libraries and links to the online documentation for specific versions of each product.

IBM Publications Center
IBM Publications Center offers customized search functions to help you find all the IBM publications you need.

IBM Terminology website

The IBM Terminology website consolidates terminology for product libraries in one location. You can access the Terminology website at http://www.ibm.com/software/globalization/terminology.

Accessibility

Accessibility features help users with a physical disability, such as restricted mobility or limited vision, to use software products successfully. With this product, you can use assistive technologies to hear and navigate the interface. You can also use the keyboard instead of the mouse to operate all features of the graphical user interface.

For additional information, see "Accessibility features" in the *IBM Security Access Manager for Enterprise Single Sign-On Planning and Deployment Guide*.

Technical training

For technical training information, see the following IBM Education website at http://www.ibm.com/software/tivoli/education.

Support information

IBM Support provides assistance with code-related problems and routine, short duration installation or usage questions. You can directly access the IBM Software Support site at http://www.ibm.com/software/support/probsub.html.

IBM Security Access Manager for Enterprise Single Sign-On Troubleshooting and Support Guide provides details about:

- What information to collect before contacting IBM Support.
- The various methods for contacting IBM Support.
- How to use IBM Support Assistant.
- Instructions and problem-determination resources to isolate and fix the problem yourself.

Note: The **Community and Support** tab on the product information center can provide additional support resources.

Statement of Good Security Practices

IT system security involves protecting systems and information through prevention, detection and response to improper access from within and outside your enterprise. Improper access can result in information being altered, destroyed, misappropriated or misused or can result in damage to or misuse of your systems, including for use in attacks on others. No IT system or product should be considered completely secure and no single product, service or security measure can be completely effective in preventing improper use or access. IBM systems, products and services are designed to be part of a comprehensive security approach, which will necessarily involve additional operational procedures, and may require other systems, products or services to be most effective. IBM DOES NOT WARRANT THAT ANY SYSTEMS, PRODUCTS OR SERVICES ARE IMMUNE FROM, OR WILL MAKE YOUR ENTERPRISE IMMUNE FROM, THE MALICIOUS OR ILLEGAL CONDUCT OF ANY PARTY.

Chapter 1. Policies in AccessAdmin

IBM Security Access Manager for Enterprise Single Sign-On uses policies to control the behavior of its product components.

The policies are configurable to meet specific organizational requirements. Policies have different visibilities and scopes, and are managed by different roles.

Each policy is identified by its policy ID with *pid* in the prefix. For example, `pid_wallet_authentication_option`.

System, machine, and user policies are configured in AccessAdmin.

Machine policies are typically configured in AccessAdmin. You can also configure machine policies in the Windows registry specially when the `pid_machine_policy_override_enabled` policy is set to **Yes**.

An Administrator can modify system and machine policies in AccessAdmin. A Help desk officer can view system and machine policies only. An Administrator or Help desk officer can modify user policies.



Figure 1. An overview of how different policies are synchronized between client and server in IBM Security Access Manager for Enterprise Single Sign-On.

Scope

The applicability of a policy is determined by scope.

- **System**: The policy is applicable to all users and machines.
- **User**: The policy affects a specific user.
- **Machine**: The policy affects a specific computer.

© Copyright IBM Corp. 2002, 2014

Take note of the following information.

- A policy might be defined for multiple scopes. If this policy is defined for two scopes, set a priority in case the timeout value is different for the computer and the entire system. For more information about setting policy priorities, see Chapter 3, "Viewing and setting policy priorities," on page 5.
- Changes to these policies are propagated to the components the next time AccessAgent synchronizes with the IMS Server.
- User policy, if defined, overrides system policy.

There are three ways to edit user policies in AccessAdmin.

- Search for the user and in the page of the user, go to the appropriate policy section, and update the policy.
- Search for a group of users and in the search result, update the policy, and apply to selected users.
- Update a User Policy Template and apply it to one or more users.

Dependencies

Policies might be dependent on other policies. For example, `pid_enc_hot_key_action` is only effective if `pid_enc_hot_key_enabled` is set to **True**. If the latter is set to **False**, any setting for `pid_enc_hot_key_action` does not affect users. The dependencies are described in the later sections

User-specific policies generally override system-wide policies, but this setting also depends on the policy priority. For example, the Authentication accounts maximum policy (`pid_auth_accounts_max`) has both user and system scopes. The user scope setting is always effective if it is defined. If the user scope setting is not defined for a user, the system scope setting becomes effective.

In general, application-specific policies override authentication service-specific policies, which in turn, override general Wallet policies. The Wallet inject password entry option default policy (`pid_wallet_inject_pwd_entry_option_default`) is used when the other two policies are not defined for a particular authentication service or application. See Chapter 13, "Policies for Applications and Authentication Services," on page 115 for more details.

Chapter 2. Policy legends

Policies can be modified only by Help desk officers and Administrators. Policies affect the behavior of the whole system and must be modified only when it is necessary. These policies must be set at deployment and followed through.

Attribute	Description
✓	Frequently used policies
Policy ID	Unique identifier of the policy.
IMS Entry	The entry in the IMS Server for System and User policies. If this column is blank, the value must be set in the registry. If not, the value indicates the name of the policy, which can be set in the IMS Server.
Description	Description of the policy, including a list of the possible behaviors that are specified by the policy. The product version that implements this policy is also indicated.
Location	Specifies the location of the policy. • For new policies: – **AccessAdmin** > **User Policy Templates** > **New template** > **Create new policy template** – **AccessAdmin** > **Machine Policy Templates** > **New template** > **Create new machine policy template** – **AccessAdmin** > **System** > **System policies** • For existing policies: – **AccessAdmin** > **User Policy Templates** > ***<template name>*** > **Policy template details** – **AccessAdmin** > **Machine Policy Templates** > ***<template name>*** > **Policy template details** – **AccessAdmin** > **System** > **System policies** • For registry entries: – **Registry Editor** > **HKEY_LOCAL_MACHINE** > **SOFTWARE** > **IBM** > **ISAM ESSO**
Registry	The entry in the Windows Registry (for Machine policies) or the IMS Server (for System, User, and Machine policies): • `[DO]` is `[HKEY_LOCAL_MACHINE\SOFTWARE\IBM\ISAM ESSO\DeploymentOptions]` • `[DIMS]` is `[HKEY_LOCAL_MACHINE\SOFTWARE\IBM\ISAM ESSO\IMSService\DefaultIMSSettings]` • `[GIMS]` is `[HKEY_LOCAL_MACHINE\SOFTWARE\IBM\ISAM ESSO\IMSService\GlobalIMSSettings]` • `[T]` is `[HKEY_LOCAL_MACHINE\SOFTWARE\IBM\ISAM ESSO\Temp]`
Type	The data type of this policy in the IMS Server or Windows Registry.
Values	Possible values of the policy. The default value is used if the policy is not specified or if the specified value is not correct.

© Copyright IBM Corp. 2002, 2014

Attribute	Description
Scope	The scope of applicability of the policy. **Values:** • **System**: Policy is system-wide • **Machine**: Policy affects only a specific machine • **User**: Policy affects only a specific user
Note	The refresh frequency is indicated here. This value indicates when a policy will be effective after it is changed. • **Refreshed on use**: Policy that is read from the IMS Server or registry every time it is used. Changes, for example, are effective immediately. • **Refreshed on sync**: Policy that is read from the IMS Server or registry entry only on the next synchronization with the IMS Server. • **Refreshed on logon**: Policy that is read from the IMS Server or registry entry only on the next AccessAgent logon. • **Refreshed on startup**: Policy that is read from the IMS Server or registry entry only on system startup.

Chapter 3. Viewing and setting policy priorities

If a policy is defined for two scopes, define which takes higher priority. Setting the priority is useful in case the timeout value for the policy is different for the two scopes. For example, if the policy priority is machine, then only the machine policy is effective.

Policies can be modified only by Help desk officers and Administrators. These policies affect the behavior of the whole system and must be modified only when it is necessary. These policies are set at deployment and followed through. Changes to these policies are propagated to clients the next time AccessAgent synchronizes with the IMS Server.

Important: Older versions of AccessAgent still use the original policy priorities, and values do not change after you upgrade the IMS Server. To change policy priorities, upgrade all installations of AccessAgent to version 8.0 or later, and then launch the command prompt.

Viewing policy priorities

View the scope and priority of a specific policy so that you can verify the implementation details of a policy.

Before you begin

Run `setupCmdLine.bat` to configure the path to the WebSphere Application Server profile where the IMS Server is installed. Set the value to WAS_PROFILE_HOME.

Procedure

1. Launch the Windows command prompt or Linux/Unix shell.
2. Navigate to the batch file folder. Type `<IMS installation folder>\bin`, then press **Enter**.
3. Type `managePolPriority.bat` or `managePolPriority.sh` to view the information about running the batch file, then press **Enter**.
4. Type `managePolPriority --policyId [name of policy]`, then press **Enter**. The scope and priority of a specific policy are displayed.
5. Type `exit` and then press **Enter**.

Setting policy priorities

Set the priority of a policy so that you can specify which policy is more important.

Procedure

1. Launch the Windows command prompt or Linux/Unix shell.
2. Navigate to the batch file folder. Type `<IMS installation folder>\bin`, then press **Enter**.
3. To change the scope of the policy, enter the following information.

```
managePolPriority
--policyId [name of policy]--scope [scp ims or scp machine] --templateId
[template ID]
```

© Copyright IBM Corp. 2002, 2014

The scope that is given highest priority is assigned a value of `1`, the next scope is assigned with a value of `2`, and so on.

Note: Provide a template ID to specify the assigned template of the machine, user, or system.

4. Press **Enter**.
5. Type `exit` to close the command prompt and then press **Enter**.

Chapter 4. Policies for Authentication Factors

This section provides a list of all policies that you must configure for different authentication factors. Examples of authentication factors are smart cards, hybrid smart cards, RFIDs, and fingerprints.

See “AccessAgent policies” on page 56 for more information about smart card, hybrid smart card, RFID, and fingerprint policies.

See the “Authentication policies” for more details.

Authentication policies

Know the different authentication policies for both user and machine scopes, where to find and set these policies, their descriptions, and their default values.

pid_second_factors_supported_list

IMS Entry	Authentication second factors supported
Location	**AccessAdmin** > **Machine Policy Templates** > **New template** > **Create new machine policy template** > **Authentication Policies**
Description	The second factors that are supported on this computer. This policy also controls the Wallet registration policy and imposes a constraint on the Wallet locks available for logon. **Note:** 1. If there is a GINA or Credential Provider installed, this policy is only updated on computer restart. 2. If there is no GINA or Credential Provider installed, this policy is only updated when a new Windows session is created. For example, when the user logs on to Windows and not when the user unlocks a Windows session. 3. Modifying this policy requires a computer restart to implement the changes.
Registry	
Type	String list MULTI_SZ
Values	• RFID • Smart card • Hybrid smart card • Fingerprint
Scope	Machine
Note	• Currently, only single value is accepted, except for simultaneous Fingerprint and RFID support. • Refreshed on startup.

pid_wallet_authentication_option

IMS Entry	Wallet authentication policy

© Copyright IBM Corp. 2002, 2014

pid_wallet_authentication_option

Location	**AccessAdmin** > **User Policy Templates** > **New template** > **Create new policy template** > **Authentication Policies**
Description	Authentication policy that enforces the combinations of authentication factors that can be used for logon. **Note:** 1. This policy does not enforce the authentication factors that are used for sign-up. The sign-up policy is enforced by `pid_second_factors_supported_list` and `pid_second_factor_for_sign_up_required`. 2. Smart card includes hybrid smart cards. 3. If AccessAgent is deployed without ESSO GINA but with ESSO Network Provider enabled, this policy is ignored.
Registry	
Type	Positive integer list
Values	• #1: Password • #2: Password + RFID • #5: Fingerprint • #6: Smart card
Scope	User
Note	• You can select multiple values. • All values are supported for 32-bit AccessAgent. • Only password and password+RFID are supported for 64-bit AccessAgent. • Refreshed on logon or unlock by different user, if online. • Refreshed on sync.

pid_mac_auth_enabled

IMS Entry	Enable Mobile ActiveCode authentication?
Location	**AccessAdmin** > **User Policy Templates** > **New template** > **Create new policy template** > **Authentication Policies**
Description	Whether Mobile ActiveCode authentication is enabled for the user.
Registry	
Type	Boolean
Values	• #True: Yes • #False: No (default value)
Scope	User
Note	Refreshed on use.

Chapter 5. Policies for Password Management

The Password Management policies contain all the settings to configure for passwords, such as password aging, change, and strength.

For more information:

- "Password aging policies"
- "Password change policies" on page 11
- "Password strength policies" on page 12

Password aging policies

Know the different password aging policies, where to find and set these policies, their descriptions, and their default values. Password aging policies follow the strictest or the most secure policy.

pid_enc_pwd_periodic_change_enabled

IMS Entry	Enable password aging?
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Aging Policies**
Description	Whether to enable password aging? User must do periodic password change.
Registry	
Type	Boolean
Values	• #True: Yes • #False: No (default value)
Scope	System
Note	Refreshed on sync.

pid_enc_pwd_change_days

IMS Entry	Maximum password age, in days
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Aging Policies**
Description	Maximum password age, in days. It is the period between two password changes for a Wallet. **Note:** Effective only if password periodic change is enabled.
Registry	
Type	Positive integer
Values	90 (default value)
Scope	System
Note	Refreshed on sync.

© Copyright IBM Corp. 2002, 2014

pid_enc_pwd_expiry_reminder_enabled

IMS Entry	Enable password change reminder?
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Aging Policies**
Description	Whether to remind the user about the expiring password. **Note:** Effective only if password periodic change is enabled.
Registry	
Type	Boolean
Values	• #True: Yes • #False: No (default value)
Scope	System
Note	Refreshed on sync.

pid_enc_pwd_expiry_reminder_days

IMS Entry	Number of days before password expiry to start reminding user
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Aging Policies**
Description	Number of days before password expiry to start reminding the user. **Note:** This policy is effective only if password expiry reminder is enabled.
Registry	
Type	Non-negative integers
Values	5 (default value)
Scope	System
Note	• Value ranges from 1 to 10. • Refreshed on sync.

pid_enc_pwd_expiry_change_enforced

IMS Entry	Enforce password change on expiry?
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Aging Policies**
Description	Whether to enforce password change on expiry. The user is prompted to change the password before logon to IBM Security Access Manager for Enterprise Single Sign-On. **Note:** Effective only if password periodic change is enabled.
Registry	
Type	Boolean
Values	• #True: Yes • #False: No (default value)
Scope	System
Note	Refreshed on sync.

Password change policies

Know the different password change policies, where to find and set these policies, their descriptions, and their default values.

pid_enc_pwd_reset_option

IMS Entry	Enable password reset?
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Change Policies**
Description	Whether to enable password reset. **Note:** 1. For option 2, the links in the ESSO GINA welcome screen and AccessAgent UI is removed if no user is logged on. 2. The options affect AccessAgent only. AccessAssistant and Web Workplace are not affected by the policy.
Registry	
Type	Non-negative integer
Values	• #1: Enable password reset link (default value) • #2: Disable password reset link
Scope	System
Note	Refreshed on sync.

pid_enc_pwd_change_option

IMS Entry	Enable changing of password?
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Change Policies**
Description	Whether to enable changing of password. **Note:** 1. For option 2, the links in the ESSO GINA welcome screen, ESSO GINA locked screen, AccessAgent UI, and AccessAgent Tray right-click menu are removed. 2. If the password is configured to expire, the user is prompted to change password during logon. 3. If the Active Directory password synchronization is enabled and the Active Directory password expires, the user is prompted to change the password. 4. If change password is forced during initial logon, the user sees the password change prompt upon initial logon. 5. The options affect AccessAgent only. AccessAssistant and Web Workplace are not affected by the policy.
Registry	
Type	
Values	• #1: Enable password change link (default value) • #2: Disable password change link
Scope	System
Note	Refreshed on sync.

pid_enc_pwd_change_on_first_logon_enabled

IMS Entry	Force provisioned users to change the password at first logon?
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Change Policies**
Description	Whether provisioned users are forced to change the ISAM ESSO Password at first logon. **Note:** 1. This policy is only effective for provisioned users and if the ISAM ESSO Passwords are synchronized with the Active Directory passwords. 2. If the ISAM ESSO Passwords are synchronized with the Active Directory passwords, the provisioned users are forced to change passwords according to the Active Directory setting for **User must change password at next logon**. 3. This feature is not supported for fingerprint logon.
Registry	
Type	Boolean
Values	• #True: Yes (default value) • #False: No
Scope	System
Note	Refreshed on logon.

pid_inject_winlogon_password_on_change_disabled

IMS Entry	
Location	**Registry Editor** > **HKEY_LOCAL_MACHINE** > **SOFTWARE** > **IBM** > **ISAM ESSO** > **DeploymentOptions**
Description	Whether to disable the injection of the Windows login password to the Windows Change Password screen. **Note:** This policy is only applicable to Windows 7 and later.
Registry	`[DO] "InjectWinlogonPasswordOnChangeDisabled"`
Type	DWORD
Values	• #0: No (default value) • #1: Yes
Scope	Machine
Note	Refreshed on use.

Password strength policies

Know the different policies for strengthening the password, where to find and set these policies, their descriptions, and their default values. Password strength policies follows the Active Directory password synchronization.

pid_enc_pwd_min_length

IMS Entry	Minimum password length
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Strength Policies**

pid_enc_pwd_min_length

Description	Minimum length of an acceptable password. **Note:** Not effective if Active Directory password synchronization is enabled. Active Directory password strength policies are used instead.
Registry	
Type	Positive integer
Values	6 (default value)
Scope	System
Note	• Value ranges from 1 to 99. • Refreshed on sync.

pid_enc_pwd_max_length

IMS Entry	Maximum password length
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Strength Policies**
Description	Maximum length of an acceptable password. **Note:** Not effective if Active Directory password synchronization is enabled. Active Directory password strength policies are used instead.
Registry	
Type	Positive integer
Values	20 (default value)
Scope	System
Note	• Value ranges from 1 to 99. • Refreshed on sync.

pid_enc_pwd_min_numerics_length

IMS Entry	Minimum number of numeric characters
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Strength Policies**
Description	Minimum number of numeric characters for an acceptable password. **Note:** Not effective if Active Directory password synchronization is enabled. Active Directory password strength policies are used instead.
Registry	
Type	Non-negative integer
Values	0 (default value)
Scope	System
Note	• Value ranges from 0 to 99. • Refreshed on sync.

pid_enc_pwd_min_alphabets_length

IMS Entry	Minimum number of alphabetic characters

pid_enc_pwd_min_alphabets_length

Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Strength Policies**
Description	Minimum number of alphabetic characters for an acceptable password. **Note:** Not effective if Active Directory password synchronization is enabled. Active Directory password strength policies are used instead.
Registry	
Type	Non-negative integer
Values	0 (default value)
Scope	System
Note	• Value ranges from 0 to 99. • Refreshed on sync.

pid_enc_pwd_mixed_case_enforced

IMS Entry	Enforce the use of both upper case and lower case characters?
Location	**AccessAdmin** > **System** > **System policies** > **Password Policies** > **Password Strength Policies**
Description	Whether to enforce the use of both upper case and lower case characters for the password. **Note:** Not effective if Active Directory password synchronization is enabled. Active Directory password strength policies are used instead.
Registry	
Type	Boolean
Values	• #True: Yes • #False: No (default value)
Scope	System
Note	Refreshed on sync.

Chapter 6. Policies for Sign up and Password Reset

Use the sign up and password reset policies to configure the different self-service features, such as sign-up and password reset.

For more information:

- "Self-service password reset policies"
- "Self-service registration and bypass of second factor policies" on page 16
- "Sign up policies" on page 17

Self-service password reset policies

Know the different self-service password reset policies, where to find and set these policies, their descriptions, and their default values.

pid_selfhelp_password_reset_enabled

IMS Entry	Enable self-service password reset?
Location	**AccessAdmin** > **System** > **System policies** > **Self-service Policies** > **Self-service Password Reset Policies**
Description	Whether to enable self-service password reset.
Registry	
Type	Boolean
Values	• #True: Yes • #False: No (default value)
Scope	System
Note	

pid_secrets_register_for_selfhelp_max

IMS Entry	Maximum number of secret questions a user can register to enable self-service
Location	**AccessAdmin** > **System** > **System policies** > **Self-service Policies** > **Self-service Password Reset Policies**
Description	Maximum number of secret questions a user can register to enable self-service
Registry	
Type	Positive integer
Values	3 (default value)
Scope	System
Note	Refreshed on sync.

pid_secrets_verify_for_selfhelp

IMS Entry	The number of secret questions the user must answer to use self-service.

© Copyright IBM Corp. 2002, 2014

pid_secrets_verify_for_selfhelp

Location	**AccessAdmin** > **System** > **System policies** > **Self-service Policies** > **Self-service Password Reset Policies**
Description	The number of secret questions the user must answer to use self-service password reset.
Registry	
Type	Positive integer
Values	2 (default value)
Scope	System
Note	Refreshed on sync.

pid_secrets_verify_invalid_trial_count_max

IMS Entry	The maximum number of invalid login attempts allowed before self-service locks out.
Location	**AccessAdmin** > **System** > **System policies** > **Self-service Policies** > **Self-service Password Reset Policies**
Description	The maximum number of allowed attempts with wrong secret answers before the self-service function is locked.
Registry	
Type	Positive integer
Values	6 (default value)
Scope	System
Note	Refreshed on sync.

Self-service registration and bypass of second factor policies

Know the different self-service registration policies, where to find and set these policies, their descriptions, and their default values.

pid_selfhelp_second_factor_registration_and_bypass_enabled

IMS Entry	Enable self-service registration and bypass of second factor?
Location	**AccessAdmin** > **System** > **System policies** > **Self-service Policies** > **Self-service Registration and Bypass of Second Factor Policies**
Description	Whether to enable self-service registration and bypass of a second factor. **Note:** 1. If this policy is enabled, the user can bypass the use of a second factor for logon by providing registered secrets. 2. If an authorization code is required for the second-factor registration, the user can do a self-service registration by providing registered secrets. 3. If the user cannot provide registered secrets, there is an option to provide an authorization code and the primary secret.
Registry	
Type	Boolean

pid_selfhelp_second_factor_registration_and_bypass_enabled

Values	• #True: Yes • #False: No (default value)
Scope	System
Note	Refreshed on sync.

Sign up policies

Know the different sign up policies, where to find and set these policies, their descriptions, and their default values.

pid_second_factor_for_sign_up_required

IMS Entry	Require authentication second factor during sign up?
Location	**AccessAdmin** > **Machine Policy Templates** > **New template** > **Create new machine policy template** > **Sign Up Policies**
Description	Whether a second factor is required during sign up. **Note:** 1. Enable this policy if a second factor is required during sign up. Second authentication factors that are defined in the user policy template can be implemented only after user registration. 2. Effective only if the second factors supported list is not empty. In this case, any one of the supported second factors can be used for sign up. There is one UI dialog that requests the user to present any one of the supported second factors. 3. If policy value is 1, sign up fails if the second factor is not presented.
Registry	`[DO] "SecondFactorForSignUpRequired"`
Type	DWORD
Values	• #True: Yes • #False: No (default value)
Scope	Machine
Note	Refreshed on use.

pid_automatic_sign_up_enabled

IMS Entry	Enable automatic sign up?
Location	**AccessAdmin** > **Machine Policy Templates** > **New template** > **Create new machine policy template** > **Sign Up Policies**
Description	Whether to enable automatic sign up. **Note:** 1. This policy must be set to 1 if password is synchronized with Active Directory password. 2. `pid_engina_welcome_text` and `pid_unlock_text` must be modified if this policy is set to 1. 3. If this policy is set to 1, the **Sign up** option is not available on both the AccessAgent UI and AccessAgent Tray menu. The user is not prompted to sign up if the user logs on to an unregistered user name. The user is not prompted to confirm sign up if an unregistered second factor is presented.

pid_automatic_sign_up_enabled

Registry	`[DO] "AutomaticSignUpEnabled"`
Type	DWORD
Values	• #True: Yes • #False: No (default value)
Scope	Machine
Note	Refreshed on use.

pid_bind_secret_question_list

IMS Entry	Question set for secret
Location	**AccessAdmin** > **System** > **System policies** > **Sign Up Policies**
Description	The set of questions user can choose from during sign-up to provide the secret answer. **Note:** 1. The system cannot display the entire secret question if it is longer than the screen width. 2. This message is available in multiple languages. It is displayed in the language that is specified by the user during an AccessAgent installation.
Registry	
Type	String list
Values	• Whats your favorite color? • Whats your favorite fruit? • Whats your mother's maiden name? • Who's your favorite author? • Who's your favorite composer? • Who's your favorite person from history?
Scope	System
Note	• You can select multiple values. • Refreshed on sync.

pid_secret_answer_min_length

IMS Entry	Minimum length of an acceptable secret answer
Location	**AccessAdmin** > **System** > **System policies** > **Sign Up Policies**
Description	Minimum length of an acceptable secret answer.
Registry	
Type	Positive integer
Values	3 (default value)
Scope	System
Note	Refreshed on sync.

pid_secrets_register_for_selfhelp_at_sign_up

IMS Entry	Prompt user to register additional secrets for self-service during sign up?
Location	**AccessAdmin** > **System** > **System policies** > **Sign Up Policies**
Description	Whether to prompt the user to register additional secrets for self-service during sign up. **Note:** If `pid_secrets_verify_for_selfhelp` is `1`, the user is not prompted to register more secrets, because the primary secret is sufficient for the self-service actions. The user can still choose to register more secrets after logon by clicking **Set self-service secrets** in AccessAgent.
Registry	
Type	Boolean
Values	• #True: Yes • #False: No (default value)
Scope	System
Note	Refreshed on sync.

pid_secret_option

IMS Entry	Option for specifying secret
Location	**AccessAdmin** > **System** > **System policies** > **Sign Up Policies**
Description	Whether the secret is required, it must be specified by the user during sign up. **Note:** 1. This policy applies to users who are signing up or who are logging on for the first time after their accounts have been pre-provisioned. 2. For policy value `0`, the user is assigned a system-defined secret. The user is not prompted for a secret when performing actions that require it (for example, reset password and offline recovery). The customer must understand the security implications to using a system-defined secret before the implementation of such a configuration. 3. If the policy value is changed from `1` to `0`, the user is automatically migrated to a system-defined secret when the user logs on to AccessAgent successfully. 4. Once the policy value is set to `0` during sign-up, adding a user-defined primary secret later is not supported. You can only add user-defined primary secret during sign-up.
Registry	
Type	Non-negative integer
Values	• #0: Secret not required. • #1: Secret required, and user must specify during sign up. (default)
Scope	System
Note	Refreshed on sync.

Chapter 7. Policies for Configurable Text and Accessibility

This section provides all the policies that you must configure for configurable text and accessibility features. The values in the configurable text policies are stored in multiple languages, depending on the language that is specified by the user during an AccessAgent installation.

For more information:

- “Configurable text policies”
- “Accessibility policy” on page 35

Configurable text policies

View the details of the different configurable text policies. To enter text policies for multiple languages, the Administrator must log on to AccessAdmin multiple times and select a different language each time.

For more information:

- “ESSO GINA text policies”
- “Unlock text policies” on page 25
- “Sign up text policies” on page 34
- “AccessAssistant and Web Workplace text policies” on page 35

ESSO GINA text policies

Know the different configurable text policies for ESSO GINA or Credential Provider, where to find and set these policies, their descriptions, and their default values.

pid_engina_welcome_text

IMS Entry	Welcome message (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text for the ESSO GINA welcome message. **Note:** 1. This message is displayed, followed by a blank line, and then the messages in one of the listed configurable text policies (depending on the list of supported second factors). 2. The two lines of messages are separated by a blank line. 3. "\n\n" can be added if more blank lines are necessary. 4. This message is available in multiple languages. It is displayed in the language that is specified by the user during an AccessAgent installation.
Registry	
Type	String list
Values	This computer is protected by ISAM ESSO AccessAgent. If you are here for the first time, click 'Sign up' to get started.
Scope	System

© Copyright IBM Corp. 2002, 2014

pid_engina_welcome_text

Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_logon_credentials_text

IMS Entry	Logon credentials message (Maximum 1 line)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text that is to be displayed right above the logon credentials when the user clicks **Log on**. **Note:** 1. If `pid_enc_pwd_is_ad_pwd_enabled` is set to **True**, this policy must be modified, for example, `Enter your Windows domain user name and password to log on`. 2. This message is available in multiple languages. It is displayed in the language that is specified by the user during an AccessAgent installation.
Registry	
Type	String list
Values	Enter your user name and password to log on.
Scope	System
Note	• Maximum of 1 string. • Text box takes 2 lines max, about 40 characters per line. • Refreshed on sync.

pid_engina_logon_with_pwd_text

IMS Entry	Instructions for password logon (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text for password logon. **Note:** See `pid_engina_welcome_text`.
Registry	
Type	String list
Values	To log on, click 'Log on'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_engina_logon_with_rfid_text

IMS Entry	Instructions for RFID logon (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text for RFID logon. **Note:** See `pid_engina_welcome_text`.
Registry	
Type	String list
Values	To log on, tap your RFID card. If you do not have your RFID card, click 'Log on'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_engina_logon_with_sc_text

IMS Entry	Instructions for smart card logon (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text for smart card logon. **Note:** See `pid_engina_welcome_text`.
Registry	
Type	String list
Values	To log on, insert your smart card. If you have already inserted your smart card and you are not prompted for a PIN, remove and reinsert your smart card. If you do not have your smart card, click 'Log on'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_engina_logon_with_hsc_text

IMS Entry	Instructions for hybrid smart card logon (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text for hybrid smart card logon.
Registry	
Type	String list

pid_engina_logon_with_hsc_text

Values	To log on, tap your hybrid smart card. If you do not have your hybrid smart card, click 'Log on'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_engina_logon_with_fingerprint_text

IMS Entry	Instructions for fingerprint logon (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text for fingerprint logon. **Note:** See `pid_engina_welcome_text`.
Registry	
Type	String list
Values	To log on, place your registered finger on the sensor. To log on without fingerprint, click 'Log on'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_engina_bypass_automatic_text

IMS Entry	Message for automatic ESSO GINA bypass
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text message for automatic ESSO GINA bypass. **Note:** This message is available in multiple languages. It is displayed in the language that is specified by the user during an AccessAgent installation.
Registry	
Type	String
Values	AccessAgent is currently unable to connect to the IMS Server to log on to your Wallet. You may proceed to log on to Windows but single sign-on is disabled.
Scope	System
Note	Refreshed on sync.

pid_engina_logon_with_fingerprint_or_rfid_text

IMS Entry	Instructions for fingerprint or RFID logon (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **ESSO GINA Text Policies**
Description	Configurable text for fingerprint or RFID logon. **Note:** See `pid_engina_welcome_text`.
Registry	
Type	String list
Values	To log on, place your registered finger on the sensor or tap your RFID card. To log on without fingerprint or RFID card, click 'Log on'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

Unlock text policies

Know the different unlock configurable text policies, where to find and set these policies, their descriptions, and their default values.

pid_unlock_text

IMS Entry	Locked computer message (Maximum 1 line)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for a computer locked message. **Note:** 1. This message is displayed, followed by a blank line, and then messages in one of the configurable unlock text policies (depending on current Wallet and `pid_unlock_option`). 2. The two lines of messages are separated by a blank line. 3. "\n\n" can be added if more blank lines are necessary. 4. This message is available in multiple languages. It is displayed in the language that is specified by the user during an AccessAgent installation.
Registry	
Type	String list
Values	This computer is protected by ISAM ESSO AccessAgent, and has been locked.
Scope	System
Note	• Maximum of 1 string. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_credentials_text

IMS Entry	Unlock credentials message (Maximum 1 line)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text that is to be displayed right above the unlock credentials when the user clicks **Unlock this computer**. **Note:** 1. If Active Directory password synchronization is enabled, this policy must be modified. For example, `Enter your Windows domain user name and password to unlock`. 2. This message is available in multiple languages. It is displayed in the language that is specified by the user during an AccessAgent installation.
Registry	
Type	String list
Values	Enter your user name and password to unlock.
Scope	System
Note	• Maximum of 1 string. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_pwd_option_1_text

IMS Entry	Instructions for unlocking with password when unlock policy is 'only the same user can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a password when the computer is locked and `pid_unlock_option` is 1. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_pwd_option_3_text

IMS Entry	Instructions for unlocking with password when unlock policy is 'any user with or without current desktop account in Wallet can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**

pid_unlock_with_pwd_option_3_text

Description	Configurable text for unlocking with a password when the computer is locked and `pid_unlock_option` is 3. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_pwd_option_4_text

IMS Entry	Instructions for unlocking with password when unlock policy is 'only the same user can unlock, but different user can re-log on to Windows' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a password when the computer is locked and `pid_unlock_option` is 4. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_sc_option_1_text

IMS Entry	Instructions for unlocking with smart card when unlock policy is 'only the same user can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a smart card when the computer is locked and `pid_unlock_option` is 1. **Note:** See `pid_unlock_text`.
Registry	
Type	String list

pid_unlock_with_sc_option_1_text

Values	To unlock, insert your smart card. If you have already inserted your smart card and you are not prompted for a PIN, remove and reinsert your smart card. If you do not have your smart card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_sc_option_3_text

IMS Entry	Instructions for unlocking with smart card when unlock policy is 'any user with or without current desktop account in Wallet can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a smart card when the computer is locked and `pid_unlock_option` is 3. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, insert your smart card. If you have already inserted your smart card and you are not prompted for a PIN, remove and reinsert your smart card. If you do not have your smart card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_sc_option_4_text

IMS Entry	Instructions for unlocking with smart card when unlock policy is 'only the same user can unlock, but different user can re-log on to Windows' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a smart card when the computer is locked and `pid_unlock option` is 4. **Note:** See `pid_unlock_text`.
Registry	
Type	String list

pid_unlock_with_sc_option_4_text

Values	To unlock, insert your smart card. If you have already inserted your smart card and you are not prompted for a PIN, remove and reinsert your smart card. If you do not have your smart card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_hsc_option_1_text

IMS Entry	Instructions for unlocking with hybrid smart card when unlock policy is 'only the same user can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a hybrid smart card when the computer is locked and `pid_unlock_option` is 1. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, tap your hybrid smart card. If you do not have your hybrid smart card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_hsc_option_3_text

IMS Entry	Instructions for unlocking with hybrid smart card when the unlock policy is 'any user with or without current desktop account in Wallet can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a hybrid smart card when the computer is locked and `pid_unlock_option` is 3. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, tap your hybrid smart card. If you do not have your hybrid smart card, click 'Unlock this computer'.
Scope	System

pid_unlock_with_hsc_option_3_text

Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_hsc_option_4_text

IMS Entry	Instructions for unlocking with hybrid smart card when unlock policy is 'only the same user can unlock, but different user can re-log on to Windows' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a hybrid smart card when the computer is locked and `pid_unlock option` is `4`. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, tap your hybrid smart card. If you do not have your hybrid smart card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_rfid_option_1_text

IMS Entry	Instructions for unlocking with RFID when unlock policy is 'only the same user can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with an RFID when the computer is locked and `pid_unlock_option` is `1`. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, tap your RFID card. If you do not have your RFID card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_rfid_option_3_text

IMS Entry	Instructions for unlocking with RFID when unlock policy is 'any user with or without current desktop account in Wallet can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with an RFID when the computer is locked and `pid_unlock_option` is 3. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, tap your RFID card. If you do not have your RFID card, click 'Unlock this computer'.
Scope	System
Note	• Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_rfid_option_4_text

IMS Entry	Instructions for unlocking with RFID when unlock policy is 'only the same user can unlock, but different user can re-log on to Windows' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with an RFID when the computer locked and `pid_unlock_option` is 4. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, tap your RFID card. If you do not have your RFID card, click 'Unlock this computer'.
Scope	System
Note	• Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_fingerprint_option_1_text

IMS Entry	Instructions for unlocking with fingerprint when unlock policy is 'only the same user can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a fingerprint when the computer is locked and `pid_unlock_option` is 1. **Note:** See `pid_unlock_text`.

pid_unlock_with_fingerprint_option_1_text

Registry	
Type	String list
Values	To unlock, place your registered finger on the sensor. To unlock without fingerprint, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_fingerprint_option_3_text

IMS Entry	Instructions for unlocking with fingerprint when unlock policy is 'any user with or without current desktop account in Wallet can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a fingerprint when the computer is locked and `pid_unlock_option` is 3. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, place your registered finger on the sensor. To unlock without fingerprint, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_fingerprint_option_4_text

IMS Entry	Instructions for unlocking with fingerprint when unlock policy is 'only the same user can unlock, but different user can re-log on to Windows' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a fingerprint when the computer is locked and `pid_unlock_option` is 4. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, place your registered finger on the sensor. To unlock without fingerprint, click 'Unlock this computer'.

pid_unlock_with_fingerprint_option_4_text

Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_fingerprint_or_rfid_option_1_text

IMS Entry	Instructions for unlocking with fingerprint or RFID when unlock policy is 'only the same user can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a fingerprint or an RFID when the computer is locked and `pid_unlock_option` is 1. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, place your registered finger on the sensor or tap your RFID card. To unlock without fingerprint or RFID card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_fingerprint_or_rfid_option_3_text

IMS Entry	Instructions for unlocking with fingerprint or RFID when unlock policy is 'any user with or without current desktop account in Wallet can unlock' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a fingerprint or an RFID when the computer is locked and `pid_unlock_option` is 3. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, place your registered finger on the sensor or tap your RFID card. To unlock without fingerprint or RFID card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

pid_unlock_with_fingerprint_or_rfid_option_4_text

IMS Entry	Instructions for unlocking with fingerprint or RFID when unlock policy is 'only the same user can unlock, but different user can relog on to Windows' (Maximum 2 lines)
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Unlock Text Policies**
Description	Configurable text for unlocking with a fingerprint or an RFID when the computer is locked and `pid_unlock option` is `4`. **Note:** See `pid_unlock_text`.
Registry	
Type	String list
Values	To unlock, place your registered finger on the sensor or tap your RFID card. To unlock without fingerprint or RFID card, click 'Unlock this computer'.
Scope	System
Note	• Maximum of 2 strings. • Each text box can contain about 40 characters per line, and contain a maximum of 15 lines. • Refreshed on sync.

Sign up text policies

Know the different sign up configurable text policies, where to find and set these policies, their descriptions, and their default values.

pid_bind_display_template

IMS Entry	Template for sign-up dialog
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **Sign Up Text Policies**
Description	The template to be used for displaying the sign-up dialog. **Note:** 1. The **Domain** field is shown if the enterprise directory is the Active Directory. 2. Other than the domain, the template can support either one or two fields only. To display only one field, set the Label of one of the fields to a blank entry. The field with the blank Label is not displayed.
Registry	
Type	Bind template
Values	Enter your domain user name and password for identity verification. User name Password
Scope	System
Note	Refreshed on sync.

AccessAssistant and Web Workplace text policies

Know the different configurable text policies for AccessAssistant and Web Workplace, where to find and set these policies, their descriptions, and their default values.

pid_accessanywhere_otp_reset_link_text

IMS Entry	Text for the OTP (OATH) reset link on AccessAssistant and Web Workplace.
Location	**AccessAdmin** > **System** > **System policies** > **Configurable Text Policies** > **AccessAssistant and Web Workpace Text Policies**
Description	Configurable text for the OTP (OATH) reset link on AccessAssistant and Web Workplace. **Note:** Effective only if `pid_auth_authentication_option` for `AccessAnywhere` contains `OTP (OATH)`.
Registry	
Type	String
Values	Reset OTP token
Scope	System
Note	Refreshed on sync.

Accessibility policy

Know the policy to enable accessibility features, and where to find and set this policy.

pid_accessibility_is_animation_enabled

IMS Entry	Enable animation?
Location	**AccessAdmin** > **Machine Policy Templates** > **New template** > **Create new machine policy template** > **AccessAgent Policies** > **Accessibility Policies**
Description	Whether to enable or not enable the accessibility features for visually impaired users, including animation effect and jaws-readable screen.
Registry	
Type	Boolean
Values	• #False: No • #True: Yes (default value)
Scope	Machine
Note	