# Mōnandæg v1.2.0

created by k.odk

# Eight takes, one fold

Mōnandæg plays your own recordings through a wave folder. Up to eight takes stand in a row, A to H. At any moment one or two of them are heard, and one or two others are only listened to.

The takes that are heard are **PLAY**. They run through three fold stages in series, and come out bent, bright and broken. The takes that are listened to are **FOLLOW**: you do not hear them as they are; their loudness becomes voltage that pushes the fold — how hard it bends, and where the bends land.

Every take also has a gate of its own. It opens when that take swells past its recent level. The gates are wired into a small network, and when one fires the roles change hands: another take plays, another take steers. So the piece keeps rearranging itself out of the sound itself — nothing has to be sequenced.

Around the fold sit six rooms. FREEZE holds one moment as a chord, BREAK cuts and rewrites the files, LOOP builds a single loop out of pieces of all of them, TEXTURE wears the output like an old tape or a skipping disc, SEND echoes it, and SPEAK has the device read a line of text aloud into a track of its own.

**Too much to learn? Skip it.** Press the metronome key at the top right (BASIC): four takes, one heard, one listening, swapping every couple of seconds. Record a few seconds into A with the record key, press play, and move the three pads. Press BASIC again to go back to where you were.

## Contents


| | |
|---|---|
| 02 | Requirements |
| 03 | The front — keys, takes, pads |
| 04 | The fold and the net |
| 05 | FREEZE — one moment, held |
| 06 | BREAK — cutting the files |
| 07 | LOOP — one loop from many takes |
| 08 | TEXTURE — tape and disc |
| 09 | SEND — echo, room, sweep |
| 10 | SPEAK — a voice and a harmoniser |
| 11 | Recording, files and versions |

# What it needs

Mōnandæg reads up to eight files, folds them four times over-sampled, and runs six rooms in real time. It asks more of the device than a typical app.


## System

| | |
|---|---|
| IOS | iOS 18.0 or later. |
| DEVICE | iPhone and iPad, played in landscape. On iPad the whole instrument fills the screen and every room opens full size. |
| RECOMMENDED | iPhone 13 or newer. Mōnandæg is developed and tested on an iPhone 13. |
| MICROPHONE | Only when you record into a take. |
| FILES | Any audio file you can open from Files can be loaded into a take. |
| VOICES | SPEAK reads with the voices installed on your device. Add more in Settings › Accessibility › Spoken Content › Voices. |
| NETWORK | None. Nothing is sent anywhere. |

## About AUv3

Mōnandæg is a **standalone app**, not an AUv3 plug-in. The microphone and the device's voices are part of the instrument, and a plug-in inside a host cannot use them in the same way.

# Keys, takes, pads FRONT




**KEYS — the rooms**

Snowflake: **FREEZE**. Hammer: **BREAK**. Arrows: **LOOP**. Tape: **TEXTURE**. Dial: **SEND**. Speech bubble: **SPEAK**. A key stays lit while its room is doing something. Beside them, one line says what just happened.

**KEYS — the right**

The curve is the shape of the fold right now; the wave beside it is the output. **REC→A** chooses the take the microphone records into — tap to step A to H. The record key starts and stops. The snowflake freezes: once for the first seat, twice for the second, a third time lets both go. ⇄ swaps the roles now. Play / pause runs the takes. The wind is **DRIFT** — the pads and knobs on the front move by themselves. The metronome is **BASIC**.

**A – H — the takes**

Tap the top of a cell to load a file into it. A letter printed white is **PLAY**, a letter in a white outline is **FOLLOW**; the rest wait. The small square at the right flashes when that take's gate opens. The strip shows the take and the part that is read: drag either edge to move it. The slider is the take's level.

**I · II · III — the fold**

Three fold stages, one after another. **X** is how hard the stage folds — at the left edge it passes untouched and reads OFF. **Y** is the bias: it moves where the folds land, so the same amount sounds different. The readout is the gain and the bias.

**Clearing a take**

Hold the top of a cell for a moment to empty it. The take and its saved recording are removed, and the cell reads EMPTY.

# Who plays, who steers

The panel under the pads shapes the fold; the panel on the right decides which takes are heard, how they are read, and when they change places.


## The fold

| | |
|---|---|
| **SOFT** | How rounded the folds are, and how much the stages are smoothed between them. Low is glassy and hard, high is warm. |
| **SPREAD** | Pulls the two channels apart. |
| **TONE** | A low-pass on the way out. Fully up reads OPEN. |
| **FOLD** | How much of the folded sound against the take as it was. |
| **SPEED** | How fast the takes are read, ×0.25 to ×4. |
| **LEVEL** | The output. |
| **THRESH** | Where a gate opens — a share of the distance between that take's recent peaks and troughs. |
| **EVERY · HOLD** | With CLOCK, how often the roles change (left end: never). With GATE, the shortest time before they may change again. |
| **RANDOM** | How much chance there is in who comes next, where a jump lands and which side it sits. |
| **CV · SHIFT** | How far the first FOLLOW take pushes the fold amount, and how far the second pushes the bias. |
| **FOLLOW** | How quickly the listening follows the loudness — short is jumpy, long is smooth. |

## The net

| | |
|---|---|
| **FILES** | 4, 6 or 8 takes in one net. 2·2 and 4·4 split them into two nets that run side by side, each with its own PLAY and FOLLOW. |
| **ROLE** | One or two PLAY, one or two FOLLOW. **POP**: now and then a short piece of some take sounds and is gone. |
| **READ** | Forward, backward, back and forth, **JUMP** (to a new place at every gate, as far as SCATTER allows) or **STEADY** (just reads, left to right). |
| **NET** | How the gates are wired to each other: RING, CROSS, STAR or ALL. |
| **SWAP** | **CLOCK** changes roles on time, **GATE** when a gate fires. **STAY** holds the line-up; **NOW** changes it at once. |
| **LOCK** | Keeps a passage you like: every 1–16 s it returns to the moment you pressed and plays it again. While it is on, nothing drifts. |
| **SCALE · PITCH** | PITCH turns the folded sound into a pitch movement on the takes, up to ±24 semitones; SCALE snaps it — FREE, 12, PENTA, or octaves and fifths. GLIDE is how long it slides. |
| **FOL VOL** | Lets a little of the FOLLOW takes be heard as they are. |

# One moment, held FREEZE




**Two seats**

1ST and 2ND each catch what is playing in their seat and hold it as a chord. **FREEZE** holds it; **STACK** lays another moment on top (the count shows as LAY). Choose the chord — MIN7, MAJ7, SUS, 5TH and so on — then OCT −, TUNE, OCT + to move it.

**LEVEL** is its volume, **CHORD** how much of the upper voices, **KEEP** how bright it stays, **HARM** an octave above, **TILT** the height of the whole thing, **SHIM** a slow shimmer.


**Both seats**

**FREEZE BOTH** catches both at once. **ROLL** rolls the knobs of both seats (not the level). **GATED** rolls again whenever the sound crosses **OVER**. **DRIFT** lets the knobs wander. **HALT ALL** stops the takes while they are frozen, so only the chord is left. **ALL OFF** lets everything go.

**MOD — four slow movers**

Each row moves one knob. The arrows choose which (a seat's chord or tilt, a pad's X, a fold knob…). **ALT** moves the same knob of the other seat the opposite way. The shape is SINE, TRI, STEP or DRIFT; **SYNC** ties one cycle to one turn of the take. Then RATE, DEPTH and MID (the centre). **ROLL MOD** rolls all four.

# Cutting the files BREAK




BREAK rewrites the file itself, not the way it is played. UNDO keeps the last four steps of each take.

### WHICH FILE

Choose A–H. **DICE** does something to it at random, **REVERSE** turns it round, **CROP TO RANGE** keeps only the part the strip on the front is reading.

### SHATTER — cut and rearrange

**GRAIN** is the size of the pieces (10–800 ms), **MESS** how far they are rearranged, **FLIP** how many are turned backwards, **SPRAY** how thick SCATTER lays them. Then **SHATTER**, **SCATTER**, **STUTTER** or **SPLICE** — which borrows its pieces from the other takes.

### FREEZE CHORD

Takes one moment of the file — **POINT**, or **HERE** for where it is playing — and writes it back as a held chord of the type you choose. **LENGTH** and **BLUR** shape it; **MAKE CHORD** writes it.

### HOLES and TIME

**MANY** and **LONG** punch silences into the file with **MAKE HOLES**. **STRETCH** lengthens or shortens it without changing the pitch; **PITCH** moves the pitch the way tape speed does; **CRUSH** drops bits and samples. Each one is written when you press its button.

# One loop from many takes LOOP




### The loop

One waveform, cut into STEPS (4 to 32). Touch a step — or drag across several — to choose where to write. **LOOP ON** plays this loop instead of the net. **LENGTH** is 0.25 to 16 seconds; changing it keeps what is written.

### Writing into it


**FROM** chooses the take. **TAKE** chooses which part of it: START, MIDDLE, END, the LOUD or QUIET part, an ATTACK, a TAIL, the most TONAL or NOISY part, RANDOM, or HERE (where it is playing now). **SHAPE** changes the piece on the way in: PLAIN, STUTTER, SMEAR, an octave up or down, ECHO, SWELL, CHOP.

**EXTRACT** writes it into the chosen steps and moves on to the next. **INTO STEPS** places pieces step by step; **SCATTER** sprinkles grains across the whole selection (DENSITY, GRAIN). **OVERDUB** adds instead of replacing, **REVERSE** turns the piece round, **RANDOM** fills the loop by itself, **UNDO** takes back the last write, **ALL** selects every step, **CLEAR** empties it.

### EQ, level, fold

**EQ** opens 24 bands that each piece passes through as it is written (FLAT, RANDOM EQ). **LEVEL** and **FOLD** set how loud the loop is and how much it goes through the fold. **INTO** A–H copies the finished loop into a take.

# Tape and disc TEXTURE




An insert on the output. Nothing is recorded; it wears what you hear, the way an old machine would.

### TAPE — transport and oxide

**WOW** and **FLUTTER** are slow and fast unsteadiness of the speed; left and right wobble out of step. **SAT** saturates the oxide, **HISS** lies under it, **DROPOUT** is where the tape loses contact, **HEAD** is a worn head that wears the top off.

### DIGITAL — the needle won't move

**SKIP**, **GRIP**, **CLOSE**, **GAP**, **SEEK**: a player that will not move on — it sticks, repeats and jumps.

### DIGITAL — the disc itself

Damage on the disc: **DEPTH**, **SLIP**, **TURN**, and **WIDE** — how far it is thrown left and right. **STUCK** and **OPEN** are two ready settings; **OFF** takes it away.

### DIGITAL — where the sound goes missing

**STARVE**, **DROP**, **LENGTH**, **CHOKE**, **FADE**, **LOSS**. **LOSS ON / OFF** switches this whole column; **HEAL** fills back what has gone missing.


### GLITCH

Now and then a short effect comes over a take and goes: STUTTER, REVERSE, TAPE STOP, CRUSH, GATE, FREEZE. Choose the takes (A–H or ALL) and the kinds; **OFTEN** is how often. While it acts, its name shows on the take's cell.

### The bottom row

**WORN TAPE** and **CLEAN TAPE** set the tape all at once; **CLEAR DIGITAL** removes every digital fault. **DRIFT** lets the knobs of this room wander, **WANDER** by how much.

# Echo, room, sweep SEND




Three boxes side by side, not in a row. On each, FILES and SPEAK choose what goes in: the folded takes, the spoken voice, or both.

**ECHO — coarser every lap**

**MIX**, **TIME**, **FEED**, **WIDTH**, and **BITS**: each repeat comes back with fewer bits, so it does not fade so much as grain. **SYNC** sets the time to one turn of the first PLAY take. SLAP, TAPE and STEP are ready settings.


**ROOM — four combs, truncated**

**MIX**, **SIZE**, **TAIL**, **DAMP**, **WIDTH**, **BITS**. The tail loses bits every lap and then falls off a cliff. PLATE, HALL, GATE and 12-BIT are ready settings.

**SWEEP — a comb that jumps**

A comb filter that steps through 2 to 32 positions: **MIX**, **DEPTH**, **RATE**, **WIDTH**. **STRAY** now and then lets a take — even a silent one — spill into the boxes, **OFTEN** how often. **DRIFT** lets the knobs wander. **ALL OFF** closes all three.

# A voice and a harmoniser SPEAK




### Text

Type what it will say. **ADD A LINE** adds a line, **CLEAR** empties it, **DONE** closes the keyboard. The next key chooses how it reads: READ ALL, FROM ANY (from anywhere in the text), LINES, or PIECES. Below, the language and the voice — **<** steps back.

### Running it

**SPEAK** speaks the text into the voice track — a track of its own that keeps turning under the takes. **PLAY / STOP** runs it, **HEAD** returns to the start, **LINK** lines its start up with the takes every lap. The next key speaks again by itself — **TIMED** on a time (AUTO) or **GATED** on a gate; **CHORD** rolls the chord too.

The gate row opens the voice only when the fold sounds: choose FOLD I–III or ANY FOLD, then GATE (open while it sounds), TRIG (from the start) or ROLL (somewhere else). **OVER** is how loud it must be.

### Harmoniser

Up to twelve voices, −12 to +12 semitones; the shapes underneath set a chord at once. **ROLL** picks one.

### How it reads

For the next SPEAK: **RATE**, **DETUNE** (cents between voices), **RES** and **RELEASE** (a resonance per voice that rings on after the words), **FREEZE** (the last moment held). **DRIFT** moves these by itself — LIGHT, SOME or ALL.

### The voice track

**LEVEL**, **PAN**, **SPEED**, **SWAY**, **WEAR** (the same damage as the takes), **VOX** (has it spoken again, a little broken), **EVERY** (how often DRIFT moves), **THROW** (scatters where it reads), **AUTO** (how often it speaks again).

# Keeping what you found

**Recording**

REC→A chooses the take; the record key starts and stops. The recording becomes that take and is saved, so it is there the next time you open the app.

**Files**

Takes live in the app's own folder, visible in Files under On My iPhone › Mōnandæg. Copy sound in there and open it into a take; copy takes out to keep them. Deleting the app removes them — there is no cloud copy.

**It keeps playing**

Sound goes on when you switch apps or lock the screen. Stop it with the pause key, from the lock screen, or by closing the app.

**It screams**

Several rooms feed back by design. Pull SEND down first, then the take levels. The limiter at the exit catches peaks but cannot undo a loop that feeds itself.

## Version 1.2.0

**1.2.0** CURRENT
iPhone and iPad, landscape · iOS 18.0 or later. This guide describes this version.

| | |
|---|---|
| **Title** | A title screen on launch, as on the other days. Tap to skip it. |
| **Keys** | Larger keys along the top, easier to hit. |
| **iPad** | Mōnandæg runs on iPad, in landscape and full screen; every room opens full screen with the iPhone layout, scaled up. |

Support · keiodak.github.io/privacy/monandaeg-support.html
Contact · kodk.dev@gmail.com
Newsletter · buttondown.com/kodk

MŌNANDÆG
by k.odk · © k.odk. Sound you make with it is yours.