Mōnandæg v1.2.2

created by k.odk

Eight takes, one fold

Mōnandæg plays your own recordings through a wave folder. Up to eight takes stand in a row, A to H. At any moment one or two of them are heard, and one or two others are only listened to.

The takes that are heard are **PLAY**. They run through three fold stages in series, and come out bent, bright and broken. The takes that are listened to are **FOLLOW**: you do not hear them as they are; their loudness becomes voltage that pushes the fold — how hard it bends, and where the bends land.

Every take also has a gate of its own. It opens when that take swells past its recent level. The gates are wired into a small network, and when one fires the roles change hands: another take plays, another take steers. So the piece keeps rearranging itself out of the sound itself — nothing has to be sequenced.

Around the fold sit six rooms. FREEZE holds one moment as a chord, BREAK cuts and rewrites the files, LOOP builds a single loop out of pieces of all of them, TEXTURE wears the output like an old tape or a skipping disc, SEND echoes it, and SPEAK has the device read a line of text aloud into a track of its own.

Too much to learn? Skip it. Press the metronome key at the top right (BASIC): four takes, one heard, one listening, swapping every couple of seconds. Record a few seconds into A with the record key, press play, and move the three pads. Press BASIC again to go back to where you were.

Contents

02	Requirements
03	The front — keys, takes, pads
04	The fold and the net
05	FREEZE — one moment, held
06	BREAK — cutting the files
07	LOOP — one loop from many takes
08	TEXTURE — tape and disc
09	SEND — echo, room, sweep
10	SPEAK — a voice and a harmoniser
11	Recording, files and versions

What it needs

Mōnandæg reads up to eight files, folds them four times over-sampled, and runs six rooms in real time. It asks more of the device than a typical app.


System

IOS	iOS 18.0 or later.
DEVICE	iPhone and iPad, played in landscape. On iPad the whole instrument fills the screen and every room opens full size.
RECOMMENDED	iPhone 13 or newer. Mōnandæg is developed and tested on an iPhone 13.
MICROPHONE	Only when you record into a take.
FILES	Any audio file you can open from Files can be loaded into a take.
VOICES	SPEAK reads with the voices installed on your device. Add more in Settings › Accessibility › Spoken Content › Voices.
NETWORK	None. Nothing is sent anywhere.

About AUv3

Mōnandæg is a **standalone app**, not an AUv3 plug-in. The microphone and the device's voices are part of the instrument, and a plug-in inside a host cannot use them in the same way.

Keys, takes, pads FRONT



KEYS — the rooms

Snowflake: **FREEZE**. Hammer: **BREAK**. Arrows: **LOOP**. Tape: **TEXTURE**. Dial: **SEND**. Speech bubble: **SPEAK**. A key stays lit while its room is doing something. Beside them, one line says what just happened.

KEYS — the right

The curve is the shape of the fold right now; the wave beside it is the output. **REC→A** chooses the take the microphone records into — tap to step A to H. The record key starts and stops. The snowflake freezes: once for the first seat, twice for the second, a third time lets both go. ⇄ swaps the roles now. Play / pause runs the takes. The wind is **DRIFT** — the pads and knobs on the front move by themselves. The metronome is **BASIC**.

A – H — the takes

Tap the top of a cell to load a file into it. A letter printed white is **PLAY**, a letter in a white outline is **FOLLOW**; the rest wait. The small square at the right flashes when that take's gate opens. The strip shows the take and the part that is read: drag either edge to move it. The slider is the take's level.

I · II · III — the fold

Three fold stages, one after another. **X** is how hard the stage folds — at the left edge it passes untouched and reads OFF. **Y** is the bias: it moves where the folds land, so the same amount sounds different. The readout is the gain and the bias.

Clearing a take

Hold the top of a cell for a moment to empty it. The take and its saved recording are removed, and the cell reads EMPTY.

Who plays, who steers

The panel under the pads shapes the fold; the panel on the right decides which takes are heard, how they are read, and when they change places.


The fold

SOFT	How rounded the folds are, and how much the stages are smoothed between them. Low is glassy and hard, high is warm.
SPREAD	Pulls the two channels apart.
TONE	A low-pass on the way out. Fully up reads OPEN.
FOLD	How much of the folded sound against the take as it was.
SPEED	How fast the takes are read, ×0.25 to ×4.
LEVEL	The output.
THRESH	Where a gate opens — a share of the distance between that take's recent peaks and troughs.
EVERY · HOLD	With CLOCK, how often the roles change (left end: never). With GATE, the shortest time before they may change again.
RANDOM	How much chance there is in who comes next, where a jump lands and which side it sits.
CV · SHIFT	How far the first FOLLOW take pushes the fold amount, and how far the second pushes the bias.
FOLLOW	How quickly the listening follows the loudness — short is jumpy, long is smooth.

The net

FILES	4, 6 or 8 takes in one net. 2·2 and 4·4 split them into two nets that run side by side, each with its own PLAY and FOLLOW.
ROLE	One or two PLAY, one or two FOLLOW. **POP**: now and then a short piece of some take sounds and is gone.
READ	Forward, backward, back and forth, **JUMP** (to a new place at every gate, as far as SCATTER allows) or **STEADY** (just reads, left to right).
NET	How the gates are wired to each other: RING, CROSS, STAR or ALL.
SWAP	**CLOCK** changes roles on time, **GATE** when a gate fires. **STAY** holds the line-up; **NOW** changes it at once.
LOCK	Keeps a passage you like: every 1–16 s it returns to the moment you pressed and plays it again. While it is on, nothing drifts.
SCALE · PITCH	PITCH turns the folded sound into a pitch movement on the takes, up to ±24 semitones; SCALE snaps it — FREE, 12, PENTA, or octaves and fifths. GLIDE is how long it slides.
FOL VOL	Lets a little of the FOLLOW takes be heard as they are.

One moment, held FREEZE



Two seats

1ST and 2ND each catch what is playing in their seat and hold it as a chord. **FREEZE** holds it; **STACK** lays another moment on top (the count shows as LAY). Choose the chord — MIN7, MAJ7, SUS, 5TH and so on — then OCT −, TUNE, OCT + to move it.

LEVEL is its volume, **CHORD** how much of the upper voices, **KEEP** how bright it stays, **HARM** an octave above, **TILT** the height of the whole thing, **SHIM** a slow shimmer.


Both seats

FREEZE BOTH catches both at once. **ROLL** rolls the knobs of both seats (not the level). **GATED** rolls again whenever the sound crosses **OVER**. **DRIFT** lets the knobs wander. **HALT ALL** stops the takes while they are frozen, so only the chord is left. **ALL OFF** lets everything go.

MOD — four slow movers

Each row moves one knob. The arrows choose which (a seat's chord or tilt, a pad's X, a fold knob…). **ALT** moves the same knob of the other seat the opposite way. The shape is SINE, TRI, STEP or DRIFT; **SYNC** ties one cycle to one turn of the take. Then RATE, DEPTH and MID (the centre). **ROLL MOD** rolls all four.

Cutting the files BREAK



BREAK rewrites the file itself, not the way it is played. UNDO keeps the last four steps of each take.

WHICH FILE

Choose A–H. **DICE** does something to it at random, **REVERSE** turns it round, **CROP TO RANGE** keeps only the part the strip on the front is reading.

SHATTER — cut and rearrange

GRAIN is the size of the pieces (10–800 ms), **MESS** how far they are rearranged, **FLIP** how many are turned backwards, **SPRAY** how thick SCATTER lays them. Then **SHATTER**, **SCATTER**, **STUTTER** or **SPLICE** — which borrows its pieces from the other takes.

FREEZE CHORD

Takes one moment of the file — **POINT**, or **HERE** for where it is playing — and writes it back as a held chord of the type you choose. **LENGTH** and **BLUR** shape it; **MAKE CHORD** writes it.

HOLES and TIME

MANY and **LONG** punch silences into the file with **MAKE HOLES**. **STRETCH** lengthens or shortens it without changing the pitch; **PITCH** moves the pitch the way tape speed does; **CRUSH** drops bits and samples. Each one is written when you press its button.

One loop from many takes LOOP



The loop

One waveform, cut into STEPS (4 to 32). Touch a step — or drag across several — to choose where to write. **LOOP ON** plays this loop instead of the net. **LENGTH** is 0.25 to 16 seconds; changing it keeps what is written.

Writing into it


FROM chooses the take. **TAKE** chooses which part of it: START, MIDDLE, END, the LOUD or QUIET part, an ATTACK, a TAIL, the most TONAL or NOISY part, RANDOM, or HERE (where it is playing now). **SHAPE** changes the piece on the way in: PLAIN, STUTTER, SMEAR, an octave up or down, ECHO, SWELL, CHOP.

EXTRACT writes it into the chosen steps and moves on to the next. **INTO STEPS** places pieces step by step; **SCATTER** sprinkles grains across the whole selection (DENSITY, GRAIN). **OVERDUB** adds instead of replacing, **REVERSE** turns the piece round, **RANDOM** fills the loop by itself, **UNDO** takes back the last write, **ALL** selects every step, **CLEAR** empties it.

EQ, level, fold

EQ opens 24 bands that each piece passes through as it is written (FLAT, RANDOM EQ). **LEVEL** and **FOLD** set how loud the loop is and how much it goes through the fold. **INTO** A–H copies the finished loop into a take.

Tape and disc TEXTURE



An insert on the output. Nothing is recorded; it wears what you hear, the way an old machine would.

TAPE — transport and oxide

WOW and **FLUTTER** are slow and fast unsteadiness of the speed; left and right wobble out of step. **SAT** saturates the oxide, **HISS** lies under it, **DROPOUT** is where the tape loses contact, **HEAD** is a worn head that wears the top off.

DIGITAL — the needle won't move

SKIP, **GRIP**, **CLOSE**, **GAP**, **SEEK**: a player that will not move on — it sticks, repeats and jumps.

DIGITAL — the disc itself

Damage on the disc: **DEPTH**, **SLIP**, **TURN**, and **WIDE** — how far it is thrown left and right. **STUCK** and **OPEN** are two ready settings; **OFF** takes it away.

DIGITAL — where the sound goes missing

STARVE, **DROP**, **LENGTH**, **CHOKE**, **FADE**, **LOSS**. **LOSS ON / OFF** switches this whole column; **HEAL** fills back what has gone missing.


GLITCH

Now and then a short effect comes over a take and goes: STUTTER, REVERSE, TAPE STOP, CRUSH, GATE, FREEZE. Choose the takes (A–H or ALL) and the kinds; **OFTEN** is how often. While it acts, its name shows on the take's cell.

The bottom row

WORN TAPE and **CLEAN TAPE** set the tape all at once; **CLEAR DIGITAL** removes every digital fault. **DRIFT** lets the knobs of this room wander, **WANDER** by how much.

Echo, room, sweep SEND



Three boxes side by side, not in a row. On each, FILES and SPEAK choose what goes in: the folded takes, the spoken voice, or both.

ECHO — coarser every lap

MIX, **TIME**, **FEED**, **WIDTH**, and **BITS**: each repeat comes back with fewer bits, so it does not fade so much as grain. **SYNC** sets the time to one turn of the first PLAY take. SLAP, TAPE and STEP are ready settings.


ROOM — four combs, truncated

MIX, **SIZE**, **TAIL**, **DAMP**, **WIDTH**, **BITS**. The tail loses bits every lap and then falls off a cliff. PLATE, HALL, GATE and 12-BIT are ready settings.

SWEEP — a comb that jumps

A comb filter that steps through 2 to 32 positions: **MIX**, **DEPTH**, **RATE**, **WIDTH**. **STRAY** now and then lets a take — even a silent one — spill into the boxes, **OFTEN** how often. **DRIFT** lets the knobs wander. **ALL OFF** closes all three.

A voice and a harmoniser SPEAK



Text

Type what it will say. **ADD A LINE** adds a line, **CLEAR** empties it, **DONE** closes the keyboard. The next key chooses how it reads: READ ALL, FROM ANY (from anywhere in the text), LINES, or PIECES. Below, the language and the voice — **<** steps back.

Running it

SPEAK speaks the text into the voice track — a track of its own that keeps turning under the takes. **PLAY / STOP** runs it, **HEAD** returns to the start, **LINK** lines its start up with the takes every lap. The next key speaks again by itself — **TIMED** on a time (AUTO) or **GATED** on a gate; **CHORD** rolls the chord too.

The gate row opens the voice only when the fold sounds: choose FOLD I–III or ANY FOLD, then GATE (open while it sounds), TRIG (from the start) or ROLL (somewhere else). **OVER** is how loud it must be.

Harmoniser

Up to twelve voices, −12 to +12 semitones; the shapes underneath set a chord at once. **ROLL** picks one.

How it reads

For the next SPEAK: **RATE**, **DETUNE** (cents between voices), **RES** and **RELEASE** (a resonance per voice that rings on after the words), **FREEZE** (the last moment held). **DRIFT** moves these by itself — LIGHT, SOME or ALL.

The voice track

LEVEL, **PAN**, **SPEED**, **SWAY**, **WEAR** (the same damage as the takes), **VOX** (has it spoken again, a little broken), **EVERY** (how often DRIFT moves), **THROW** (scatters where it reads), **AUTO** (how often it speaks again).

Keeping what you found

Recording

REC→A chooses the take; the record key starts and stops. The recording becomes that take and is saved, so it is there the next time you open the app.

Files

Takes live in the app's own folder, visible in Files under On My iPhone › Mōnandæg. Copy sound in there and open it into a take; copy takes out to keep them. Deleting the app removes them — there is no cloud copy.

It keeps playing

Sound goes on when you switch apps or lock the screen. Stop it with the pause key, from the lock screen, or by closing the app.

It screams

Several rooms feed back by design. Pull SEND down first, then the take levels. The limiter at the exit catches peaks but cannot undo a loop that feeds itself.

Version 1.2.0

1.2.0
iPhone and iPad, landscape · iOS 18.0 or later.

Title	A title screen on launch, as on the other days. Tap to skip it.
Keys	Larger keys along the top, easier to hit.
iPad	Mōnandæg runs on iPad, in landscape and full screen; every room opens full screen with the iPhone layout, scaled up.

Support · keiodak.github.io/privacy/monandaeg-support.html
Contact · kodk.dev@gmail.com
Newsletter · buttondown.com/kodk

MŌNANDÆG
by k.odk · © k.odk. Sound you make with it is yours.

Keeping a whole session

The PRESET room

The tray key along the top opens one room with everything for keeping what you found. Its key lights while a WAV is recording, or while RING, FM or AT END is on.

Twelve presets

Hold a slot to store it: every setting, and the files loaded in A–H with their ranges and names. Press a stored slot to bring all of it back — the takes in A–H are replaced by the preset's. CLEAR SLOT, then a slot, empties it.

WAV

Type a file name, press ● REC, press ■ STOP. What you hear is written as a 24-bit WAV to Files › On My iPhone › Mōnandæg › Recordings. Without a name, the date is used. Recording carries on when the room is closed.

CLEAR ALL FILES

Empties A–H in one go. Press it twice. To empty one take on the front, hold the top of its cell.

Cross — RING and FM

RING multiplies each take by the others that are sounding. FM bends each take's reading speed with the others' sound, up to three octaves either way.

FADE and AT END

FADE is how long one take takes to give way to the next, from 0.01 to 8 seconds (it starts at 0.035, as before). AT END → NEXT moves on when the playing take reaches the end of its range; NEXT NOW moves on at once.

Opening empty

Mōnandæg now opens with A–H empty, ready for your own sounds. The test-tone key still fills them.

Version 1.2.2

1.2.2 CURRENT

iPhone and iPad, landscape · iOS 17.0 or later. This guide describes this version.

PRESET	Twelve slots that keep the settings and the files in A–H.
WAV	Name, REC, STOP — the output as a 24-bit WAV in Files.
FADE	RING and FM between the takes; fade length; AT END → NEXT.
Clear	CLEAR ALL FILES empties A–H in one go.
Start	Opens empty.
iOS 17	Now runs on iOS and iPadOS 17.