- 1.Topológia kábelezése
- 2.soho router konfigurálása
- 3.laptop dhcp szórás
- 4.Budapest:
- -enable conf t int se0/0/0 ip add 192.168.230.1 no sh clock rate 2000000
- 5. Sopron:
- -enable conf t int se0/0/0 ip add 192.168.230.2 255.255.255.0 no sh exit int g0/0 ip add 192.168.240.1 255.255.255.0 no sh
- 6. S-SW:
- -enable conf t- hostname S-SW no ip domain-lookup banner motd 'szöveg' enable secret enaSopron -line con 0 password conSopron login int vlan 1 ip add 192.168.240.2 255.255.255.0 exit ip default-getaway 192.168.240.1 line vty 0 15 -password vtySopron login logging synhronous exit service password-encryption int g0/1 description Router fele exit do wri
- 7. S2 PC konfigurálása
- 8. másik switch név BP-SW
- 9. BP-SW:
- enable conf t int range fa0/1-24 switchport mode access switchport port-security switchport port-security mac-address sticky switchport port-security max 2 switchport portsecurity violation sh exit -int range fa0/3-12 shutdown int range fa0/15-24 shutdown exit
- hostname BP-SW vlan 210 name KETTOTIZES exit vlan 220 name KETTOHUSZAS exit -
- -int range fa0/1-12 switchport access vlan 210 exit int range fa0/13-24 switchport access vlan 220 exit int g0/1 switchport mode trunk
- 10. Budapest
- -enable conf t int g0/0.210 encapsulation dot1Q 210 ip add 192.168.210.1 255.255.255.0 exit int g0/0.220 encapsulation dot1Q 220 ip add 192.168.220.1 255.255.255.0 exit ip dhcp exluded-address 192.168.210.1 192.168.210.5 ip dhcp exluded-address 192.168.220.1 192.168.220.5 ip dhcp pool KETTOTIZES network 192.168.210.0 255.255.255.0 dns-server 209.165.201.10 default-router 192.168.210.1 exit ip dhcp pool KETTOHUSZAS network 192.168.220.0 255.255.255.0 dns-server 209.165.201.10 default-router 192.168.220.1 exit
- 11. BP-PCk dhcp szórás
- 12. Sopron
- enable conf t ip route  $0.0.0.0 \ 0.0.0.0$  serial 0/0/1 router rip version 2 passive-interface g0/0 default-information originate network 192.168.230.0 network 192.168.240.0
- 13. Budapest

- enable - conf t – router rip – version 2 – network 192.168.210.0 – network 192.168.220.0 – network 192.168.230.0

## 14. Sopron

- enable – conf t – ip nat inside source static  $192.168.240.2\ 209.165.200.3$  – int ser0/0/1 – ip nat outside – int s0/0/0 – ip nat inside – int g0/0 – ip nat inside – access-list 1 permit  $192.168.210.0\ 0.0.0.255$  - access-list 1 permit  $192.168.220.0\ 0.0.0.255$  - access-list 1 permit  $192.168.240.0\ 0.0.0.255$