

Land Claim Setup Reference

Staff Guide for Command Block Configuration

Overview

This guide walks Server Admins and Head Admins through the complete process of setting up land claims using command blocks across all three dimensions: Overworld, Nether, and End. When a player purchases a claim and receives coordinates from their ticket, you'll use this reference to build the three-block protection system. Players can hold up to 9 claims total across all dimensions.

The Claim Workflow

1. **Player submits ticket** with claim purchase (Overworld, Nether, or End)
2. **Scoreboard updated** for the claim
3. **Claim documented** (limit: 9 total across all dimensions)
4. **Coordinates issued** in ticket (X,Z to X,Z format)
5. **You build the command blocks** using this guide

Understanding Coordinate Differences (DX, DY, DZ)

Minecraft uses a "difference" system for command target selectors. Instead of specifying two corners, you specify a starting corner and a *difference* (distance) from that corner.

The Formula

If your starting coordinate is **A** and your ending coordinate is **B**:

Starting Point = The lower/minimum number

Difference = Ending number – Starting number

Example Scenarios

Scenario	Starting Point	Difference	Range
Positive to Positive	100	100	100 to 200
Negative to Negative	-6000	500	-6000 to -5500
Negative to Positive	-100	300	-100 to +200

The Three-Block System

All land claims use exactly three command blocks. Each serves a specific purpose in protecting the claim. All three command blocks are placed in the Overworld in an always-ticking area, but they use **/execute in** to protect claims in other dimensions.

Block 1: Title/Warning (Purple Block)

Type: Repeating, Unconditional, Always Active

Tick: 10

Purpose: Displays a warning message when players approach the claim boundary

Detection Area: 50-block buffer zone around the actual claim

Block 2: Bounce Warning (Green Block)

Type: Chain, Unconditional, Always Active

Tick: 0

Purpose: Sends a message to players entering the protected area

Detection Area: Exact claim boundary

Block 3: Teleport (Green Block)

Type: Chain, Unconditional, Always Active

Tick: 0

Purpose: Teleports unauthorized players to a safe bounce location

Detection Area: Exact claim boundary

Bounce Location: Admin-chosen, suggested within the warning buffer but outside the claim

Overworld Protection (250×250 Max)

Overworld claims are limited to 250×250 blocks. The command blocks operate normally without dimension targeting.

Setting Up the Commands

Step 1: Calculate Your Coordinates

You receive coordinates from the ticket in this format:

X1, Z1 to X2, Z2

Example: **-200, -300 to 300, 200**

Step 2: Build Block 1 (Warning System)

The warning block needs a 50-block buffer around your claim. This means you'll **expand your coordinates by 50 blocks in all directions**.

Example with claim -200, -300 to 300, 200:

```
Original coordinates: X1 = -200, Z1 = -300, X2 = 300, Z2 = 200
Expand by 50: New X1 = -250, New Z1 = -350, New X2 = 350, New Z2 = 250
  X = -250, DX = 600 (350 - (-250) = 600)
  Z = -350, DZ = 600 (250 - (-350) = 600)
  Y = 0, DY = 400 (always)
```

Block 1 Command:

```
title @a[tag=!TownTag,x=X,dx=DX,y=0,dy=400,z=Z,dz=DZ] actionBar $dYou're
approaching [TownName]
```

Replace:

X = Your calculated starting X (e.g., -250)

DX = Your calculated difference X (e.g., 600)

Z = Your calculated starting Z (e.g., -350)

DZ = Your calculated difference Z (e.g., 600)

[TownName] = The actual town name from the ticket

Step 3: Build Block 2 (Bounce Warning) & Block 3 (Teleport)

Blocks 2 and 3 use the **original, exact coordinates** from the ticket—**no expansion, no modification**.

Using the same example claim (-200, -300 to 300, 200):

```
X = -200, DX = 500 (300 - (-200) = 500)
Z = -300, DZ = 500 (200 - (-300) = 500)
Y = 0, DY = 300 (always 0 to 300)
```

Block 2 Command (Warning):

```
/w @a[tag=!TownTag,x=X,dx=DX,y=0,dy=300,z=Z,dz=DZ] You have been teleported away
from [TownName]
```

Block 3 Command (Teleport):

```
/tp @a[tag=!TownTag, x=X, dx=DX, y=0, dy=300, z=Z, dz=DZ] [BounceX] [BounceY] [BounceZ]
```

Note: Replace [BounceX], [BounceY], [BounceZ] with the safe coordinates you choose within the warning area.

Nether Protection (32×32 Claims)

Nether claims are limited to 32×32 blocks. The command blocks are still placed in the Overworld, but use **/execute in nether** to protect the Nether claim. Y-coordinates in the Nether typically range from 0–128.

Understanding /execute in

The **/execute in nether** subcommand changes the dimension context, allowing command blocks in the Overworld to protect areas in the Nether. This is essential for multi-dimensional claim management.

Step 1: Receive Nether Coordinates

You receive a separate ticket with Nether coordinates in this format:

X1, Z1 to X2, Z2

Example: **500, 100 to 532, 132** (32×32 claim)

Step 2: Build Block 1 (Warning) with /execute in

Expand the claim by 50 blocks in all directions for the warning buffer.

Example with Nether claim 500, 100 to 532, 132:

Original: X1 = 500, Z1 = 100, X2 = 532, Z2 = 132

Expand by 50: New X1 = 450, New Z1 = 50, New X2 = 582, New Z2 = 182

X = 450, DX = 132 (582 – 450)

Z = 50, DZ = 132 (182 – 50)

Y = 0, DY = 128 (full Nether height)

Block 1 Command (Nether):

```
/execute in nether run title @a[tag=!TownTag,x=X,dx=DX,y=0,dy=128,z=Z,dz=DZ]  
actionbar $dYou're approaching [TownName] (Nether)
```

Step 3: Build Block 2 & 3 (Exact Boundaries) with /execute in

Use original, exact coordinates—no expansion.

Using exact claim coordinates (500, 100 to 532, 132):

X = 500, DX = 32 (532 – 500)

Z = 100, DZ = 32 (132 – 100)

Y = 0, DY = 128 (full Nether height)

Block 2 Command (Nether Warning):

```
/execute in nether run /w @a[tag=!TownTag,x=X,dx=DX,y=0,dy=128,z=Z,dz=DZ] You have  
been teleported away from [TownName] (Nether)
```

Block 3 Command (Nether Teleport):

```
/execute in nether run /tp @a[tag=!TownTag,x=X,dx=DX,y=0,dy=128,z=Z,dz=DZ] [BounceX]  
[BounceY] [BounceZ]
```

Note: [BounceX], [BounceY], [BounceZ] are Nether coordinates—pick a safe spot within the warning buffer.

End Protection (100×100 Claims)

End claims are limited to 100×100 blocks. Like Nether claims, command blocks are in the Overworld but use **/execute in the_end** to protect the End claim. Y-coordinates in the End typically range from 0–256.

Step 1: Receive End Coordinates

You receive a separate ticket with End coordinates in this format:

X1, Z1 to X2, Z2

Example: **-50, -50 to 50, 50** (100×100 claim)

Step 2: Build Block 1 (Warning) with /execute in the_end

Expand the claim by 50 blocks in all directions for the warning buffer.

Example with End claim -50, -50 to 50, 50:

Original: X1 = -50, Z1 = -50, X2 = 50, Z2 = 50

Expand by 50: New X1 = -100, New Z1 = -100, New X2 = 100, New Z2 = 100

X = -100, DX = 200 (100 - (-100))

Z = -100, DZ = 200 (100 - (-100))

Y = 0, DY = 256 (full End height)

Block 1 Command (End):

```
/execute in the_end run title @a[tag=!TownTag,x=X,dx=DX,y=0,dy=256,z=Z,dz=DZ]  
actionbar $dYou're approaching [TownName] (End)
```

Step 3: Build Block 2 & 3 (Exact Boundaries) with /execute in the_end

Use original, exact coordinates—no expansion.

Using exact claim coordinates (-50, -50 to 50, 50):

X = -50, DX = 100 (50 - (-50))

Z = -50, DZ = 100 (50 - (-50))

Y = 0, DY = 256 (full End height)

Block 2 Command (End Warning):

```
/execute in the_end run /w @a[tag=!TownTag,x=X,dx=DX,y=0,dy=256,z=Z,dz=DZ] You have  
been teleported away from [TownName] (End)
```

Block 3 Command (End Teleport):

```
/execute in the_end run /tp @a[tag=!TownTag,x=X,dx=DX,y=0,dy=256,z=Z,dz=DZ]  
[BounceX] [BounceY] [BounceZ]
```

Note: [BounceX], [BounceY], [BounceZ] are End coordinates—pick a safe spot within the warning buffer.

Common Mistakes (And How to Avoid Them)

Mistake #1: Using Expanded Coordinates for Blocks 2 & 3

- **Wrong:** Calculating a 50-block buffer for all three blocks
- ✓ **Right:** Use the buffer ONLY for Block 1. Blocks 2 & 3 are exact.

Mistake #2: Forgetting to Account for Negative Numbers

- **Wrong:** Starting with the positive number when both positive and negative exist
 - ✓ **Right:** Always start with the **lower/minimum number**, even if it's negative.
- Example: Between -100 and +200, start with -100 (not +200).

Mistake #3: Wrong DY for Dimension

- **Wrong:** Using DY=400 for all dimensions
- ✓ **Right:** Overworld Block 1 = 400, Overworld Blocks 2/3 = 300. Nether = 128. End = 256.

Mistake #4: Forgetting /execute in for Nether/End

- **Wrong:** Using regular target selectors without /execute in for Nether/End claims
- ✓ **Right:** Always wrap Nether/End commands with /execute in nether or /execute in the_end

Mistake #5: Wrong Town Name in Message

- **Wrong:** Copying a generic message without replacing [TownName]
- ✓ **Right:** Use the exact town name from the ticket. Include dimension indicator if helpful.

Troubleshooting

Players aren't seeing warnings in Nether/End

- Check:** Does the command start with /execute in nether or /execute in the_end?
- Check:** Are the coordinates in the correct dimension scale?
- Check:** Is Block 1 set to Repeating and Always Active?

Players aren't being teleported from Nether/End

- Check:** Is Block 3 wrapped with /execute in nether or /execute in the_end?
- Check:** Are the bounce coordinates in the correct dimension?
- Check:** Is Block 3 a Chain connected to Block 2?

Math doesn't seem right after calculation

- Solution:** Double-check your starting point. It should **always be the lower number**.
- Helpful check:** Add your starting coordinate + difference. You should get your ending coordinate.

Commands are bouncing wrong dimension

Check: Are you using the correct /execute in statement?

Nether: **/execute in nether run ...**

End: **/execute in the_end run ...**

Overworld: No /execute in needed

Dimension Quick Reference

Dimension	Max Size	Block 1 DY	Blocks 2/3 DY	Execute Command	Y Range
Overworld	250×250	400	300	N/A	0–255
Nether	32×32	128	128	/execute in nether run	0–128
End	100×100	256	256	/execute in the_end run	0–256

Last Updated: June 24, 2026 | Honeydew Homes SMP | All Dimensions Supported