



Using the Legacy Production Configuration Page

Version 2026.1
2026-04-20

Using the Legacy Production Configuration Page

PDF generated on 2026-04-20

InterSystems IRIS Version 2026.1

Copyright © 2026 InterSystems Corporation

All rights reserved.

InterSystems®, HealthShare Care Community®, HealthShare Unified Care Record®, InterSystems IRIS® IntegratedML®, InterSystems Caché®, InterSystems Ensemble®, InterSystems HealthShare®, InterSystems IRIS®, InterSystems IRIS® for Health, and TrakCare are registered trademarks of InterSystems Corporation. HealthShare® Health Connect Cloud™, InterSystems® Data Fabric Studio™, and InterSystems Supply Chain Orchestrator™ are trademarks of InterSystems Corporation. TrakCare is a registered trademark in Australia and the European Union.

All other brand or product names used herein are trademarks or registered trademarks of their respective companies or organizations.

This document contains trade secret and confidential information which is the property of InterSystems Corporation, One Congress Street, Boston, MA 02114, or its affiliates, and is furnished for the sole purpose of the operation and maintenance of the products of InterSystems Corporation. No part of this publication is to be used for any other purpose, and this publication is not to be reproduced, copied, disclosed, transmitted, stored in a retrieval system or translated into any human or computer language, in any form, by any means, in whole or in part, without the express prior written consent of InterSystems Corporation.

The copying, use and disposition of this document and the software programs described herein is prohibited except to the limited extent set forth in the standard software license agreement(s) of InterSystems Corporation covering such programs and related documentation. InterSystems Corporation makes no representations and warranties concerning such software programs other than those set forth in such standard software license agreement(s). In addition, the liability of InterSystems Corporation for any losses or damages relating to or arising out of the use of such software programs is limited in the manner set forth in such standard software license agreement(s).

THE FOREGOING IS A GENERAL SUMMARY OF THE RESTRICTIONS AND LIMITATIONS IMPOSED BY INTERSYSTEMS CORPORATION ON THE USE OF, AND LIABILITY ARISING FROM, ITS COMPUTER SOFTWARE. FOR COMPLETE INFORMATION REFERENCE SHOULD BE MADE TO THE STANDARD SOFTWARE LICENSE AGREEMENT(S) OF INTERSYSTEMS CORPORATION, COPIES OF WHICH WILL BE MADE AVAILABLE UPON REQUEST.

InterSystems Corporation disclaims responsibility for errors which may appear in this document, and it reserves the right, in its sole discretion and without notice, to make substitutions and modifications in the products and practices described in this document.

For Support questions about any InterSystems products, contact:

InterSystems Worldwide Response Center (WRC)

Tel: +1-617-621-0700

Tel: +44 (0) 844 854 2917

Email: support@InterSystems.com

Table of Contents

1 Introduction to the Legacy Production Configuration Page	1
1.1 Displaying the Production Configuration Page	1
1.2 The Update Button	2
1.3 Controlling the Display	2
1.3.1 Filtering the Display by Category	2
1.3.2 Sorting Business Hosts	2
1.3.3 Choosing a View Type	3
1.3.4 Controlling the Refresh	4
1.3.5 Hiding the Settings Pane	4
1.4 Understanding the Color Coding	4
1.5 Accessing Management Options	5
1.6 See Also	5
2 Creating a Production (Legacy UI)	7
2.1 Creating a Production	7
2.2 Opening a Production	7
2.3 Exporting a Production	8
2.4 Generating Production Documentation	8
2.5 Deleting a Production	9
2.6 See Also	9
3 Adding Business Hosts (Legacy UI)	11
3.1 Introduction	11
3.2 Configuration Names	11
3.3 Adding Business Hosts to a Production	12
3.4 Business Service Wizard	12
3.5 Business Process Wizard	13
3.6 Business Operation Wizard	14
3.7 See Also	15
4 Modifying Business Hosts (Legacy UI)	17
4.1 Enabling, Disabling, or Restarting a Business Host	17
4.2 Changing the Class That a Business Host Uses	18
4.3 Copying a Business Host	18
4.4 Deleting a Business Host	19
4.5 Repairing an Error	19
4.6 Viewing and Configuring Connections	19
4.7 Working with Multiple Versions of a Business Host	20
4.8 See Also	20
5 Configuring Settings (Legacy UI)	23
5.1 Configuring Settings	23
5.2 Color Coding	24
5.3 Searching for a Setting	24
5.4 Getting Help for Settings	24
5.5 Restoring a Setting to Its Default Value	24
5.6 See Also	25

1

Introduction to the Legacy Production Configuration Page

Note: Starting with 2025.1, you can use a [new integrated application](#) to configure productions (and also edit rule sets and DTL data transformations).

To create and configure interoperability productions, you use the Production Configuration page, introduced here.


1.1 Displaying the Production Configuration Page

To display the Production Configuration page:

1. Log in to the Management Portal.
2. Switch to the namespace you want to work in.
3. Click **Interoperability > Configure > Production**.

This page then displays the currently selected production (if any) in that namespace.

For example, the following figure shows a sample production.



The main area of the page displays the production, and the Settings tab on the left displays settings relevant to the currently selected item, as well as additional tabs that provide easy access to management options.

If you click **Production Settings** above the diagram, the options apply to the entire production. Similarly, if you click a business host, the options apply to that business host.

1.2 The Update Button

While you are developing new code and configuring the production, it sometimes happens that when you start the Management Portal, InterSystems IRIS detects a discrepancy between the production as defined in the code, and the status of the running production. Examples would be if:

- A specific business host experienced an error and has died (the most likely cause).
- You changed a configuration parameter for a business host in a running production, such that the host now needs to be restarted.
- You enabled or disabled an item in a production, and this action requires the production to be stopped and restarted.
- A production typically opens a Terminal window, but this window was closed by a user action while the production was still running.


When such discrepancies occur, the **Update** button appears on the **Production Configuration** page. If you click the button, InterSystems IRIS updates the production to resolve the discrepancy. If you prefer for the system to attempt to resolve the discrepancy automatically, you can add a business service based on the `Ens.ProductionMonitorService` class to the production. For more information, see [Using the Production Monitor Service](#).

1.3 Controlling the Display

This section describes how to [filter](#) the display, [sort](#) the display, how to display alternative [views](#) of the production, how to control the [refresh](#) of the display, and how to [hide](#) the production or business host settings.

1.3.1 Filtering the Display by Category

To filter the business hosts in the production diagram, use the **Category** list.




Select a value from this list. When you do so, the diagram display only those business hosts that have been assigned to the given category. Or click **All** to view all the business hosts in the production.

Note that a business host can be assigned to multiple categories.

For details, see [Category](#) in the reference [Settings in All Productions](#).

1.3.2 Sorting Business Hosts

To sort the business hosts in the production diagram, use the **Sort** options:



- **Name**—Sorts items alphabetically within each column.

- **Status**—Sorts items within each column by status as follows: disabled, enabled, error, inactive.
- **Number**—Sorts items as listed in the production class (which, by default, represents the order in which they were added to the production). To modify this order, you can edit the production class in an IDE.

1.3.3 Choosing a View Type

To view the business hosts in a different way, use the **View** options:



These view types are as follows:

- The **listing view**  displays the business hosts in lists, within the **Services**, **Processes**, and **Operations** columns. If the name of a business host is truncated due to the width of the columns, you can hover over the business host to view its full name.

The listing view is used in most of the documentation.


Production Running			Category: All	Legend	Production Settings
Services	Processes	Operations			
● Demo.Loan.BankMetrics ● Demo.Loan.FindRateCSPService ● Demo.Loan.FindRateEmailService ● Demo.Loan.FindRateFileService ● Demo.Loan.FindRateMQSeriesService ● Demo.Loan.FindRateMSMQService ● Demo.Loan.FindRateTCPService ● Demo.Loan.FindRateTerminalService	● Demo.Loan.BankEven ● Demo.Loan.BankManana ● Demo.Loan.BankSoprano ● Demo.Loan.BankUS ● Demo.Loan.FindRateDecisionProcessBPL ● Demo.Loan.FindRateDecisionProcessCustor	● Demo.Loan.FindRateEmailOperation ● Demo.Loan.FindRateFileOperation ● Demo.Loan.FindRateMQSeriesOperation ● Demo.Loan.FindRateMSMQOperation ● Demo.Loan.FindRateTCPOperation ● Demo.Loan.WebOperations ● My Terminal Output			

- The **monitor view**  represents each business host in a larger circle where you can easily see items that may need attention. Here, click a circle to see a box with details for the business host.

Production Running			Category: All	Legend	Production Settings
Services	Processes	Operations			
  	  	  			
  	  	  			
 					

-  The *service bus view* is relevant only if you configure [business partners](#) and enter values in the **Business Partner** setting.

This view displays the business hosts grouped by their associated business partners.



1.3.4 Controlling the Refresh

Click the circular arrow to refresh the diagram once or click **on** to reload a fresh copy of the production diagram every 60 seconds; the refresh timer is **off** by default.

Note that InterSystems IRIS checks the status of individual business hosts (on a shorter interval) and refreshes the display for individual hosts as needed, regardless of the setting of auto-refresh.

1.3.5 Hiding the Settings Pane

Click the **Hide Settings Tabs** icon  to hide the production or business host settings.

1.4 Understanding the Color Coding

When in list or monitor [view](#), the **Production Configuration** page displays a circular status indicator next to each business host. The color of this circle indicates the state of the business host, as follows:

- Pale green means that the business host is enabled but is not running.
- Dark green means that the business host is running.
- Gray means that the business host is disabled.
- Red means that the business host is in an error state.
- Purple means that the business host is retrying its activity.
- Yellow means that the business host is inactive.

The page includes the **Legend** link, which you can use to display this information.

Note: You can increase the visibility of the error states by specifying that the Error, Retry and Inactive states are to be indicated by a colored ellipse, not a circle. To do this append &VISUALAID=1 to the URL for the Production Configuration page.

1.5 Accessing Management Options

The Production Configuration page includes tabs that provide easy access to management options.

These management tabs are as follows:

- **Queue**—Click to view a list of the queues related to this production or business host.
- **Log**—Click to view an abbreviated list of Event Log entries for this production or business host.
- **Messages**—Click to view an abbreviated list of messages processed by this production or business host.
- **Jobs**—Click to view jobs related to this production or business host.

Each of these tabs provides a link to a management page (which opens in a new window) with more information; see [Managing Productions](#).

On the **Jobs** tab, you can also manage active jobs; see [Aborting Messages](#), [Suspending Messages](#), and [Stopping Jobs](#).

1.6 See Also

- [Introduction to Configuration Tasks](#)
- [Creating a Production \(Legacy UI\)](#)
- [Managing Productions](#)
- [Monitoring Productions](#)

2

Creating a Production (Legacy UI)

This page describes how to use the [legacy Production Configuration page](#) to create, open, export, generate documentation for, and delete productions.

For information on performing these tasks with the new UI, see [Creating a Production](#).

Note: If a production is Suspended or Troubled, see [Correcting Production Problem States](#).

2.1 Creating a Production

To create a production:

1. Display the [Production Configuration page](#).
2. Select **New** to create a new production.
3. Enter a **Package Name**, **Production Name**, and **Description**.
4. Choose **Generic** production.
5. Click **OK**.
6. Now you can [add business hosts](#) and [configure them](#).

2.2 Opening a Production

To open a production:

1. If you are not already in an interoperability-enabled namespace, choose your working namespace from the available interoperability-enabled namespaces.
2. Navigate to the **Interoperability > List > Productions** page, and then select **Go**, if necessary.
3. Select **Open** to open an existing production.

To open a production or create a new production when you currently configuring a production on the **Production Configuration** page:

1. If you have clicked anywhere within the diagram, click **Production Settings**.

Production Settings

This step returns the focus to the production and changes the options on the **Actions** tab.

2. Select the **Actions** tab.
3. Select **Open** on the **Actions** tab to open an existing production or select **New** on the same tab to create a new production.

2.3 Exporting a Production

To export a production from the **Production Configuration** page:

1. If you have clicked anywhere within the diagram, click **Production Settings** in the right-hand pane.
This step returns the focus to the production and changes the options on the **Actions** tab.
2. Click **Export** on the **Actions** tab.
3. Select items to export.
4. Click **Export**.
5. Select whether you want to export the production to the server or to your local machine via the browser's downloading capability.
6. If you are exporting to the server, enter a path and name of the export file. If you are downloading to your local machine via the browser, enter the name of the export file.
7. Click **OK**.

See [Deploying a Production](#) for details on exporting and deploying a production.

2.4 Generating Production Documentation

You can navigate to the **Production Documentation** page from the following places in the Management Portal:

- From the **Interoperability > List > Productions** page, select a production name and click **Document**.
- From the **Interoperability > Configure > Production** page, on the **Actions** tab for the production, click **Document**.

From the **Production Documentation** page for a production, you can generate or view the production documentation, which includes a list of all the business hosts and their settings. Perform one of the following actions:

- Click **View** to display the online documentation you previously generated. If you click **View** and no HTML documentation exists, you can choose to generate it.
- Click **Generate** to create new documentation for this production using a background job.

It may take a considerable amount of time to generate documentation for large productions; therefore, you may not want to generate new documentation if you have not made changes to the configuration of your production.

- **Cancel** to cancel the operation.

You can also generate HTML documentation and, additionally, PDF documentation using the following methods in the `Ens.Config.Production` class:

- **CreateDocumentHTML()**—creates new documentation in HTML format.

For example, to create documentation for Demo.Loan.FindRateProduction in HTML format:

ObjectScript

```
Set
status=##class(Ens.Config.Production).CreateDocumentHTML("Demo.Loan.FindRateProduction",1,.URL,.ErrLog)
```

- **RemoveDocumentHTML()**—removes existing HTML-format documentation from the current namespace.
- **CreateDocumentPDF()**—creates new documentation as a PDF file.

For example, to create documentation for Demo.Loan.FindRateProduction in PDF format, you can use the method in a statement similar to the following:

ObjectScript

```
Set
status=##class(Ens.Config.Production).CreateDocumentPDF("Demo.Loan.FindRateProduction",1,"C:\Temp\Rate.pdf",.Log)
```

The PDF format requires that you have a PDF renderer installed. It also requires Java.

2.5 Deleting a Production

To delete a production:

1. Navigate to the **Interoperability > List > Productions** page.
2. Click the production that you want to delete.
3. Click **Delete**.
4. Click **OK**.

2.6 See Also

- [Introduction to the Legacy Production Configuration Page](#)
- [Adding Business Hosts \(Legacy UI\)](#)
- [Modifying Business Hosts \(Legacy UI\)](#)
- [Configuring Settings \(Legacy UI\)](#)
- [Deploying a Production](#)

3

Adding Business Hosts (Legacy UI)

This topic describes how to use the [legacy Production Configuration page](#) to add business hosts to a production.

For information on performing these tasks with the new UI, see [Adding Business Hosts](#).

3.1 Introduction

A business host is any business service, business process, or business operation within a production. These are also referred to generically as *configuration items*.

A configuration item is always associated with a specific production. It may resemble or duplicate items in other productions. Each production is an entirely closed universe that does not use configuration items from other productions.

3.2 Configuration Names

By default, the *name* of a configuration item is the name of its underlying host class. However, you can assign a different name, to describe the purpose of the item, for example.

For example, if you have a business service class that communicates with a specific type of server, and you use it to communicate with the same *type* of server in different enterprise *locations*, you must configure the business service with different settings to communicate with each enterprise location, even though the type of server is the same. Each different configuration of the business service must have a different *Name* in the diagram (except see [Working with Multiple Versions of a Business Host](#)).

The following rules govern configuration names:

- The name must consist of at least one character.
- The name can contain letters, numbers, and any printable character except for the following:
| ; , : [< > \ / & "
- Neither the first nor the last character can be any of the following: ! \$.
- The first character cannot be _
- The name (if is it one character long) cannot be *

Important: You cannot change the name of an existing configuration item. If you require a name change, you can [copy](#) the item and [delete](#) the original item.

3.3 Adding Business Hosts to a Production

To add a business host to a production:

1. Identify (or create and compile) the appropriate business host class.
2. Open the production on the **Interoperability > Configure > Production** page.
3. Click plus-sign icon next to the **Services, Processes, or Operations** column heading.
4. Use the wizard; the details are different for the [Business Service Wizard](#), the [Business Process Wizard](#), and the [Business Operation Wizard](#).
5. Click **OK** to add the process to the production.
6. Configure the business process as needed.

This process does not generate any new classes. It updates the production class.

3.4 Business Service Wizard

The Business Service Wizard provides multiple tabs, which correspond to different types of business service classes to use. Click a tab and then specify values as follows:

- If you click the **All Services** tab, specify the following values:
 - Choose a host class from the **Service Class** list. If the class you need is not listed, create and compile the class in an IDE, and then return here to choose it.
 - Specify a configuration **Service Name**. For rules, see [Configuration Names](#).
 - Enter a text label in the **Display Category** field to sort and organize items within the production. **Display Category** names are case-sensitive, and space characters are allowed. To place an item in multiple categories, list them in the **Display Category** field separated by commas (with no spaces around these commas).
 - **Comment** is an optional text description.
- If you click the **X12 Input** tab or **HL7 Input** tab (if available), specify the following values:
 - Choose a messaging protocol to select an existing specialized host class.
 - Specify a configuration **Name**. For rules, see [Configuration Names](#).
 - Use the **Target Name** field to identify the business process or business operation to which this business service will send the messages that it receives.

If you select the **Create New Router** option, you can use the **New Rule Package** field to specify a package name that will be added to the name of the rule created for the new router. If you do not specify a **New Rule Package** value, the production's package is used.

- Select the **Default applies if no value** check box if you want blank settings to be replaced with the [system default settings](#) when the business service is created. Fields identified by an asterisk (*) will be replaced with the system default values. Click  to view the possible default values.
- If you click the **Business Metric** tab, specify the following values:
 - Choose a host class from the **MetricClass** drop-down list. If the class you need does not appear on this list, create the class in an IDE, then return to choose it.
See [Creating Business Metrics](#).
 - Specify a configuration **Name**. For rules, see [Configuration Names](#).
 - Enter a text label in the **Category** field to sort and organize items within the production. **Category** names are case-sensitive, and space characters are allowed. To place an item in multiple categories, list them in the **Category** field separated by commas (do not allow spaces around these commas).
 - **Comment** is an optional text description.
 - **Call Interval** determines how often the business metric will recalculate the values of its properties. The **Call Interval** is in seconds, starting from a minimum of 0.1 seconds. The default is 5 seconds.

3.5 Business Process Wizard

The Business Process Wizard provides multiple tabs, which correspond to different types of business process classes to use. Click a tab and then specify values as follows:

- If you click the **All Processes** tab, specify the following values:
 - **Business Process Class**—Choose a base class from the list of valid business process classes. If the class you need does not appear on this list, create and compile the class and then return here to choose it.
 - Specify a configuration **Name**. For rules, see [Configuration Names](#).
The wizard defaults to the business process class name if you leave this blank.
 - Specify other values as given after this list.
- If you click the **X12 Router** tab or **HL7 Router** tab (if available), specify the following values:
 - **Auto-create Rule**—Select this check box to create a rule definition name based on the business process class name. When **Auto-create rule** is selected, you can use the **New Rule Package** field to specify a package name that will be added to the name of the rule created for the new router. If you do not specify a **New Rule Package** value, the production's package is used. In most cases, the **New Rule Package** field is ignored if the **Routing Process Name** field begins with a package name. However, if the package specified by the **Routing Process Name** field is the system package name `Ens` or `EnsLib`, a rule that is auto-created will have a different package name added to the beginning of the rule name. This additional package is determined by the contents of the **New Rule Package** field. If the package of the production or routing process is used instead of a specified value, the generated rule class name ends with 'RoutingRule'.
 - **Routing Rule Name**—Use the field to identify the name of the routing rule set to which this business process sends the messages that it receives. Only appears if the previous check box is cleared.
Once you select a rule name, you can click the magnifying glass to open the Rule Editor.
 - Specify a **Routing Process Name**. For rules, see [Configuration Names](#). To specify a package for the new routing process, use the format `package . name` in the field.

The underlying business process class is `EnsLib.MsgRouter.VDocRoutingEngine` depending on which type of router you choose.

- Specify other values as given after this list.
- If you click the **Component** tab, specify the following values:
 - **Component Class**—Choose a base class from the list of valid business process classes designated as components.
 - **Component Name**—Enter a configuration name for this item. For rules, see [Configuration Names](#). The wizard defaults to the component class name if you leave this blank.
 - Specify other values as given after this list.

Note that all types of business process share the following optional fields:

- **Display Category**—Enter a text label in the field to sort and organize items within the production. Category names are case-sensitive and space characters are allowed. To place an item in multiple categories, enter a comma-separated list.
- **Comment**—Enter a brief comment about the business process to appear in the informational settings.
- **Enable Now**—Select this check box if you want this business process to begin processing messages immediately when the production runs; clear it for the process to be initially disabled.

3.6 Business Operation Wizard

The Business Operation Wizard provides multiple tabs, which correspond to different types of business operation classes to use. Click a tab and then specify values as follows:

- If you click the **All Operations** tab, specify the following values:
 - Choose a host class from the **Operation Class** list. If the class you need does not appear on this list, create the class in an IDE, then return here to choose it.
 - Specify a configuration **Name**. For rules, see [Configuration Names](#).
 - Enter a text label in the **Display Category** field to sort and organize items within the production. **Display Category** names are case-sensitive, and space characters are allowed. To place an item in multiple categories, list them in the **Display Category** field separated by commas (do not allow spaces around these commas).
 - **Comment** is an optional text description.
 - Specify other values as given after this list.
- If you click the **X12 Output** tab, specify the following values:
 - Choose **TCP**, **File**, or **FTP** to determine the host class. Each class already exists and requires no programming. Simply choose one.
 - Give the item a configuration **X12 Operation Name**. For rules, see [Configuration Names](#).
 - Specify other values as given after this list.
 - Select the **Default applies if no value** check box if you want blank settings to be replaced with the [system default settings](#) when the business operation is created. Fields identified by an asterisk (*) will be replaced with the system default values. Click  to view the possible default values.

- If you click the **Workflow** tab, specify the following values:
 - Choose a host class from the **Operation Class** drop-down list. If the class you need does not appear on this list, create the class in an IDE, then return here to choose it.
 - Give the item a configuration **Operation Name**. For rules, see [Configuration Names](#).
 - Choose whether or not to auto-create a workflow role.
 - Specify other values as given after this list.

All types of business operation share the following optional fields:

- **Display Category**—Enter a text label in the field to sort and organize items within the production. Category names are case-sensitive and space characters are allowed. To place an item in multiple categories, enter a comma-separated list.
- **Comment**—Enter a brief comment about the business operation to appear in the informational settings.
- **Enable Now**—Select this check box if you want this business operation to begin processing messages immediately when the production runs; clear it for the operation to be initially disabled.

3.7 See Also

- [Introduction to the Legacy Production Configuration Page](#)
- [Modifying Business Hosts \(Legacy UI\)](#)
- [Configuring Settings \(Legacy UI\)](#)

4

Modifying Business Hosts (Legacy UI)

This topic describes how to use the [legacy Production Configuration page](#) to modify business hosts.

For information on performing these tasks with the new UI, see [Modifying Business Hosts](#).

4.1 Enabling, Disabling, or Restarting a Business Host

You can either enable, disable, or restart business hosts individually or for a selection of business hosts.

To enable, disable, or restart a single business host, do one of the following:

- Double-click a host item. InterSystems IRIS displays a dialog box that allows you to enable, disable, or restart the host item depending on the current state of the production and the host item:
 - If the production is running and the host item is enabled, the dialog box gives you the option to disable the host item, restart the host item, or to cancel the request.
 - If the production is not running and the host item is enabled, the dialog box gives you the option to disable the host item or to cancel the request.
 - If the host item is disabled, the dialog box gives you the option to enable the host item or cancel the request.
- Select or clear the **Enabled** setting (as appropriate) and then click **Apply**. To restart a host item, first disable it and then enable it.
- Use the **Stop**, **Start**, and **Restart** buttons on the **Action** tab. Because the setting controlled by the **Enabled** check box is a setting stored in the production class definition, you cannot use it to stop, start, or restart a production that you cannot edit, for example because you lack sufficient privileges, or it is marked read-only due to being managed by source control system. The **Stop**, **Start**, and **Restart** buttons on the **Action** tab perform these actions without modifying the production class definition.

To enable, disable, or restart a selection of business hosts, do the following:

1. Select multiple business hosts in the Production Configuration page by using the Ctrl and Shift keys. The Ctrl key keeps any existing selection and either adds or removes the item from the selection. The Shift key allows you to select a contiguous set of one kind of business hosts—either Business Services, Business Processes, or Business Operations.
2. Once you have selected multiple business hosts, the right panel automatically switches to the **Actions** tab, which will include **Enable**, **Disable**, and **Restart** buttons.
3. Select the button to enable, disable, or restart the selected business hosts.

Note: You cannot disable a business process with a pool size of 0. The management portal does not allow this action because disabling it would stop all business processes with a pool size of 0, which use the same shared actor queue. If you want to disable only a single business process, you must first set its pool size to 1 or more. After you apply the settings, you can disable it. If you do want to stop all business processes using the shared actor pool, select **Production Settings** and set the **Actor Pool Size** to 0. Also see [Pool Size and Actor Pool Size](#).

4.2 Changing the Class That a Business Host Uses

To modify a business host so that it is based on a different class:

1. Display the **Production Configuration** page:
2. Click the business host in the diagram.
3. Click the **Actions** tab.
4. Click **Change Class**. This button is visible only when you can edit the business host.
5. Select a new class.

4.3 Copying a Business Host

To create a copy of a business host within a given production:

1. Display the **Production Configuration** page:
2. Click the business host in the diagram.
3. Click the **Actions** tab.
4. Click **Copy**. This button is visible only when you can edit the business host.
5. Click **Copy** to create a copy of the selected business host.

A dialog box prompts you to enter a configuration name.

6. Enter a unique name and click **OK**.

When first created, the copy has the same host class and settings as the original; only the name is different. Generally your next step is to configure the copy to make it unique. For example:

- If you have an incoming TCP *business service* that receives messages from a client application, and you want to receive messages from a similar application on a different application server, you can copy the first TCP service and configure the copy with the other server address.
- If you have a *business process* for one message routing interface, and you want a similar one but with alterations for another interface, you can copy the first routing process and configure the copy to route messages between different sets of business services and business operations.
- If you have an outgoing email *business operation* that alerts a user, but you want to alert another user at different times of day, you can copy the first outgoing email operation and configure the copy with the other email address.

The copy has no relationship to the original item; you can configure, enable, and disable each item independently.

Note: The **Copy** command works only within the same production. You cannot copy a business host from one production to another.

4.4 Deleting a Business Host

To delete a business host within a given production:

1. Display the **Production Configuration** page:
2. Click the business host in the diagram.
3. Click the **Actions** tab.
4. Click **Delete**. This button is visible only when you can edit the business host.

This process removes this item from the production configuration. This action does not delete the business host class on which the business host is based.


4.5 Repairing an Error

If the class for a given business host is not available, the diagram displays the item with a red background. To fix the error:

1. Select the item.
2. Click the **Actions** tab.
3. Now either click **Delete** to remove the item or click **Change Class** to choose a class. This button is visible only when you can edit the business host.

4.6 Viewing and Configuring Connections

When you click the status indicator of a business host, lines connect items as defined by the values in the **Target Config Names** setting or, in the case of a routing process, as defined by the associated **Business Rule Name**. The following figure shows an example:



You can assign a business service **Target Config Names** by clicking its status indicator and dragging the pointer to a business process or operation until you see its status indicator highlighted. When you do so, the **Production Configuration** page displays

a dialog window requesting you to confirm the connection. If you confirm the connection, the page displays a *Settings applied* message and the item is added to the list in the **Target Config Names** setting.

4.7 Working with Multiple Versions of a Business Host

During development, it can be convenient to include multiple versions of a business host in the production and then switch among them for testing.

Only one of them can be enabled at any time; when you enable one, InterSystems IRIS automatically disables any previously enabled version.


To create and work with multiple versions of a host:

1. Add the first business host as usual.
2. Add the next business host and provide the same configuration name as for the first one.


The production configuration still shows only one business host with the given name.

3. If you are not in listing view, click the listing view icon .
4. Select the business host.

Now the diagram displays a small box that indicates the number of items that have this name, as follows:



Also, the area above the diagram shows a drop-down list that you can use to select the specific item to work with:



By default, the enabled version is selected. If no host is enabled, the selected version is the first business host that you added.

5. Use the **Item** list to select the version that you want to configure. Specify configuration details as usual and apply them.
6. Repeat if needed.

To understand why this is useful, consider the following: when testing or troubleshooting the production you might want to send messages by typing them at the console command line, or by reading data from files. But when running the production, you might intend for these messages to arrive from an external application via a TCP connection. Each means of obtaining input for the production requires a different business service host class.

4.8 See Also

- [Introduction to the Legacy Production Configuration Page](#)

- [Adding Business Hosts \(Legacy UI\)](#)
- [Configuring Settings \(Legacy UI\)](#)

5

Configuring Settings (Legacy UI)

This topic describes how to use the [legacy Production Configuration page](#) to configure settings.

For information on performing these tasks with the new UI, see [Configuring Settings](#).

5.1 Configuring Settings

To configure settings for a business host:

1. Click the business host.
2. Click the **Settings** tab.
3. Expand and collapse the groups as needed to see the settings. You can also [search](#) for a setting.
4. Edit values as needed.
 - Some configuration settings, take comma-separated lists to define their possible values. You can change these items either by editing the list directly or by selecting the check boxes of the desired values in the associated drop-down list. When you edit settings that use drop-down lists, be sure to click outside of the list to close it.
 - Some configuration settings have a magnifying glass icon next to them. You can click this to see more details of a selected value, or to open a new portal page for entering additional information. This depends on the type of setting you are editing.

See [Settings in All Productions](#). Also see information on specific adapters and business hosts.

5. Click **Apply**.

If the apply command is successful, you receive a *Settings applied* message.

InterSystems IRIS® validates the values for settings. If you provide a string value for a setting that requires a numeric value, InterSystems IRIS does not apply that value.

Similarly, to configure settings for the production, first click **Production Settings**. This step returns the focus to the production and changes the options on the **Actions** tab. Then continue as described in the previous steps.

In both cases, the changes are immediately saved and take effect immediately.

5.2 Color Coding

The setting names are color coded as follows:

Color	Source
Black	Setting value comes from the production definition—the value you enter and apply in the configuration page.
Green	Setting value comes from the class definition; it is the default value for the property as defined in the class.
Blue	Setting value comes from the system defaults table .

5.3 Searching for a Setting

To find a setting more easily, use the **Search** option. Enter text to show all settings whose name, type, category, or value contains the search string. Click the X icon to clear the contents of the **Search** box.

5.4 Getting Help for Settings

This page provides context-sensitive help. Hover the cursor over any setting name to display its help text as it appears in the Class Reference for the associated class property or click the setting name to display the help text in a separate pop-up window.

The property name appears beneath the localized setting name in this window if the name is different.

Also see [Settings in All Productions](#), as well as other pages that discuss specific adapters and business hosts.

5.5 Restoring a Setting to Its Default Value

To restore a setting to its default value:

1. Click the default setting icon  on the **Settings** tab.

InterSystems IRIS then displays a dialog box with a table that displays the following columns:

Column	Description
Select check box	Shown only if the current value is not the default.
Setting	Name of the setting as displayed in the Management Portal.
Target	Indicates if the setting applies to a host or to an adapter. This is blank for a production setting.
Value	Current value of the setting.

Column	Description
Value Source	Source of the current value: - class definition—the value is specified in the class on which this item is based. - default setting—the value is a system default setting. - production definition—the value is specified in the production definition.
Default	Default value for this setting.
Default Source	Source of the default value: - class definition—if you see this, there is no system default for this setting. - default setting See the notes for Value Source.

- For each setting that you want to change, select the check box.
- Click **OK**. The property label changes color depending on the **Default Source**. See [Understanding the Color Coding for Settings](#).

Or, if you make a mistake and want to return to the original values, click **Cancel**; the settings refresh to the previous values and the dialog box closes.

- Click **Apply** to save all your changes.

5.6 See Also

- [Defining System Default Settings](#)
- [Understanding the Color Coding for Settings](#)
- [Settings in All Productions](#)

