



Windows Installation Details

Version 2026.1
2026-04-20

Windows Installation Details

PDF generated on 2026-04-20

InterSystems IRIS Version 2026.1

Copyright © 2026 InterSystems Corporation

All rights reserved.

InterSystems®, HealthShare Care Community®, HealthShare Unified Care Record®, InterSystems IRIS® IntegratedML®, InterSystems Caché®, InterSystems Ensemble®, InterSystems HealthShare®, InterSystems IRIS®, InterSystems IRIS® for Health, and TrakCare are registered trademarks of InterSystems Corporation. HealthShare® Health Connect Cloud™, InterSystems® Data Fabric Studio™, and InterSystems Supply Chain Orchestrator™ are trademarks of InterSystems Corporation. TrakCare is a registered trademark in Australia and the European Union.

All other brand or product names used herein are trademarks or registered trademarks of their respective companies or organizations.

This document contains trade secret and confidential information which is the property of InterSystems Corporation, One Congress Street, Boston, MA 02114, or its affiliates, and is furnished for the sole purpose of the operation and maintenance of the products of InterSystems Corporation. No part of this publication is to be used for any other purpose, and this publication is not to be reproduced, copied, disclosed, transmitted, stored in a retrieval system or translated into any human or computer language, in any form, by any means, in whole or in part, without the express prior written consent of InterSystems Corporation.

The copying, use and disposition of this document and the software programs described herein is prohibited except to the limited extent set forth in the standard software license agreement(s) of InterSystems Corporation covering such programs and related documentation. InterSystems Corporation makes no representations and warranties concerning such software programs other than those set forth in such standard software license agreement(s). In addition, the liability of InterSystems Corporation for any losses or damages relating to or arising out of the use of such software programs is limited in the manner set forth in such standard software license agreement(s).

THE FOREGOING IS A GENERAL SUMMARY OF THE RESTRICTIONS AND LIMITATIONS IMPOSED BY INTERSYSTEMS CORPORATION ON THE USE OF, AND LIABILITY ARISING FROM, ITS COMPUTER SOFTWARE. FOR COMPLETE INFORMATION REFERENCE SHOULD BE MADE TO THE STANDARD SOFTWARE LICENSE AGREEMENT(S) OF INTERSYSTEMS CORPORATION, COPIES OF WHICH WILL BE MADE AVAILABLE UPON REQUEST.

InterSystems Corporation disclaims responsibility for errors which may appear in this document, and it reserves the right, in its sole discretion and without notice, to make substitutions and modifications in the products and practices described in this document.

For Support questions about any InterSystems products, contact:

InterSystems Worldwide Response Center (WRC)

Tel: +1-617-621-0700

Tel: +44 (0) 844 854 2917

Email: support@InterSystems.com

Table of Contents

1 Windows User Accounts	1
2 Installing a Web Server on Windows	3
3 Command Line Reference	5
3.1 Command-Line Properties Reference	5
3.2 Custom-Installable Features Reference	9
4 Managing Auto-start	11
5 The Write-cache Buffer	13

1

Windows User Accounts

When installing InterSystems IRIS, you must choose the Windows user account to run the InterSystems service, *InterSystems IRIS Controller for <instance-name>*. There are two options:

- The default SYSTEM account (Windows Local System account). This is used in **Minimal** security installations.
- A defined Windows user account. This account must have interactive login privileges for the duration of the installation; they can be revoked after.

Running the InterSystems service under the default SYSTEM account is appropriate for many installations, but in some cases can cause issues relating to file permissions and network security access. If you anticipate potential problems in these areas for an InterSystems IRIS instance—for example due to your network configuration or security arrangements—specify a Windows account for the InterSystems service that has the needed privileges and access, such as a domain administrator account.

For instructions on how to change the service account after installation, see [Managing Access to the InterSystems IRIS Instance](#).

Important: If you are using Kerberos, you must configure a Windows account before installing InterSystems IRIS. InterSystems recommends you use a separate account specifically set up for this purpose as described in [Preparing the Security Environment for Kerberos](#).

Note: If running InterSystems IRIS under a defined Windows user account, be sure to grant that account the Windows “Lock Pages in Memory” (SELockMemory) privilege. See [Configuring Large Pages on Windows](#) in the “Preparing to Install InterSystems IRIS” chapter for details.

2

Installing a Web Server on Windows

Before installing InterSystems IRIS, you should install a supported web server in order to access web applications, including the Management Portal. The installation procedure will vary depending on the web server you choose. For details, you should refer to your web server's documentation.

In many cases, the InterSystems IRIS installer can automatically configure a new or upgraded instance to serve its built-in web applications using your web server. For details, see [Connect Your Web Server Automatically](#).

If you would like to manually set up your web server, you can do this after installing IRIS. For details, see [Connect Your Web Server Manually](#).

If you intend on configuring the web server manually and you are performing an unattended installation, you should include the `cspiis` component and set `CSPSKIPIIISCONFIG=1`. This installs the necessary IIS CSP binary files without configuring your web server. If the `cspiis` component is included and `CSPSKIPIIISCONFIG` is not set or is set to 0, the installer will attempt to configure your web server and will fail if one is not detected.

If you do not plan on configuring a web server at any point, you can omit `cspiis` from `ADDLOCAL`. This prevents the installation of the IIS CSP binary files.

Important: InterSystems recommends using the Microsoft IIS web server because it can be automatically configured during the installation process. Make sure it is installed and running before beginning the installation process. In most cases, it is not necessary to manually configure the IIS web server.

3

Command Line Reference

3.1 Command-Line Properties Reference

The command-line properties reference describes the InterSystems IRIS-specific unattended install properties that you can modify via the command-line interface. These can be used when performing an [unattended installation](#) or when launching an [attended installation](#) from the command line. The property name must be uppercase, but the arguments are not case-sensitive; each property must be separated by one or more spaces, and properties can be specified in any order as *PROPERTYNAME=argument*. For example:

```
... ISCSTARTIRIS=0 ISCSTARTLAUNCHER=0 INITIALSECURITY=Normal
```

Note: In the following reference, the **REINSTALL** and **REMOVE** properties are used with installed instances, as described in [Running an Unattended Upgrade or Reinstall](#) and [Running an Unattended Removal](#), respectively.

ADDLOCAL

Default: ALL (installs all features)

Use this property to custom install a new instance of InterSystems IRIS with a subset of features or to omit optional databases (see the [Custom-Installable Features Reference](#)) by specifying a comma-separated list of *featurenames* together with their group names, as described in the example following this reference.

See also the **REINSTALL** property, for use with installed instances.

CSPSKIPIISCONFIG

Default: 0 if the **cspiis** component is included, otherwise 1

Use this property to install IIS CSP binary files. With a value of 1, the files are installed without any changes to the IIS web server configuration. With a value of 0, the installer updates the IIS web server configuration regardless of the existence of the /csp virtual directory.

When this property is set to 0, the installation will fail if a web server is not detected. If you don't want the installer to automatically configure your web server, you should set this property to 1.

CSPSYSTEMUSERPASSWORD

Default: value of **IRISUSERPASSWORD** if security level is Normal or LockedDown, otherwise not used

If the security level is Normal or LockedDown, optionally use this property to specify a password for the CSP-System predefined user.

If the initial security level is `None`, do not use this property.

CSPSYSTEMUSERPASSWORD

Default: value of **IRISUSERPASSWORD**

Optionally use this property to specify a password for the CSPSystem predefined user.

INITIALSECURITY

Default: `LockedDown`

Use this property to specify the level of security to be used by the instance being installed. Specify `None`, `Normal`, or `LockedDown`.

Use this property to specify the level of security to be used by the instance being installed. Specify `Normal` or `LockedDown`.

See also the **IRISUSERPASSWORD**, **CSPSYSTEMUSERPASSWORD**, and **SERVICECREDENTIALS** properties in this reference.

INSTALLDIR

Default: `C:\InterSystems\IRISn`, where *n* is {empty}, 1, 2, ... 127.

Default: `C:\InterSystems\IRISHealthn`, where *n* is {empty}, 1, 2, ... 127.

Default: `C:\InterSystems\HealthConnectn`, where *n* is {empty}, 1, 2, ... 127.

Use this property to specify the directory in which the instance is to be installed.

INSTALLERMANIFEST

If installing with an installation manifest, as described in [Using the Manifest](#) in the appendix “Creating and Using an Installation Manifest”, you must use this property to specify the location of the installation manifest (that is, your exported manifest class).

INSTALLERMANIFESTLOGFILE

If installing with an installation manifest, as described in [Using the Manifest](#) in the appendix “Creating and Using an Installation Manifest”, this property specifies where %Installer prints messages.

INSTALLERMANIFESTLOGLEVEL

If installing with an installation manifest, optionally use this property to specify the [log level](#) of the **setup()** method of your installation manifest class. The default log level is 1.

INSTALLERMANIFESTPARAMS

If installing with an installation manifest, as described in [Using the Manifest](#) in the appendix “Creating and Using an Installation Manifest”, use this property to specify the name/value pairs (*name=value*) to be passed to the first argument of the **setup()** method of your installation manifest class. This property can be used to modify the configuration parameter file (`iris.cpf`) and activate the changes before your manifest runs. You can specify these parameters:

- `bbsiz`
- `globals4kb`, `globals8kb`, `globals16kb`, `globals32kb`, `globals64kb`
- `gmheap`
- `LibPath`
- `locksiz`

- MaxServerConn
- Path
- routines
- ZFSize, ZFString

For example:

```
INSTALLERMANIFESTPARAMS="bbsiz=512000, globals4kb=20,
globals8kb=30, globals16kb=40, globals32kb=50,
globals64kb=100, routines=40, gmheap=10000,
LibPath=c:\libpath\, locksiz=2179648, MaxServerConn=5,
Path=c:\lib\, ZFSize=2000, ZFString=3000"
```

The following would be useful in installing and activating 100 MB of 64KB buffers before running a manifest that creates a 64kb block size database:

```
INSTALLERMANIFESTPARAMS="globals64kb=100"
```

IRISSERVICEDOMAIN

Required if the service credentials are defined as `UserDefined`

If the service credentials are specified as `LocalSystem`, do not use this property.

See the **SERVICECREDENTIALS** property in this reference. Use this property to specify the domain of the Windows InterSystems service login account specified by **IRISSERVICEUSER**.

IRISSERVICEPASSWORD

Required if the service credentials are defined as `UserDefined`

If the service credentials are specified as `LocalSystem`, do not use this property.

See the **SERVICECREDENTIALS** property in this reference. Use this property to specify the password for the Windows InterSystems service account specified by **IRISSERVICEUSER**.

IRISSERVICEUSER

Required if the service credentials are defined as `UserDefined`

If the service credentials are specified as `LocalSystem`, do not use this property.

See the **SERVICECREDENTIALS** property in this reference. Use this property to specify the username of the account under which to run the Windows InterSystems service.

IRISUSERPASSWORD

Required if the security level is `Normal` or `LockedDown`

If the initial security level is `None`, do not use this property.

See the **INITIALSECURITY** property in this reference. Use this property to specify the password for the predefined InterSystems IRIS accounts `_SYSTEM`, `Admin`, and `SuperUser`, as well as the account with the username specified by **IRISSERVICEUSER** if **SERVICECREDENTIALS** is specified as `UserDefined`.

IRISUSERPASSWORD

Required

Use this property to specify the password for the predefined InterSystems IRIS accounts `_SYSTEM`, `Admin`, and `SuperUser`, as well as the account with the username specified by **IRISSERVICEUSER** if **SERVICECREDENTIALS** is specified as `UserDefined`.

ISCSTARTIRIS

Default: 1 (start InterSystems IRIS after installation)

Optionally set this property to 0 to prevent InterSystems IRIS from starting after installation.

ISCSTARTLAUNCHER

Default: 1 (add the launcher to the system tray)

Optionally set this property to 0 to prevent the InterSystems IRIS launcher from being added to the system tray.

REINSTALL

Use this property to [reinstall](#) (repair) an installed instance of InterSystems IRIS or to change the custom-installed features (see the [Custom-Installable Features Reference](#)) for an installed instance of InterSystems IRIS:

- To reinstall whatever features are currently installed for the instance—whether that is a custom-installed subset of features or all features—specify `ALL`.
- To reinstall a subset of InterSystems IRIS features that is different from the subset of features currently installed, specify a comma-separated list of *featurenames* together with their group names (as described in the example following this reference).

See also the **ADDLOCAL** property (for use with new instances) and **REMOVE** property (for uninstalling installed instances).

REMOVE

Use this property to [uninstall](#) (remove) an instance of InterSystems IRIS or a subset of custom-installed features (see the [Custom-Installable Features Reference](#)) installed for an installed instance of InterSystems IRIS:

- To remove an instance of InterSystems IRIS, specify `ALL`.
- To remove a subset of InterSystems IRIS features, specify a comma-separated list of *featurename* together with their group names (as described in the example following this reference).

See also the **ADDLOCAL** (for new instances) and **REMOVE** properties in this reference.

SERVICECREDENTIALS

Default: `LocalSystem` if security level is `Normal` or `LockedDown`, otherwise not used

If the initial security level is `None`, do not use this property.

If the security level is `Normal` or `LockedDown`, optionally use this property to specify the credentials under which the Windows InterSystems service runs: `LocalSystem` for the default local system account or `UserDefined` (an existing Windows user account).

If you specify `UserDefined` for this property, you must also specify the **IRISSERVICEDOMAIN**, **IRISSERVICEPASSWORD**, and **IRISSERVICEUSER** properties.

See [Managing Access to the InterSystems IRIS Instance](#) for important information about the InterSystems service account.

SERVICECREDENTIALS

Default: LocalSystem

Use this property to specify the credentials under which the Windows InterSystems service runs: LocalSystem for the default local system account or UserDefined (an existing Windows user account).

If you specify UserDefined for this property, you must also specify the **IRISSERVICEDOMAIN**, **IRISSERVICEPASSWORD**, and **IRISSERVICEUSER** properties.

See [Managing Access to the InterSystems IRIS Instance](#) for important information about the InterSystems service account.

SKIPUPGRADECHECK

Default: 0 (pre-upgrade checking enabled)

When upgrading an instance, set this property to 1 to bypass system pre-upgrade checking.

Note: Generally, you should leave pre-upgrade checking enabled.

SUPERSERVERPORT

Default: 1972 if available, otherwise 51773 or the first available subsequent number

Use this property to specify the Superserver port to be used by the instance being installed.

UNICODE

Default: 1 (16-bit Unicode characters are supported)

Use this property to specify whether 8-bit or 16-bit Unicode characters are to be supported by the instance being installed. For 8-bit characters, specify 0; for 16-bit characters, specify 1.

3.2 Custom-Installable Features Reference

The custom-installable features reference lists component group/component names and the associated *featurename* for each. You can specify “ALL” (to specify all available features) or a comma-separated list (with no spaces) of feature names (to specify individual features).

To specify components in ADDLOCAL, REINSTALL, and REMOVE properties, specify the *featurename* of a component group, followed by the *featurename* of each specific component from that group that you want installed. For example, to install only the USER database include the following in the command line:

```
ADDLOCAL=server,server_user
```

When specifying a component group, you must also specify at least one associated component; if no components are listed with a component group, the component group is ignored and no components are installed. For example, if you specify:

```
ADDLOCAL=documentation,documentation_pdf,server,development,callin
```

the **server** component group is ignored and no server components are installed. (This requirement does not apply to the **cube** group, as it has no components.)

development

Use **development** for the development component group which includes the following components:

- ActiveX Connectivity (**activex**)
- Callin (**callin**)
- Callin, Threaded (**callin_threaded**)
- Other Development Libraries (**development_other**)

documentation

Use **documentation** for the documentation component group which includes the following components:

- PDF Documentation (**documentation_pdf**)

cube

Use **cube** for the launcher component. This component group includes no other components.

server

Use **server** for the server component group which includes the following components:

- User database (**server_user**)
- SQL Gateway (**sqlgateway**)
- Apache Formatting Objects Processor (**fop**)
- Server monitoring tools (**server_monitoring**)
- Agent Service (**agent_service**)
- [InterSystems Package Manager](#) (**server_ipm**)
- HotJVM RenderServer/QueuingRenderServer for Zen Reports (**renderserver**)

sqltools

Use **sqltools** for the database drivers component group which includes the following components:

- ODBC (**odbc**)
- JDBC (**jdbc**)

cspgateway

Use **cspgateway** for the Web Gateway component group which includes the following components:

- IIS (**cspiis**)

4

Managing Auto-start

The Windows InterSystems service includes the instance name. After installing, by default the instance starts automatically when you start your server; this means the InterSystems IRIS instance is automatically configured to autostart (start when the system starts).

You can configure the instance not to autostart by changing the **Start InterSystems IRIS on System Boot** setting on the **Memory and Startup** page of the Management Portal (from the home page, select **System Administration > Configuration > System Configuration > Memory and Startup**).

5

The Write-cache Buffer

Certain InterSystems IRIS features utilize **Windows write-cache buffer flushing**, which is enabled by default. To verify this option is correctly enabled and InterSystems IRIS receives the full benefit of these features:

1. Open the **Device Manager** from the **Control Panel**.
2. Select the storage device from the **Disk Drives** section.
3. Click on the **Policies** tab.
4. Ensure that **Turn off Windows write-cache buffer flushing on this device** is *not* selected.

