Search

Feature flags and Al Configs > Al Configs

Target with AI Configs

Overview

This topic explains how to use AI Config targeting to control which of your customers receive a particular variation of an AI Config, based on their context. Targeting is enabled by default for all AI Configs. You can turn targeting off to serve the off variation to all contexts.

LaunchDarkly <u>contexts</u> are data objects that represent users, devices, organizations, and other entities that interact with your application. These data objects contain <u>context</u> <u>attributes</u> that describe what you know about that context, such as their name, location, device type, or organization they are associated with. LaunchDarkly <u>AI SDKs</u> can pass any context attributes you want to LaunchDarkly, where you can then use those attributes in AI Config targeting, as well as in the AI Config variation's messages.

If you are familiar with LaunchDarkly's <u>flag targeting</u>, this process is very similar: with Al Configs, you can target individuals or segments, or target contexts with custom rules.

Additionally, every AI Config has a default rule and an off variation.

Targeting rules are specific to each <u>environment</u>. You can update targeting rules if your role includes the <u>updateAIConfigTargeting</u> action.

Target individuals

You can target specific contexts based on their context key. If you are targeting more than one or two individuals, we recommend targeting a segment instead, because segments

10 target marviadas.

- 1. Navigate to the **Targeting** tab for the Al Config.
- 2. At the top of the tab, select the <u>environment</u> for which you want to create targeting rules. Targeting rules are specific to each environment.
 - To add targeting rules to an environment that's not shown, click the + icon to add another environment to the **Targeting** tab.
- 3. Click the + button between existing rules, and select **Target individuals**.
 - If the Al Config is off and the rules are hidden, click **View targeting rules**.
- 4. In the "Individual targeting" section, search for and select the context you want to target.
- 5. Alternatively, you can create a new context from the search menu. To do so:
 - Enter the new context name.
 - Click Create new.
 - Select a context kind from the context kind menu.
- 6. Select a variation to **Serve**.
- 7. To add more contexts, click **Add individual context**.
- 8. Click Review and save.

Contexts that LaunchDarkly has evaluated within the last 30 days are indicated by a green eye icon.

Target segments


Segments are lists of contexts that you can use to manage Al Config targeting behavior in bulk. You can target segments to release specific Al Config variations to different groups of contexts or end users at once.

targeting rule or set of rules for many Al Configs.

To target segments:

- 1. Navigate to the **Targeting** tab for the Al Config.
- 2. At the top of the tab, select the <u>environment</u> for which you want to create targeting rules. Targeting rules are specific to each environment.
 - To add targeting rules to an environment that's not shown, click the + icon to add another environment to the **Targeting** tab.
- 3. Click the + button between existing rules, and select Target segments.
 - If the AI Config is off and the rules are hidden, click **View targeting rules**.
- 4. (Optional) Enter a name for the rule.
- 5. In the **Operator** menu, select whether you want contexts in these segments or not in these segments to match the targeting rule.
- 6. In the **Segments** menu, enter or select the segments you want to target.
- 7. (Optional) Click the + to add additional clauses to your targeting rule.
- 8. From the **Select...** menu, select the variation to serve, or set a percentage rollout.
- 9. Click Review and save.

Here is an example of a targeting rule for segments:



To learn more, read Segments.

Target contexts with custom rules

You can create custom targeting rules using any context kinds and any context attributes.

To create a custom targeting rule:

- 1. Navigate to the **Targeting** tab for the Al Config.
- 2. At the top of the tab, select the <u>environment</u> for which you want to create targeting rules. Targeting rules are specific to each environment.
 - To add targeting rules to an environment that's not shown, click the + icon to add another environment to the **Targeting** tab.
- 3. Click the + button between existing rules, and select **Build a custom rule**.
 - If the AI Config is off and the rules are hidden, click View targeting rules.
- 4. (Optional) Enter a name for the rule.
- 5. Select an option from the **Context kind** menu:
 - Choosing a specific context kind lets you target on attributes for contexts of that kind.
 - Choosing "Context kind" lets you target one or more context kinds. If you choose "Context kind," skip to step 7.
 - Context kinds are included in this menu after either you <u>create them from the</u>
 Contexts list or <u>customize an Al Config using a LaunchDarkly Al SDK.</u>
- 6. In the **Attribute** menu, select one of this context's attributes.
- 7. In the **Operator** menu, select the operator for your clause.
- 8. In the **Values** menu, enter one or more values to check against.
- 9. (Optional) Click the + to add additional clauses to your targeting rule.

If a targeting rule references any context kinds or attributes with null values, or that do not exist for a given context, then the Al Config skips that rule. For example, in a rule that checks "region is one of Canada," any context whose region attribute is not set or is set to null does not match the rule. Similarly, in a rule that checks "region is not one of Canada," any context whose region attribute is not set or is set to null does not match the rule. This behavior ensures that your rules only target contexts for which you explicitly have attribute information.

To reference this rule when working with other members of your organization, click the **three-dot** overflow menu and choose **Copy link to rule**.

To learn more about how to construct targeting rules, read <u>About targeting rules</u>. Although that topic applies specifically to feature flag targeting, the "About targeting rules" section discusses the components of targeting rules, including their descriptions, conditions, rollouts, attributes, and operators. These elements are common to both feature flags and Al Configs.

Set the default rule

Each Al Config automatically includes a default rule. It describes which Al Config variation should be served to contexts that don't match any of the previous targeting rules on the Al Config.

The default rule is different from the fallback value, which is set in your application's code and is the value that contexts receive if your application can't connect to LaunchDarkly. To learn more, read Fallback value.

The default rule is also different from the off variation, which is the value LaunchDarkly serves when the flag is off. To learn more, read The off variation, below.

To set the default rule:

Navigate to the **Targeting** tab for the Al Config.

- To add targeting rules to an environment that's not shown, click the + icon to add another environment to the **Targeting** tab.
- 3. Find the last rule on the **Targeting** tab, which is labeled "Default rule."
 - If the Al Config is off and the rules are hidden, click **View targeting rules**.
- 4. Click **Edit** to configure the default rule to serve a specific variation, or apply a percentage rollout to any remaining contexts.

Here is an image of a default rule:



Use guarded rollouts

When you update which variation an Al Config serves, you can use a <u>guarded rollout</u> to gradually serve the new variation while monitoring key metrics for regressions.

Guarded rollouts help reduce risk when updating prompts, models, or other Al-powered behavior. If LaunchDarkly detects a regression, it can pause the release or restore the previous variation automatically. This helps you detect problems early and avoid serving broken or degraded Al responses.

To use a guarded rollout, open the **Targeting** tab, make a variation update, and select **Guarded rollout** when reviewing your changes. You can monitor release progress and metric results from the **Monitoring** tab.

Each AI Config has a special "disabled" variation, which is created automatically. It is served when the AI Config is toggled off.

