



ELIT /zOS

Administrator's Guide

Table of contents

INTRODUCTION	3
Related Documentation.....	3
Purpose.....	3
ELIT Alerts.....	3
Trademarks.....	3
LOCATION CODES.....	4
CHIP – CUSTOMER HELP INTERFACE	6
Location Table – Base Records	6
Add Function.....	7
Delete and Update Functions.....	7
Browse Functions.....	8
Reinstate Functions	8
Swap Screen Functions	8
Help Screens.....	8
Controlling Mass Changes on a Local or Central Location Table	9
Location Table Parameters for Base Records	11
SIMPLE DATA FORMAT RULES	29
Date and Time Patterns	29
Examples.....	31
SAMPLE LOCATION TABLE ENTRIES FOR BASE RECORDS.....	32
LOCATION TABLE – CONVERSION & ACCESS CODE OVERRIDE RECORDS.....	37
ADD FUNCTION	37
DELETE FUNCTION.....	38
UPDATE FUNCTION	38
BROWSE FUNCTION.....	39
SWAP SCREEN FUNCTION	39
REINSTATE RRA FUNCTION.....	39
HELP SCREENS	39
LOCATION TABLE PARAMETERS FOR CONVERSION RECORDS	40
SAMPLE LOCATION TABLE ENTRIES FOR CONVERSION RECORDS	41
LOCATION TABLE PARAMETERS FOR ACCESS CODE OVERRIDE RECORDS..	41
SAMPLE LOCATION TABLE ENTRIES FOR ACCESS CODE OVERRIDE RECORDS..	42
CARBON COPY AND REDIRECT RECORDS	43

OVERVIEW.....	43
CARBON COPY/REDIRECT RECORDS FIELDS.....	43
ADDITIONAL CONSIDERATION.....	43
RESTRICTED AUTHORIZATION RECORDS	45
OVERVIEW.....	45
FILE TRACKING.....	45
RELATED FILE TRACKING INFORMATION.....	46
THIRD PARTY AND ELIT NETWORKS	47
COMMUNICATION WITH ASSOC OF AMERICAN RAILROADS	47
Description.....	47
Location Table Entry	48
COMMUNICATION WITH VISTEON	48
Description.....	48
Sending Data to Visteon	48
Receiving Data from Visteon.....	48
COMMUNICATION WITH VALUE ADDED NETWORKS (VAN)	49
Description.....	49
Preliminary Considerations	49
Sending Data to a Trading Partner Using a VAN	49
Receiving Data from a Trading Partner Using a VAN	50
APPENDIX A – FILE TRACKING EVENTS	52
APPENDIX B – FILE TRACKING EVENT CODES	53

INTRODUCTION

Related Documentation

Document/Website

ELIT/zOS Customization and Maintenance Guide

ELIT/zOS Operators Guide

ELIT/zOS Administrators Guide

External website:

https://www.bes.svcs.entsvcs.com/mft/Resource_Library.htm

Internal website:

https://github.dxc.com/pages/Global-BES/BES/mft_elit/

Purpose

This Administrators guide is intended to be used in conjunction with the *ELIT/zOS User's Guide*. The functions and processes described in this guide are functions and processes normally performed by an ELIT administrator not an ELIT End User.

The BSC (Binary Synchronous Communication) protocol is no longer supported by ELIT and is considered obsolete.

ELIT Alerts

Documentation revisions which have not been formally incorporated into this manual are available online via CHIP or by browsing the messages dataset SYS2.GMNMA.TNETMSGs.

Trademarks

All trademarks or servicemarks used herein are the properties of their respective owners.

- IBM® are registered trademarks of International Business Machines Corporation.
- RACF(TM) is a trademark of International Business Machines Corporation.
- CA-ACF2® is a registered trademark of Computer Associates International, Incorporated.
- CA-7(TM) is a trademark of Computer Associates International, Incorporated.
- CONTROL-M® is a registered trademark of BMC Software.
- ELIT™ and ELIT/ zOS™ are trademarks of DXC Technology.

LOCATION CODES

Several different types of location codes are defined on each ELIT system.

Type	Definition
Home Location Code	This type of location identifies the primary code for an ELIT system executing on a processor. Several different ELITs may be executing on a single processor with each ELIT having its own unique physical home location. Each ELIT system may have multiple home location codes (or logical home locations) but only one physical or "true" home location code is defined per ELIT system. That code is defined in the system startup parameters. For further clarification on home location codes and system startup parameters, refer to <i>ELIT/zOS Customization Guide</i> , MGMN-CD971.
Alternate Home Location Codes	This type of location identifies alternate codes, or "aliases" for an ELIT system. Alternate home location codes are usually defined when ELIT systems are consolidated. Multiple alternate home location codes can be defined at each ELIT system.
Switcher Location Codes	This type of location identifies another ELIT system that a home location code can communicate with. A switcher location must be defined for each indirect site that will receive transmitted data from a home location. The switcher performs a "store and forward" function, acting as an indirect link to the final destination. Multiple switcher location codes can be defined at each ELIT system.
Direct Location Codes	This type of location identifies a site that is directly connected to (or communicating with) a home (or source) location. A direct location does not require any further switching of transmitted data by a home location. Multiple direct location codes can be defined at each ELIT system.
Indirect Location Codes	This type of location identifies a site that is not directly communicating with a home location. An indirect location requires further switching of transmitted data by a home location. An indirect location specifies the switcher location that is to be used for routing data. Multiple indirect location codes can be defined at each ELIT system.

All location codes are maintained in the ELIT location table. Non-DXC Technology locations running ELIT may choose to maintain one location, the (their) Local Location Table. ELIT maintains two types of location tables, a Local Location Table and a Central Location Table. The Central Location Table is the MASTER location table where all location table entries are managed centrally. Changes to the Central Location Table are transmitted daily and are referred to as `master updates`. At ELIT MFT, the Local Location Table is the user's local ELIT location table. At most ELIT installations, the Local Location Table is identical to the Central Location Table, but they can be different. Changes to the Local Location Table are made by the local ELIT Support group.

Location tables contain various types of records; base records, conversion records, access code override records, carbon copy records, and restricted authorization records. Base records are used to define ELIT location codes. Base records contain routing and communications attributes. Conversion records convert from an alias identifier to a valid location code. These records are typically used to process EDI files that do not contain ELIT headers. Access code override records allow for the ELIT MFT access code to be modified based on source, destination and/or filename information. Carbon copy records allow files destined for one location to be also sent to another. Restricted Authorization records (RA) identify the authorized senders/receivers for restricted ids.

If your assigned location code is ABC and you want to transmit a data file to location code XYZ, then the following routing through the ELIT network may take place:

ABC --- BDS <--> PL5 --- XYZ

- locations BDS and PL5 are ELIT sites (home locations) that can communicate with each other.

- BDS's location table defines ABC as a direct location, XYZ as an indirect location that switches through PL5, and PL5 as a switcher location.

- PL5's location table defines XYZ as a direct location, ABC as an indirect location that switches through BDS, and BDS as a switcher location.

For additional information on how to browse the local location codes, refer to ["Browse Function"](#).

CHIP – CUSTOMER HELP INTERFACE

See the *ELIT/zOS User's Guide Chapter 5 CHIP – Customer Help Interface Program* for additional information.

Location Table – Base Records

If option 5 is selected from the CHIP main menu, the following panel is displayed. This panel is used to select a function that will add, delete, update, browse, or reinstate a previously deleted base location table entry on a Local or Central Location Table. If a user is not authorized, only the browse function can be performed. For an explanation of all base record parameters, refer to "Location Table Parameters for Base Records". See "Sample Location Table Entries for Base Records" for examples.

Figure 1: CHIP Location Base Record Maintenance Panel

```
+-----+
|----- ELIT/zOS Base Location Table -----|
|Command ==>|
|
|Function Code =>  A=Add, D=Delete, U=Update, B/space=Browse|
|                  R=Reinstate previous delete, S=Swap Screen|
|
|Location Code=|
|Location Owner=|
|
|Type=|
|CNCT=|
|Xmit=|
|X=|
|Trk Grp=|
|Msg Schd=|
|Access=|
|Name=|
|Address=|
|
|Switcher=|
|Max#Ses =|
|Max Blk=|
|Backup=|
|Active Times=|
|Msg Rst=|
|Change IPsw=|
|
|Rid =|
|VM#=|
|LU =|
|-|
|Fmt Codes=|
|OPsw=|
|
|Netsite=|
|SecProt=|
|Max Msg=|
|M T W T F S|
|Days=|
|Var Info=|
|Platform=|
|Delim=|
|
|Created|
|Changed|
|By|
|Used|
|SNA Console LU=|
|Operations Phone=|
|
|Press END KEY to Return to the Previous Menu.|
+-----+
```

A Common location table entry is any location table entry which does not specify a Location Owner= location code. These type of entries, by definition, are the primary location table entries that are common to all ELIT sites that use this location table.

An Owner location table entry is any location table entry which specifies a Location Owner= location code. These types of unique entries are owned by the ELIT site that use this location code as its home location code. Owner entries allow ELIT sites to modify common location table entries when unique location table parameters (such as switcher, phone number or LU name) must be specified.

"Common" vs "Owner" Entries

Location Code= ABC --> This common entry will be used
Location Owner= by all ELIT sites.

Location Code= ABC --> This unique owner entry will
Location Owner= BDS only be used by ELIT site BDS
to override the common entry.

Add Function

To Add a new location table entry, two methods may be utilized. The first is to browse a known location with similar fields. After the location entry is displayed, enter a Function Code of A and the new Location Code (and optionally a Location Owner) of the location to be added.

Modify any of the parameters or press ENTER. If any of the location parameters are invalid, the appropriate error message is displayed. Correct the parameter in error and press ENTER. When all of the parameters are valid, the message 'Location ADDED' is displayed.

The second method is to enter a Function Code of A and the new Location Code and then complete all required fields for that selection.

A Common location table entry must be defined before an Owner location table entry can be added. If a Location Owner is specified, then this code must be a valid location table entry.

Delete and Update Functions

To **Delete** or **Update** an existing location table entry, enter a Function Code of **D** or **U** and the Location Code (and optionally a Location Owner) of the location to be deleted or updated. Press ENTER. The location code and the message 'Retv for Maint' is displayed on the screen and a **D** or **U** appears in the Location Code field.

To logically delete the displayed location press ENTER. The message 'Locn Log DELETED' is displayed if the delete request was successful. This entry is not physically deleted from the location table and the user can still browse the location. A logically deleted location must be reinstated before any updates can be made to that location. Any location conversion records or restricted authorization records that are associated with this logically deleted BASE location record must be deleted from the location table prior to deleting a base record. Refer to ["Location Table - Conversion and Access Code Override Records"](#) for more information.

To physically delete the displayed logically deleted location table entry, enter a Function Code of **D** and press ENTER. The message 'Locn Phy DELETED' is displayed if the delete request was successful. This entry is physically erased from the location table.

All unique Owner location table entries associated to a Common location table entry must be deleted (logically or physically) before the Common location table entry can be deleted.

To update the displayed location modify the appropriate parameters and press ENTER. If any of the location parameters are invalid, the appropriate error message is

displayed. Correct the parameter in error and press ENTER. When all of the parameters are valid, the message 'Location UPDATED' is displayed.

The Location Owner field cannot be modified when a location table entry is updated.

Browse Functions

To Browse a specific location table entry, enter a Function Code of **B** and the Location Code (and optionally a Location Owner) of the location to be browsed and press ENTER. The location is displayed. If the location is not a valid entry in the location table, the message 'Location not found' is displayed and the user is prompted to enter another Function Code.

To position the location table, leave the Function Code blank and enter a partial Location Code. Press ENTER. The next sequentially higher location code is displayed. After a location has been displayed, press ENTER again to view the next entry. If the next entry is a conversion record entry, then the display will automatically swap to the Conversion/Override Record Maintenance Panel.

Reinstate Functions

To **Reinstate** a previously logically deleted location table entry, enter a Function Code of **R** and the Location Code (and optionally a Location Owner) of the location to be reinstated. Press ENTER. The location and message 'Locn REINSTATED' is displayed if the request is successful. The user may then update the location. The message 'Reinstate Error' is displayed if the location was not previously logically deleted.

Note: Before any unique Owner location table entries can be reinstated, the associated Common location table entry must be reinstated.

Swap Screen Functions

This enables the user to swap to the Conversion/Override Record Maintenance Panel. Enter a Function Code of **S** and press ENTER. Refer to ["Location Table - Conversion and Access Code Override Records"](#) for more information.

Help Screens

When a short form error message is displayed on a panel, additional information can be provided by pressing the PF1 key. A more detailed long form description of the error message is displayed on the same panel. If more information is required, a help screen can be invoked by pressing the PF13 key. This provides detailed information to further clarify the error message. Press the END key (PF3) to return to the Base Record Maintenance and Browse panel.

Controlling Mass Changes on a Local or Central Location Table

This section is intended for the ELIT support groups who are responsible for maintaining the various location tables in the ELIT network.

Controlling Maintenance Time & Date

From time to time it may be necessary to make a change to a local table which does not need to get passed to the Master Location Table, or a change to the master table is necessary which does not need to be distributed to all of the local tables.

To do this, disable the updating of the Maintenance Time & Date fields of the location table records to be updated. Enter a blank Function Code and **\$DATEOFF** in the `Location Code` field before selecting and changing any records.

To get back to normal mode of updating the Maintenance Time & Date fields, enter a blank Function Code and **\$DATEON** in the `Location Code` field.

Setting Record Selection Specifications

Selection of records to browse or update may be done by setting EQUAL and/or UNEQUAL arguments. Setting of arguments should be done from a screen with all fields blank. If all fields are not blank, enter a blank Function Code and **\$CLEARSCREEN** in the `Location Code` field to clear them.

To enter EQUAL arguments, enter a blank Function Code and **\$EQUALON** in the `Location Code` field plus one or more of the location table entry argument fields and press ENTER. In the upper right corner "Have equal args" will appear. By pressing ENTER a second time; a location table record would be selected when ALL of the argument fields match the corresponding fields on the record. To turn off EQUAL arguments, enter a blank Function Code and **\$EQUALOFF** in the `Location Code` field. Enter a '-' to search for blanks in the field.

To enter UNEQUAL arguments, enter a blank Function Code and **\$UNEQUALON** in the `Location Code` field plus one or more of the location table entry argument fields and press ENTER. In the upper right corner "Have equal args" will appear. By pressing ENTER a second time; a location table record would be selected when ANY of the argument fields do not match the corresponding fields on the record. To turn off UNEQUAL arguments, enter a blank Function Code and **\$UNEQUALOFF** in the `Location Code` field. When the last selected location table record has been displayed, the message "Fixing Completed" will be displayed on the upper right corner of the screen. Enter a '-' to search for blanks in the field.

Setting Changes to Fields

The Record Selection Specification must first be set by using **\$EQUALON** and/or **\$UNEQUALON**.

To enter CHANGE fields, enter a blank Function Code and **\$CHANGETOON** in the Location Code field plus one or more of the location table entry change fields. Each change field that was entered will be replaced on the corresponding field of the selected record. To turn off CHANGE fields, enter a blank Function Code and **\$CHANGETOOFF** in the Location Code field.

While performing changes, each selected record will be displayed. A Function Code of **U** may be entered to update the record or a blank to skip to the next selected record. Once the selection arguments and change fields are correct, a blank Function Code may be entered and **\$CHANGEALLON** in the Location Code field. This will cause all selected location table records to be changed.

When the message `Fixing Completed` is displayed, all of the selection arguments and change fields are removed.

Running the Full Location Table Fix/Validation Routine

The full location table fix/validation routine is used to insure that all location table entries contain valid information. Each location table entry is examined by the validation routines as if it had been entered by the user. If an inconsistency is found the location entry is presented for immediate examination and/or correction.

To invoke this routine for validation and immediate correction, enter a location code of **\$FIX\$LOOP\$**.

To invoke this routine for validation only, enter a location code of **\$FIX\$LOOP\$CHECK\$**.

Note: To skip this record while in update mode, erase the **U** in the Function Code field. To correct a record while in browse mode, place the **U** in the Function Code field

WARNING - This routine may take several minutes to complete

Location Table Parameters for Base Records

The following pages explain all of the parameters used to define a base record location table entry. The parameters are listed as presented on the sample panel.

Parameters	Definition
Location Code=	This field indicates the 3 to 17 character code that identifies a location in the ELIT network. Valid codes are defined when any combination of the following characters are used together: 1. Any alphabetic character (A - Z) 2. Any numeric character (0 - 9) 3. Any national character (@, #, \$) 4. Blank characters in positions 4-17 These location codes are assigned and maintained by the Corporate ELIT Services Group.
Location Code Type=	This field indicates what type of location is defined by this location table entry. Note: The Home location code is defined in the ELIT startup parameters, but will be defined in this field as an I or S type of location. A This location code is an Alternate Home location code. It is an alternate (or alias) to the home location code. Alternate home codes are normally defined when ELIT systems are consolidated. Multiple alternate home codes are allowed per location table. D This location code is a logically deleted location code. This value indicates that this location code has been temporarily suspended from use by this ELIT system. I This location code is a Systems Management Center (SMC) location code. This location code identifies a special ELIT system with switcher and billing responsibilities. Multiple SMC codes are allowed per location table. S This location code is a Switcher location code. This location code identifies a site that the home ELIT system can communicate with. A switcher code is defined to allow communication with non-direct location codes by routing data through this switcher location code. Multiple switcher codes are allowed per location table. V This location code is a Value Added Network (VAN) location code. It identifies a site which is not in the ELIT network, but a home ELIT system can communicate with it. A VAN is similar to a Switcher except it is not another ELIT system. Multiple VAN codes are allowed per location table. blank This location code is a direct (Switcher= ' ') or a non-direct (Switcher= 'sss') location code. A direct code identifies a site that is directly connected to the home ELIT system. A non-direct code identifies a site that is not directly connected to the

	home ELIT system. Communication with this location is accomplished by routing data through the specified switcher code. Multiple direct and non-direct codes are allowed per location table.
Header Type=	This field represents the type of header records to be sent to this location code when an outbound data transmission is initiated. Refer to the <i>ELIT zOS Users Guide</i> section on "Original Format *THS/*THD/*TTR Control Records" and "Revised Format *THS/*THD/*TTR Control Records" for more information on these type of records. Extended *THS header records are used for internal communications between various ELIT platforms (e.g. ELIT/MVS <-> ELIT/VMS) only ORIG = Send original format (Lrecl=80) *THS/*THD/*TTR records to this location code. Supports 3 character location codes only REV = Send revised format (Lrecl=80) *THS/*THD/*TTR records to this location code. Supports up to 17 character location codes EXT = Send extended format (Lrecl=variable) *THS records to this location code. Supports up to 17 character location codes.
Location Owner=	This field defines the home location code that "owns" this unique definition of this location table entry. If a home location code is specified as the "owner" of this location table entry, then this entry will only be valid at the ELIT site that uses this location code as its home location code. If this field is left blank, this location table entry will be defined as the "common" entry for use by all ELIT sites. A "common" location table entry must be defined before a location table entry can be added that specifies a location owner.
Type=	This field determines the line protocol to be used when communicating with this location code TCP/IP = Transmission Control Protocol/Internet Protocol TCP = Transmission Control Protocol for ELIT-to-ELIT communications RESERV = This is a reserved location Code. The line type will be modified when the location code is assigned SNA = Systems Network Architecture using VTAM. This includes parallel session support. VMS = RSCS SNA communication with a VM site
Switcher=	This field indicates the location code of the first switcher to be used when transmitting data to this base record location code sss = Any location table entry that is currently defined as a switcher (Location Code Type= S). The base record location code is a non-direct location code. The home location code will communicate through this switcher location code, establishing a non-direct multi-point routing path. blank = The base record location code is a direct location code. The home location code will communicate directly with the base record location code, establishing a direct point-to-point routing path.

Netsite=	This field signifies whether this site will be responsible for paying for transmissions. It, along with the "Access =" field, will determine whether the sender or receiver will pay for the file that is sent or received YES = This location code will be responsible for paying for all transmissions sent to any other site. It will also be responsible for any transmissions sent to this site by another with "Netsite=NO". NO = Any location defined as "Netsite=NO" and without an access code in the "Access=" field will never be responsible for paying for ELIT transmissions. If there is a valid access code in the "Access=" field, that site would pay for the transmission if the receiver is a "Netsite=NO" site (if sending) or if the sender is a Netsite=NO" site without an access code This field also determines if a file can be sent between sites. A transmission is not allowed if the source and destination location codes are both defined with Netsite= NO and there is not a valid access code in the "Access=" field.
Cnct=	This field declares how to initiate transmissions to this location code PUSH = ELIT will attempt to connect this location code. MAILBOX = No transmissions will be initiated to this location code. This implies that the location will always connect into ELIT. N/A = This is used for reserved locations.
Max#Ses=	This field defines the maximum number of sessions that will be allowed for this location. Valid entries = 01-50. Values higher than 50 are only valid for midrange connected sites. A '*' following the number indicates that the maximum number of sessions is the default value for the connection type. In addition, on the ELIT \$DLOC operator command, a '#' following the number indicates that the maximum number of sessions has been derived from ELIT's internal location table entry for this location. Also on the \$DLOC operator command a '??' in place of a number indicates that the value found in the internal location table entry for this location is invalid.
Rid=	This defines the Restricted Id type of this location. The value of this field is automatically maintained between the common base record and all owner records and this field can only be modified on the common base record. To change/remove a restricted id type, all corresponding Restricted Authorization records must first be logically deleted. Blank indicates that the location is not restricted. RCVR = Identifies the location as a Restricted Receiver Id. Sending locations must be authorized in order to send to this location. A Restricted Authorization record with Rid type of 'RCVR' needs to be defined for each authorized sender id. SNDR = Identifies the location as a Restricted Sender Id. Receiving locations must be authorized in order to receive from

	this location. A Restricted Authorization record with Rid type of 'SNDR' needs to be defined for each authorized receiver id. SNDR&RCVR = Identifies the location as both a Restricted Sender Id and a Restricted Receiver Id; sender and receiver Restricted Authorization record types are required (see above).
SecProt	This field specifies the security protocol used for TCP/IP ELIT to ELIT connections. For mainframe ELIT to connect securely with another ELIT, AT-TLS usage is required. TLS = TLS security protocol used. This is required for midrange ELIT to initiate a secure connection with another ELIT. For mainframe ELIT, this field is informational only; see AT-TLS policy for additional information.
Xmit=	This field indicates the transmission directions available for this location code. S&R = This location code is able to send and receive data. S R = This location code is able to send or receive data. Line turnarounds will not be allowed during a session. SEND = This location code can only send data; it is not able to receive data. No transmissions will be initiated to this location code and no data will be loaded for transmission to this location code. RCV = This location code can only receive data; it is not able to send data. Line turnarounds will not be allowed after this location code has received all of its data from this site.
Max Blk=	This field defines the maximum size of the transmission block to be used when communicating with this location code 00080-01000 = A five (5) digit numeric number in this range when communicating with ELIT 5.0 sites or non-SNA type ELIT 6.0 sites 02048 = When communicating with SNA type ELIT 6.0 sites 32760 = Must be used when communicating with all TCP/IP sites. Note that when ELIT to ELIT TCP/IP sites are transmitting BPX files a larger block size may be used.
VM#=	This field defines the VM RSCS name for this location code. xxxxxxx = A maximum eight (8) character alphanumeric RSCS name blank = An RSCS name is not used to establish a session with this location code.
Max Msg=	This field signifies the maximum number of messages in one (1) file that this location code can receive. One message = 250 transmission blocks 001 = A value of 001 implies that the entire file (regardless of size) will be sent as 1 message 002-998 = A value of 002-998 implies that the file will be sent with message breaks and that it is limited in size by the number of messages specified

	999 = A value of 999 implies that the entire file (regardless of size) will be sent with message breaks up to the 998th message. Message 999 will contain the remainder of the file.
X=	This field signifies the inbound and outbound user exits to be executed when communicating with a TCP/IP location code. xx, yy = A two (2) digit numeric value to define the inbound (xx) and outbound (yy) user exits. If no exits are used by this location code, then the value '00,00' should be designated. blank = User exits are not used with this location code.
Backup=	This field declares how to handle file backups with this location code SEND = Backup all files sent to this location code. Also used to control file backups from the home ID to an alternate home ID (backup all files unloaded for this alternate home ID) RCV = Backup all files received from this location code. Also used to control file backups from the home ID to an alternate home ID (backup all files inducted for this alternate home ID) S&R = Backup all files sent to or received from this location code NONE = Do not backup any files sent to or received from this location code Notes: This parameter will only be honored if the location table backup processing option (LTBL=) has been enabled and the location code is a direct location. Refer to the section Startup Parameters (Backup Processing Options) in the <i>ELIT/zOS Customization Guide</i>, MGMN-CD971 for more information If updating the Corporate Central Location Table, always specify Backup= NONE, unless a contractual backup is required, specify Backup= SEND/RCV/S&R.
LU=	This field defines the line logical unit (LU) name for this location code as defined to VTAM (VTAM applid) xxxxxxxx = A maximum eight (8) character alphanumeric LU name blank = An LU name is not used to establish a session with this location code.
Trk Grp=	This field indicates the Tracking Group to be associated with this location code. A Tracking Group allows related File Tracking event records to be identified and grouped together. A Tracking Group only needs to be specified on switcher locations, and all locations that switch through it will then also be considered as belonging to the same Tracking Group. A – Z A one (1) character alphabetic code.
Active Times=	This field represents the time window during which communications can occur with this location code hhmm – hhmm = A four (4) digit numeric value to define both the start and end of the time window in an hours/minutes format.

	Hours (hh) can be in the range of 00 to 24. Minutes (mm) can be in the range of 00 to 59 A time window of 0000 - 2400 indicates that this location code is available 24 hours a day. A time window of 0000 - 0000 indicates that this location code is never active.
Days=	This field determines the weekdays during which communications can occur with this location code Y = This day (Monday - Sunday) is active to communicate with this location code during the active time window (Active Times=) specified N = This day (Monday - Sunday) is NOT active to communicate with this location code during the time window of 0000 – 2400.
Msg Schd=	This field represents how message scheduling should be managed with this location code YES = Indicates this location can handle message level transmission scheduling NO = Implies that all messages for a file must be transmitted before a message from another file is sent. Interspersing messages from different files is not allowed.
Msg Rst=	This field identifies how message level restarts should be managed with this location code YES = This location code can handle message level restarts. Note that when BPX files are sent, record level restart is used rather than message level restart. NO = Implies that with line errors, or other transmission failures, the retransmission of the file will begin with the first message of the file. N,1 = Implies the same as NO, and also indicates that the site is capable of receiving only one file per connection. This value causes the connection to be broken after each file is sent. The header and trailer records for the file must have the same transmission block size as the file being sent.
Fmt Codes=	This field determines the format codes that should be used when communicating with this location code ff,vv = A two (2) digit numeric value to define the format codes to be used for fixed (ff) and variable (vv) type files ff = 00, 01, 02, 06, 07, 08, 12, 16 vv = 00, 03, 04, 05, 06, 08, 16 00/06 = F/FB/V/VB/U spanned 01 = fixed length, unblocked records (F) 02 = fixed length, blocked records (FB) 03 = variable length, blocked records (VB) 04 = variable length, unblocked records (V) 05 = teletype start/stop format 07 = fixed / variable blocked records (FB/VB) (EDI X12 ISA/BG stream data)

	08 = fixed / variable unblocked records (F/U) 12 = compressed 02 16 = compressed 06
Var Info=	This field displays variable logon and/or miscellaneous flags for various types of connections. The 1st character of this field is the category code. If this location code requires a special logon id or communication control structure, then the following codes are defined: M = Mailbag ANSI X12.56 Interconnect Control Structure will be used when sending/receiving data to/from this location code The use of this code requires that all data must be in ANSI X12 ISA Electronic Data Interchange (EDI) format. N = ELIT Network location. W = TCP/IP external web site logon id. X = EDI translation to be performed prior to delivery. If this location code requires a logon id (W in col 1), then the following logon ID's are defined: 2-19 = freeform logon id. (F in column 1) 2-18 = TCP/IP external web logon id. (W in column 1) Note: If the site is defined as TCP/IP and CNCT=PUSH is selected, the Var Info= field must contain a W. The W indicates to ELIT that this is a TCP/IP internet logon ID. The ensuing characters will contain the logon string or ID that will be sent to the receiving internet site. If this location code uses the Mailbag ANSI X12.56 Interconnect Control Structure (M in column 1), then the following information must be defined: 02-11 = mailbag logon id. 12-15 = return acknowledgements via this location code ("ZZ" qualifier assumed). 16 = acknowledge in a separate mailbag. (Y/N) 17-18 = maximum number of interchanges per mailbag. (01-20) 19 = (P)roduction or (T)est. Example of a test mailbag site with 12 interchanges requesting an acknowledgement be returned via location ABC: VAR INFO= MVANSITE123ABC Y12T Refer to Chapter 15, "Communicating with Value Added Networks" for more information. If this location code is an ELIT Network site (N in column 1), then the following information must be defined: 02 = distribute ELIT location table changes?(Y/N) 03 = location supports ELIT feedback. (Y/N) 04-09 = release / platform (6.0.0, MR) 10 = BPX flag (blank=BPX not enabled, X=BPX enabled). See the <i>ELIT/zOS Customization and Maintenance Guide</i> for additional information on BPX processing. 11 = BPX type (L=local unloads only, U=all unloads); a value is required if BPX flag=X. 12 = BPX midrange flag (M=midrange outbound BPX supported) 13-18 = blank. 19 = TCP/ELIT IP verification type; to enforce IP match option set to E; blank to log warning message only

Example of an ELIT network site receiving location table changes, accepting feedback and is at release ELIT V6.0.0:
VAR INFO= NYY6.0.0

If this location code requires EDI translation prior to delivery (**X** in column 1), then the following information must be defined:

02 = (**W**)rap or (**U**)nwrapped.

03-04 = Record format. (**U**, **F** or **FB**)

05-08 = LRECL. (must be zero filled)

09-12 = BLKSIZE. (must be zero filled)

13-14 = Segment delimiters. (must be in range of 00-FF)

15 = IEA padding required. (**Y**, **N** or **blank**)

Note: LRECL and BLKSIZE required if Record format present.

Example of a site requiring wrapping with fixed block count of 1000 and a LRECL of 1000 with segment delimiters of EE and IEA padding:

VAR INFO=XWFB10001000EEY

Access=	This field defines the access code to be used for the purpose of billing files that are sent or received by this location code. Valid access codes are alphanumeric and are six (6) characters in length. This code is validated in the Corporate Access Code Master Table.
Change	This field determines the number of days that a password may be used by this TCP/IP location code before it must be changed
IPsw/OPsw=	IPsw (Inbound) = 000 - Inbound password must be changed every connection. 001-184 - Inbound password must be changed every ### days. 185-998 - Inbound password must be changed every 185 days. 999 - Inbound password never needs to be changed. NOTE: If PCI Enabled region, IPsw= range is 000-090 OPsw (Outbound) = 000 - Outbound password never needs to be changed. 001-998 - Outbound password must be changed after ### days. 999 - Outbound password never needs to be changed
Platform=	This field indicates the operating system platform used by this TCP/IP location code, and can optionally specify if forced character encoding translation should take place. Specify "/A" to force all data to be sent using ASCII character encoding translation. Specify "/E" to force all data to be sent 'as is' (EBCDIC), where no character encoding translation will occur MVS, M/A, M/E = This TCP/IP site uses a MVS platform INTEL, I/A, I/E = This TCP/IP site uses an INTEL platform UNIX, U/A, U/E = This TCP/IP site uses a UNIX platform VMS, V/A, V/E = This TCP/IP site uses a VMS platform
Delim=	This field displays the record delimiter that will be inserted after each logical record being sent to this TCP/IP location code.

The non-forced insertion parameters only apply to data records that are formatted as text (i.e. skip the insertion of delimiters on data flagged as EDI, Mailbag, or Binary):

CR = Insert a carriage return (hex 0D) after each record.

LF = Insert a line feed (hex 25) after each record.

CR/LF = Insert a carriage return/line feed (hex 0D25) after each record.

The forced insertion parameters apply to all data records in any format (i.e. insert delimiters on data flagged as text, EDI, Mailbag, or Binary):

FCR = Force insertion of a carriage return (hex 0D) after each record.

FLF = Force insertion of a line feed (hex 25) after each record.

FCRLF = Force insertion of a carriage return/line feed (hex 0D25) after each record.

NONE = Do not insert a record delimiter after each record.

Name=	This freeform text field displays a company name for this location code.
Address=	This freeform text field identifies a company address for this location code. Note: If this site is defined as TYPE= TCP and CNCT= PUSH is selected, the Address= field must contain the IP address of the CPU that the ELIT region runs on. (i.e. 100.25.26.28) The second line of this field must contain the listening port number for this ELIT region. Optionally after the TCP location has been defined, a failover IP & PORT can be specified by typing over the 'FAILOVER.IP' (first line) and 'FOPRT' (second line). Note: If this site is defined as TYPE= TCP/IP and CNCT= PUSH is selected, then the Address= field must contain the URL that ELIT will send the Logon request to. This field must start with HTTP://, HTTPS:// or FTP:// and can continue onto the second line of the address field. This field is case-sensitive. In addition, if this site is defined as TYPE= TCP/IP and DIAL= NO is selected, then the address= field may contain inbound parameters beginning with a comma and followed by the selected parameter. (i.e. ,VI=123.456.789.012 or ,PI=123.456.789.012

This entry should be coded as

FTP://www.final_dest.com:port/directory_for_files/options. The parameters are:

Parameters	Definition
FINAL_DEST	DNS name of remote server or Cluster name.
PORT	FTP or AS2/EDIINT port where ELIT is pushing the files (see notes). A text string of "FTA" indicates the

	remote site is an instance of the “File Transfer Agent” running in cluster mode (see notes).
DIRECTORY_FOR_FILES	Directory where the files will be placed at the remote site.
,FTP SITE OPTIONS	Select which variables are desired

The parameters available for the FTP OPTIONS field are:

Parameters	Definition
svropts=x	Use the string following the x_options parameter in the ClientWrapper.properties file to override the options found in the location table
+	Add the ELIT Filename as the last node of the directory entry
+fc	Add the ELIT File Control number to the end of the data set name in the form of F#####.C#####.
+ts	Add the current date and time to the end of the data set name in the form of yyyy mm dd hh mm ss
-x	Remove the first x nodes of the data set name. (ACF2 requires them on MVS)
lc	Send the data set name in lower case
dlc	Send the directory in lower case
fdack	Server should issue an ACK to keep all received files (FTP and SSH only), even if some of the files will be held due to unknown ID's. If not specified, FTP and SSH server default will be to NAK (delete all received files) the transmission. This parameter only applies to inbound fromdata deliveries when unknown sender/receiver ID's are detected on any file, FTP will reply with a 426 when all files are NAK'ed, or a 226 when all files are ACK'ed.
nocd	Do not issue CD after logon - Use the HOME directory on the server
nocm	Do not issue the CHMOD command after file delivery (SSH only). File permissions will be determined by the local file system.
um=xxx	Use xxx for the UMASK on the CHMOD command (SSH only). If 'nocm' and 'um=xxx' are not specified, then by default, the MFT SSH server will issue a CHMOD=755 (777-022 umask) after file delivery. If 'um=xxx' is specified, then the MFT SSH server will issue a CHMOD=777-(um=xxx). For example, um=222 will issue a CHMOD=555 (777-222). Permissions: Owner / User group Other / Everyone 0 – no access to the file whatsoever 1 – execute only 2 – write only 3 – write and execute 4 – read only 5 – read and execute 6 - read and write

	7 – read, write, and execute
f=xxx	Use xxx as a template for the filename that may include \$yyy/&yyy variables for replacement
d=xxx	Use xxx as a template for the directory that may include \$yyy/&yyy variables for replacement
act	Use active FTP protocol for the data channel (ELIT selects the port). The default is passive, where the user selects the port
nat	Use the NAT address from the properties file on the port command when using active mode transmissions. This is usually required when using secure FTP with active mode
txt	Use text mode transmission rather than binary
tr	Turn on extended tracing in the ClientWrapper logs for tracing outbound commands. No outbound data is traced with this parameter
trd	Turn on extended tracing in the ClientWrapper logs for tracing of the inbound/outbound data buffers. Data is displayed exactly as read or written on the socket with the remote server (Valid for both FTP and SSH). If ClientWrapper is doing a FТПPULL or SSHPULL and 'TRD' is "on" in the FТПPULL file destination location table record, then the pulled data(inbound) from the remote server will be written(traced) to the ClientWrapper log4j log.
rn=xxx	Transmit the file using xxx as a data set name prefix. When the file is successfully delivered, rename the file by removing the xxx.
fw=xxx	Transmit the file using a proxy firewall. The initial string following the FTP:// will be the address of the firewall. XXX will be the host name of the FTP server. The ClientWrapper.properties file will contain the variables LOC.proxyuserid and LOC.proxypasswd where LOC is the receiving location. The values will contain the firewall userid and password.
fbc=x	Replace every occurrence of "x" in the filename with a blank.
dbc=x	Replace every occurrence of "x" in the directory with a blank.
mcp	Use mixed case Userid and Password (FTP will force lowercase if not specified).
site	Issue a 'site lrecl=xx' command, where xx is the lrecl of the original MVS dataset.
chunk=#	Requests that the data should be segmented into # sized records (delimited with CR/LF). The last record will be padded with spaces if the data does not completely fill an entire record. This command is useful when the platforms file system is limited to certain size records (AS400). Note: 'DELIM= NONE' should also be specified on the location table entry to avoid additional delimiter characters from being added to the data.
ebmx	Used on Chrysler locations only. Will default q= and tp= values to 'chryft' (but can be overridden if q= and/or tp= is specified after 'ebmx'). Will scan and

	replace '-' to '_' in original dataset name and add senderID/FST# suffix to generate unique filename. Will issue quote site DCXSUBMIT command after the PUT to acknowledge and delete the file on Chrysler's system.
q=xxx	Quote Template. Issue a 'quote' command using the template named xxx_quote supplied in the server's optionfile properties. The template can contain \$yyy variables for substitution.
tp=xxx	Tracking Prefix. Scan the reply from a PUT command using the string specified with the "xxx_tracking" parameter supplied in the ELITServices.properties file, or the file pointed to by the "optionfile" parameter within the ClientWrapper.properties file. The data following the scan string will be supplied to File Tracking as the TP reference number.
as1.5	Indicates this location uses AS1 over FTP (Linen's N' Things).
ssh	Use SSH (Secure Shell) for the File Transfer Protocol.
sk	Use SSH (Secure Shell) key authentication.
bh	Use the Basic HTTP file upload format (MIME multipart) in the POST command to send the data file to the recipient.
bhx	Use instream data to send the XML document in the POST command to the recipient (CAP format).
rsp	This parameter provides support for Common Aftermarket Protocol (CAP) XML messages (e.g., AvailabilityRequest / AvailabilityResponse). It can be specified with either the "bh" or "bhx" parameter to read the response to the HTTP post. The response is then sent to the location specified in the ELIT filename.
soap	Parse the received XML file into an XML document. If parsing is successful create a SOAP message containing the document and POST it to the specified receiver web service (e.g., SAP XI). The file will not be sent if it does not contain a valid XML document.
na	For E5 V2 and HTTP/S Transfers. This option stops the server from sending the HTTP Basic Authentication header.
h=xx=yy	Insert xx=yy as a header(s) in the HTTP output stream used in the POST command. Multiple H= are allowed.
opw1	Indicates to the ELIT ClientWrapper server to use Outbound Processing syntax #1 (OLDPW^NEWPW), when required to change the outbound password for this particular FTP/SSH customer. An alphanumeric 8 character PW will be generated. Add 'Mcp' (see description above) if mixed case characters are desired
opw2	Indicates to the ELIT ClientWrapper server to use Outbound Processing syntax #2 (OLDPW/NEWPW), when required to change the outbound password for this particular FTP/SSH customer. An alphanumeric 8 character PW will be generated. Add 'Mcp' (see description above) if mixed case characters are desired

altIP	Indicates to ELIT ClientWrapper server to use Alternate IP connection processing on this outbound transmission for this particular customer. Initially established for FORD. The IP address found in the 'dnsname' file in the ClientWrapper directory, that matches the location table DNS name will be used to connect to the remote server rather than the DNS name found in the ELIT location table
psIP	Indicates to ELIT ClientWrapper server to use Secondary IP addressing processing on this outbound transmission for this particular customer. The IP address found in the location table will be attempted first for connectivity. If a connection failure occurs, the secondary IP address matching the customer communication code in the secIPname file will be attempted. Available for both FTP and SSH.
zlib	Enables compression using zlib compression algorithm (SSH only).
upasv	Indicates to ELIT ClientWrapper server to use the returned passive port IP address of the data connection of the remote FTP Server rather than the IP address of the control connection which could be an intermediate device.
ldir	Ignore directories when pulling multiple files using mget command in FTPPULL trigger file (SSH only)
pgpe	Use PGP encryption for this file. By default, the Trading Partner's public PGP key (ReceiverId_PGP.pub) is used. This parameter can be used for pushed sites as well as pull sites (mailboxes).
pgps	Sign this file using the ELIT private PGP key. By default, ClientWrapper's private key is used (i.e. ELCLWP004P_PGP.pri). The pgpe parameter must also be specified if the pgps parameter is used.
pgpaa	Use ASCII Armor on this PGP file.
pgpd	PGP decrypt received files. This option forces PGP decryption in the SSH and FTP protocols, relieving the user from triggering decryption, and requiring that the files are PGP encrypted when sent to ELIT. By default, the private PGP key of the server is used for decryption (i.e. ELSSHP004P_PGP.pri, ELFTPP004P_PGP.pri).
Pgpdv	PGP decrypt and verify signature of received files. This option forces PGP decryption and signature verification in the SSH and FTP protocols, relieving the user from triggering these functions, and requiring that the files are PGP encrypted and signed when sent to ELIT. By default, the private PGP key of the server is used for decryption (i.e. ELSSHP004P_PGP.pri, ELFTPP004P_PGP.pri), and the Trading Partner's public key is used for signature verification.
Pgpo	Use the older PGP full packet data stream. Files in this format are restricted to a maximum size of 4 gig.
Pgpni	Do not supply the PGP "Integrity Check" (older PGP implementations do not support the MIC).
pgp1k	Only PGP encrypt using the Trading Partners public PGP key (ReceiverId_PGP.pub). If omitted, then also encrypt with the ELIT public key (i.e.

	ELCLW_PGP.pub, etc.). Encrypting with the ELIT public key allows us to decrypt the data, if needed, during problem analysis.
pgpv3	Use PGP Version 3 Signatures for this file.
pgpea=x	Use the specified PGP Encryption Algorithm (see PGP table). Default=9 (AES-256)
pgpha=x	Use the specified PGP Hash Algorithm (see PGP table). Default=10 (SHA-512)
pgpca=x	Use the specified PGP Compression Algorithm (see PGP table). Default=1 (ZIP)
ftpto=x	Number of seconds for the socket timeout parameter on outbound FTP transfers (both the control and data ports). Default=120 (Two Minutes)
sshto=x	Number of seconds for the socket timeout parameter on outbound SSH transfers. Default=30 seconds
mbih	The Hub should use the MFT generic Van Id (i.e. ZZ*ELIT) when building the Mailbag IH* header record.
semn	The Hub should check for a 'Special EMail Notification' GFNT definition for this location. An Email will be sent to the defined address when 1) a file is mailboxed, or 2) a delivered file exceeds the specified size. Requires that GFNT entries also be added to specify the Email notification address in 'Notify Delivery Success', and optionally, a file exceeded size in 'User Parameter 1'.

PGP Encryption Algorithms

Parameters	Definition
2	Triple-DES (DES-EDE, as per spec - 168 bit key derived from 192)
3	CAST5 (128 bit key, as per RFC 2144)
4	Blowfish (128 bit key, 16 rounds)
5	SAFER-SK128 (13 rounds)
6	DES/SK
7	AES with 128-bit key
8	AES with 192-bit key
9	AES with 256-bit key
10	Twofish

PGP Hash Algorithms

Parameters	Definition
1	MD5
2	SHA-1

3	RIPE-MD/160
4	double-width SHA
5	MD2
6	TIGER/192
7	HAVAL (5 pass, 160-bit)
8	SHA-256
9	SHA-384
10	SHA-512
11	SHA-224

PGP Compression Algorithms

Parameters	Definition
0	No Compression
1	ZIP (RFC 1951)
2	ZLIB (RFC 1950)
3	BZIP2

FTP NOTES –

The port will default to 21.

Prefixing the port with 'S' will indicate Secure FTP "Implicit Session Security".

Prefixing the port with 'P' will indicate Secure FTP "Implicit Session Security" with an explicit request to protect data channel PORT P, required by some implementations of FTP servers (for example FileZilla).

Prefixing the port with 'N' will indicate Secure FTP using "Negotiated Session Security". Prefixing the port with 'O' will indicate Secure FTP using "Negotiated Session Security" and "SSL" instead of "TLS".

Prefixing the port with 'A' will indicate Secure FTP using "Negotiated Session security" and "AUTH TLS" instead of the older "AUTH TLS-P".

The URL should always end with a / even when the entry does not include a directory or options.

When using \$yyy variables in a FTP Quote template, the variable must end with a dot (".") (i.e. Cov_quote=routing to =\$rid.,from=\$sid.,doctype=\$fnm.,format=GM),

SSH NOTES –

Mainframe: Authentication can be either user-id/password or shared key.

Midrange: Intranet allows either user-id/password or shared key authentication.

Internet allows shared key authentication only, password authentication is not allowed.

File Transfer Agent NOTES –

The ELIT File Transfer Agent has the capability to run in "cluster mode". When the port is specified using the string "FTA", the requests should be sent to an instance of the Client Wrapper (CITY=) using a protocol of HTTP://. The Client Wrapper will verify the presence of a ClusterName_cluster tag (see FINAL_DEST) in the properties file. This tag will consist of comma delimited URL's (Host:port) that will be used by load balancing and failover code in the Client Wrapper.

Example of FTA Cluster URL in Addr1:

HTTP://VERFTA:FTA

Example of ClientWrapper cluster property:

VERFTA_cluster =
www.host1.com:25500,www.host2.com:25500,www.host3.com:25500

AS2/EDIINT SITE OPTIONS Select which variables are desired.

The parameters available for the AS2/EDIINT OPTIONS field are:

Parameters	Definition
e=h	Encrypt data using 168 bit DES_EDE3_CBC.
e=m	Encrypt data using 128 bit RC2_CBC.
fr=xxx	Use xxx as the AS2-From id in the transaction (defaults to the ELIT SenderId).
to=xxx	Use xxx as the AS2-To id in the transaction (defaults to the ELIT ReceiverId).
ac=xxx	Use xxx as the Application Content Type in the Mime header.
f=xxx	Use xxx as a template for the filename that may include \$yyy variables for replacement.
us	The transaction will be unsigned.
cs	The transaction will be compressed before signing.
uc	The transaction will be uncompressed.
um	The transaction will request an unsigned MDN.
nm	The transaction will not request an MDN.
dc	The transaction will use Dual Certificates (see notes).
am=xxxx	The transaction will request an Asynchronous MDN using the specified protocol (xxxx=HTTP or HTTPS).
pto=	Post Timeout in minutes. This is used to override the default post timeout limit on the AS2 server for known slow connection.

The valid \$yyy/&yyy variables are listed below. Each variable must be prefixed by a delimiter (period or slash), except the first variable, if it is at the start of the string (i.e. 'EDI.\$sid.&fcn', '\$sid/\$rid/AA/&ref'). Specifying a '\$yyy' variable will cause the delimiter to be included before the inserted variable. When building remote directories/ filenames, specifying a '&yyy' variable will cause the inserted variable to be appended onto the string (remove the delimiter).

Variable	Definition
\$dat/&dat	Date the file was received in the form of yyyy mm dd.
\$tim/&tim	Time the file was received in the form of hh mm ss.
\$rid/&rid	ELIT location code of the receiver (file destination).
\$sid/&sid	ELIT location code of the sender (where file originated from).
\$ref/&ref	ELIT File Reference number (supplied by file sender).
\$fnm/&fnm	ELIT Filename.

\$fcn/&fcn	ELIT File Control number (FC# supplied by ELIT).
\$fst/&fst	ELIT File Control number (FST# supplied by ELIT).
\$dsn/&dsn	Original data set name.
\$pfc:XX:##&pfc:XX :#	Prefixed File Control Number - where XX is the prefix, and # is the total length. Example - \$pfc:AF:8 will create a string 8 characters long starting with "AF" followed by the lowest 6 characters of the File Control Number (FC# supplied by ELIT). This is used for systems with very restrictive naming conventions (TANDEM). The valid length range (#) that can be specified is a minimum value of the prefix length +1, and a maximum value of the prefix length +10. So in the above example, since the prefix="AF", the valid length range that can be specified is between 3-12.
\$rdt=xxx	Use the ELIT received date as input to the xxx mask for building a filename string applying the SimpleDateFormat rule.
\$sdt=xxx	Use the ELIT send date as input to the xxx mask for building a filename string applying the SimpleDateFormat rule.

AS2/EDIINT NOTES -

The transaction will default to unencrypted (encrypt using HTTPS), compressed, signed data, requesting a Synchronous Signed MDN.

The server's home directory will contain the trading partner's digital certificate named "LOCATION.cer".

If the Dual Certificates option was specified, the server's home directory will contain two certificates – "LOCATION.cer" for digital signatures, and "LOCATION.enc.cer" for

Parameter	Definition
City=	This freeform text field identifies a city that is associated with the above address. Note: If this site is defined as TYPE= TCP/IP and CNCT= PUSH is selected, then the City= field must contain the URL of the ELIT Batch Browser, which processes PUSH requests. This field must start with www or a specific IP address (i.e. 100.25.26.27). This field is case-sensitive
State=	This freeform text field defines a state that is associated with the above address.
Zip=	This freeform text field indicates a zip code that is associated with the above address.
Country Code=	This freeform text field defines a country code that is associated with the above address.
Contact Name=	This freeform text field reveals a contact name for this location code.
SNA Console LU=	This field indicates the SNA console logical unit (LU) name for this location code as defined to VTAM (VTAM applid).

	XXXXXXX = A maximum eight (8) character alphanumeric LU name blank = An LU name is not used to log onto a console for this location code
Contact Phone=	This freeform text field indicates a phone number that is associated with the above contact name.
Operations Phone=	This freeform text field indicates a secondary phone number for the operations group that supports this location code.

SIMPLE DATA FORMAT RULES

Date and Time Patterns

Date and time formats are specified by date and time pattern strings. Within date and time pattern strings, unquoted letters from 'A' to 'Z' and from 'a' to 'z' are interpreted as pattern letters representing the components of a date or time string. Text can be quoted using single quotes (') to avoid interpretation. '""' represents a single quote. All other characters are not interpreted; they're simply copied into the output string during formatting or matched against the input string during parsing.

The following pattern letters are defined (all other characters from 'A' to 'Z' and from 'a' to 'z' are reserved):

Letter	Date or Time	Presentation	Examples
G	Era designator	Text	AD
y	Year	Year	1996
M	Month in year	Month	July; Jul; 07
w	Week in year	Number	27
W	Week in month	Number	2
D	Day in year	Number	189
d	Day in month	Number	10
F	Day of week in month	Number	2
E	Day in week	Text	Tuesday; Tue
a	Am/pm marker	Text	PM
H	Hour in day (0-23)	Number	0
k	Hour in day (1-24)	Number	24
K	Hour in am/pm (0-11)	Number	0
h	Hour in am/pm (1-12)	Number	12
m	Minute in hour	Number	30
s	Second in minute	Number	55
S	Millisecond	Number	978
z	Time zone	General time zone	Pacific Standard
Z	Time zone	RFC 822 time zone	-0800

Pattern letters are usually repeated, as their number determines the exact presentation:

Text: For formatting, if the number of pattern letters is 4 or more, the full form is used; otherwise a short or abbreviated form is used if available. For parsing, both forms are accepted, independent of the number of pattern letters.

Number: For formatting, the number of pattern letters is the minimum number of digits, and shorter numbers are zero-padded to this amount. For parsing, the number of pattern letters is ignored unless it's needed to separate two adjacent fields.

Year: For formatting, if the number of pattern letters is 2, the year is truncated to 2 digits; otherwise it is interpreted as a [number](#).

For parsing, if the number of pattern letters is more than 2, the year is interpreted literally, regardless of the number of digits. So using the pattern "mm/dd/yyyy", "01/11/12" parses to Jan 11, 12 A.D.

For parsing with the abbreviated year pattern ("y" or "yy"), SimpleDateFormat must interpret the abbreviated year relative to some century. It does this by adjusting dates to be within 80 years before and 20 years after the time the SimpleDateFormat instance is created. For example, using a pattern of "mm/dd/yy" and a SimpleDateFormat instance created on Jan 1, 1997, the string "01/11/12" would be interpreted as Jan 11, 2012 while the string "05/04/64" would be interpreted as May 4, 1964. During parsing, only strings consisting of exactly two digits, as defined by [Character.isDigit\(char\)](#), will be parsed into the default century. Any other numeric string, such as a one digit string, a three or more digit string, or a two digit string that isn't all digits (for example, "-1"), is interpreted literally. So "01/02/3" or "01/02/003" are parsed, using the same pattern, as Jan 2, 3 AD. Likewise, "01/02/-3" is parsed as Jan 2, 4 BC.

Month: If the number of pattern letters is 3 or more, the month is interpreted as text; otherwise, it is interpreted as a number.

General time zone: Time zones are interpreted as text if they have names. For time zones representing a GMT offset value, the following syntax is used:

```
GMTOffsetTimeZone:
    GMT Sign Hours : Minutes
Sign: one of
    + -
Hours:
    Digit
    Digit Digit
Minutes:
    Digit Digit
Digit: one of
    0 1 2 3 4 5 6 7 8 9
```

Hours must be between 0 and 23, and Minutes must be between 00 and 59. The format is locale independent and digits must be taken from the Basic Latin block of the Unicode standard.

For parsing, RFC 822 time zones are also accepted.

RFC 822 time zone: For formatting, the RFC 822 4-digit time zone format is used:

```
RFC822TimeZone:
Sign TwoDigitHours Minutes
TwoDigitHours:
    Digit Digit
```

TwoDigitHours must be between 00 and 23. Other definitions are as for [general time zones](#).

For parsing, [general time zones](#) are also accepted.

SimpleDateFormat also supports localized date and time pattern strings. In these strings, the pattern letters described above may be replaced with other, locale dependent pattern letters. SimpleDateFormat does not deal with the localization of text other than the pattern letters; that's up to the client of the class.

Examples

The following examples show how date and time patterns are interpreted in the U.S. locale. The given date and time are 2001-07-04 12:08:56 local time in the U.S. Pacific Time zone.

Time & Date Pattern	Result
yyyy.MM.dd G 'at' HH:mm:ss z"	2001.07.04 AD at 12:08:56 PDT
"EEE, MMM d, "yy"	Wed, Jul 4, '01
"h:mm a"	12:08 PM
"hh 'o'clock' a, zzzz"	12 o'clock PM, Pacific Daylight Time
"K:mm a, z"	0:08 PM PDT
"yyyy,MMMM,dd GGG hh:mm aaa"	02001, July. 04 AD 12:08 PM
"EEE, d MMM yyyy HH:mm:ss Z"	Wed, 4 Jul 2001 12:08:56 -0700
"yyMMddHHmmssZ"	010704120856-0700

SAMPLE LOCATION TABLE ENTRIES FOR BASE RECORDS

Figure 2: CHIP Location Table Sample Base Entries

Sample Home Entry			
Location Code= TSZ	Location Code Type= I	Header Type= EXT	
Location Owner=			
Type= SNA	Switcher=	Netsite= YES	
Cnct= PUSH	Max#Ses=005	Rid=	SecProt=
Xmit= S&R	Max Blk= 1000	VM#=	Max Msg= 999
X=	Backup= SEND	LU = NCCAG003	M T W T F S S
Trk Grp=	Active Times=	0000 - 2400	Days= Y Y Y Y Y Y Y
Msg Schd= YES	Msg Rst= YES	Fmt Codes= 16	Var Info=
Access=	Change IPsw=	OPsw=	Platform= Delim=
Sample Alternate Home Entry			
Location Code= PVC	Location Code Type= A	Header Type= EXT	
Location Owner=			
Type= SNA	Switcher=	Netsite= YES	
Cnct= PUSH	Max#Ses=005	Rid=	SecProt=
Xmit= S&R	Max Blk= 1000	VM#=	Max Msg= 999
X=	Backup= NONE	LU = AA2RSCS3	M T W T F S S
Trk Grp=	Active Times=	0000 - 2400	Days= Y Y Y Y Y Y Y
Msg Schd= YES	Msg Rst= YES	Fmt Codes= 16	Var Info=
Access=	Change IPsw=	OPsw=	Platform= Delim=
Sample Switcher Entry			
Location Code= HEY	Location Code Type= S	Header Type= EXT	
Location Owner=			
Type= SNA	Switcher=	Netsite= YES	
Cnct= PUSH	Max#Ses=005 *	Rid=	SecProt=
Xmit= S&R	Max Blk= 1000	VM#=	Max Msg= 999
X=	Backup= NONE	LU = NCAAG002	M T W T F S S
Trk Grp= A	Active Times=	0000 - 2400	Days= Y Y Y Y Y Y Y
Msg Schd= YES	Msg Rst= YES	Fmt Codes= 06	Var Info=
Access=	Change IPsw=	OPsw=	Platform= Delim=

Sample SNA Entry

Location Code= DA3 Location Code Type= Header Type=
EXT
Location Owner=TSZ

Type= SNA Switcher= Netsite= YES
Cnct= PUSH Max#Ses=010 Rid= SecProt=
Xmit= S&R Max Blk= 1000 VM#= Max Msg= 999
X= Backup= SEND LU = PMFNGBDB M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y Y
Msg Schd= YES Msg Rst= YES Fmt Codes= 16 Var Info=
Access= Change IPsw= OPsw= Platform= Delim=

Sample SNA Entry with an Owner

Location Code= DA3 Location Code Type= Header Type= EXT
Location Owner= TSZ

Type= SNA Switcher= Netsite= YES
Cnct= PUSH Max#Ses=005 Rid= SecProt=
Xmit= S&R Max Blk= 1000 VM#= Max Msg= 999
X= Backup= SEND LU= PMFXXBDT M T W T F S S
Trk Grp= Active Times= 1200 - 2400 Days= Y Y Y Y Y Y Y
Msg Schd= YES Msg Rst= YES Fmt Codes= 16 Var Info=
Access= Change IPsw= OPsw= Platform= Delim=

Sample Value Added Network (VAN) Entry

Location Code= VAN Location Code Type= V Header Type=
ORIG
Location Owner=

Type= TCP/IP Switcher= GD8 Netsite= YES
Cnct= PUSH Max#Ses=003 Rid= SecProt=
Xmit= S|R Max Blk= 32760 VM#= Max Msg= 001
X= 00,00 Backup= NONE LU = V/FT M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y Y
Msg Schd= NO Msg Rst= NO Fmt Codes= 07 Var Info= WEDSNET PM
Access= Change IPsw= 000 OPsw= 999 Platform= U/E Delim=NONE

Sample FTP Entry that connects via Secure FTP

Location Code= MENTOR Location Code Type= Header Type=
EXT
Location Owner=

Type= TCP/IP Switcher= Netsite= YES
Cnct= PUSH Max#Ses=002 Rid= SecProt=
Xmit= S&R Max Blk= 32760 VM#= Max Msg= 999
X= Backup= NONE LU = I/FS M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y N
Msg Schd=YES Msg Rst=YES Fmt Codes= 07 Var Info= WFMENTORSQ
Access= Change IPsw= 180 OPsw= 180 Platform= INTEL Delim= CR
Name=
Address= FTP://trdvow02.iweb.ibm.com:S999/site/

Sample VAN Entry using Mailbag Interconnect Control Structure

Location Code= ZZATTEDSNETELS Location Code Type= V Header Type=
EXT
Location Owner=

Type= TCP/IP Switcher= GD8 Netsite= YES
Cnct= PUSH Max#Ses=009 Rid= SecProt=
Xmit= S|R Max Blk= 32760 VM#= Max Msg= 001
X= 00,00 Backup= NONE LU =V/FT M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y Y
Msg Schd= NO Msg Rst= NO Fmt Codes= 07 Var Info= WEDSNET PM
Access= Change IPsw= 000 OPsw= 999 Platform=U/E Delim=NONE

Sample VM Entry (Interface with RSCS)

Location Code= VME Location Code Type= Header Type= ORIG
Location Owner=

Type= VMS Switcher= Netsite= YES
Cnct= PUSH Max#Ses=001 Rid= SecProt=
Xmit= S&R Max Blk= 1000 VM#= AHIPC2S Max Msg= 001
X= Backup= NONE LU = AA2RSC2S M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y Y
Msg Schd= NO Msg Rst= NO1 Fmt Codes= 00 Var Info=
Access= Change IPsw= OPsw= Platform= Delim=

Sample Indirect VM Entry switched through another VM site

Location Code= VM1 Location Code Type= Header Type= ORIG
Location Owner=

Type= VMS Switcher= LJT Netsite= YES
Cnct= PUSH Max#Ses=001 Rid= SecProt=
Xmit= S&R Max Blk= 1000 VM#= JESNN3A Max Msg= 001
X= Backup= NONE LU= VTAMRSC2 M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y N N N N N N
Msg Schd= NO Msg Rst= NO Fmt Codes= 00 Var Info=
Access= Change IPsw= OPsw= Platform= Delim=

Sample TCP Entry for ELIT-to-ELIT communications

Location Code= TC1 Location Code Type= S Header Type= EXT
Location Owner=

Type= TCP Switcher= Netsite= YES
Cnct= PUSH Max#Ses=020 Rid= SecProt=
Xmit= S&R Max Blk= 32760 VM#= Max Msg= 999
X= Backup= NONE LU = M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y N
Msg Schd=YES Msg Rst=YES Fmt Codes= 16 Var Info=
Access= Change IPsw= OPsw= Platform= Delim=
Name=
Address= 248.26.58.392
 7900

Sample TCP/IP Entry for ELIT-to-Server communication

Location Code= AUTOPUSHSITE Location Code Type= Header Type=
EXT
Location Owner=

Type= TCP/IP Switcher= Netsite= YES
Cnct= PUSH Max#Ses=010 Rid= SecProt=
Xmit= S&R Max Blk= 32760 VM#= Max Msg= 099
X= Backup= NONE LU = M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y N
Msg Schd= NO Msg Rst= NO Fmt Codes= 07 Var Info= WEDS
Access= Change IPsw= 180 OPsw= 180 Platform= INTEL Delim= CR
Name=
Address= HTTP://www.elit.eds.com:8090/servlet/

Sample FTP Entry that connects to a NT server

Location Code= PYC Location Code Type= Header Type=
EXT
Location Owner=

Type= TCP/IP Switcher= Netsite= YES
Cnct= PUSH Max#Ses=007 Rid= SecProt=
Xmit= S&R Max Blk= 32760 VM#= Max Msg= 999
X= Backup= NONE LU = M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y N
Msg Schd=YES Msg Rst=YES Fmt Codes= 07 Var Info= WEDSELITE
Access= Change IPsw= 180 OPsw= 180 Platform= INTEL Delim= CR
Name=
Address= FTP://888.99.77.254/,nocd,+fc,+ts,lc
City= www.elit.eds.com:12345

Sample FTP Entry that connects via Secure FTP

Location Code= MENTOR Location Code Type= Header Type=
EXT
Location Owner=

Type= TCP/IP Switcher= Netsite= YES
Cnct= PUSH Max#Ses=002 Rid= SecProt=
Xmit= S&R Max Blk= 32760 VM#= Max Msg= 999
X= Backup= NONE LU = I/FS M T W T F S S
Trk Grp= Active Times= 0000 - 2400 Days= Y Y Y Y Y Y N
Msg Schd=YES Msg Rst=YES Fmt Codes= 07 Var Info= WFMENTORSQ
Access= Change IPsw= 180 OPsw= 180 Platform= INTEL Delim= CR
Name=
Address= FTP://trdvow02.iweb.ibm.com:S999/site/
 live/upload,f=pu_mentor.txt
City= www.elit.eds.com:12345

LOCATION TABLE – CONVERSION & ACCESS CODE OVERRIDE RECORDS

If Function Code **S** is selected from the base record maintenance and browse panel, the following panel is displayed. This panel is used to select a function that will add, delete, update, or browse a conversion or access code override location table entry. If a user is not authorized, only the browse function can be performed.

Location table conversion records are used to convert location and filename table entries from one code to another. For an explanation of all conversion record parameters, refer to "[Location Table Parameters for Conversion Records](#)". See "[Sample Location Table Entries for Conversion Records](#)" for examples.

Location table access code override records define various filename, source location, and final destination location combinations. A file will use an override access code for billing purposes if the file matches a defined filename, source, and final destination combination. For an explanation of all access code override record parameters, refer to "[Location Table Parameters for Access Code Override Records](#)". See "[Sample Location Table Entries for Access Code Override Records](#)" for examples.

Figure 3: CHIP Location Conversion/Override Record Maintenance Panel

```
+-----+
|----- ELIT/zOS Conversion/Override Location Table -----|
|Command ==>|
|
|  Function Code =>      A=Add, D=Delete, U=Update, B/space=Browse
|                      S=Swap Screen, R=Reinstate RA Record
|
|VAN AND AAR CONVERSION RECORDS
| Conv Code=
| To Code=
| Conv Type=          Strip=
|
|ACCESS CODE OVERRIDE RECORDS          CARBON COPY/REDIRECT RECORDS|
| Filename=                      Destination=
| File Source=                    Carbon Copy To=
| File Destination=                Source Id   =
| Access Code=                      Filename   =
|                                   Redirect (Y) =
|RESTRICTED AUTHORIZATION RECORDS      Start Date = (MM/DD/YYYY)|
| Receiver Id   =                      End Date   = (MM/DD/YYYY)|
| Sender Id    =
| Record Rid Type=                    (SNDR or RCVR)
| Record Status =
|
|Press END KEY to Return to the Previous Menu.
+-----+
```

ADD FUNCTION

To **Add** a new location table conversion or override entry, mask the appropriate entry by first browsing an existing entry. After the entry is displayed, enter a Function Code of **A**. If adding a conversion entry, enter the new Conv Code and modify any of the other conversion parameters. If adding an override entry, modify the appropriate override parameters and press ENTER.

If any of the conversion or override parameters are invalid, the appropriate error message is displayed. Correct the parameter in error and press ENTER. When all of

the parameters are valid, the message 'Location ADDED' or 'Access Override ADDED' is displayed.

If entering the panel for the first time, a conversion or override entry may be added by modifying all of the appropriate parameters delete function

Note: A conversion record will not be added if the To Code base location table entry does not exist in the location table.

DELETE FUNCTION

To **Delete** an existing location conversion, override table entry, carbon copy, or restricted authorization record, enter a Function Code of **D** after the appropriate entry has been displayed and then press ENTER. Conversion or override entry will be physically deleted and the message 'Locn Phy DELETED' or 'Access Override DELETED' will be displayed.

Note: Location conversion or override records can only be physically deleted, logical deletes are not supported.

A restricted authorization record will be logically deleted on the master location table and the delete will be pushed out to the local sites where the record is physically deleted. The master's logical delete will become a physical delete on the next calendar day on which the updates are processed. On standalone location tables, the entry will be physically deleted.

UPDATE FUNCTION

To **Update** an existing location conversion or override table entry, enter a Function Code of **U** after the appropriate conversion or override entry has been displayed and then press ENTER. The message 'Retv for Maint' will be displayed if the entry has not been previously displayed. Modify the appropriate parameters. Press ENTER.

If any of the location parameters are invalid, the appropriate error message is displayed. Correct the parameter in error and press ENTER. When all of the parameters are valid, the message 'Location UPDATED' or 'Access Override UPDATED' will be displayed.

Note: To Update the Conv Code field of an AAF type filename entry, you must first delete the original entry and then immediately add the new entry with the updated Conv Code field.

BROWSE FUNCTION

To **Browse** a specific location conversion or override table entry, enter a Function Code of **B** and the Conv Code or Filename/File Source/File Destination combination to be browsed. Press ENTER. The location conversion or override entry is displayed. The message 'Location not found' is displayed if the entry is not defined in the location table and the user is prompted to enter another Function Code.

To position the location table, leave the Function Code blank and enter a partial Conv Code or Filename and press ENTER. The next sequentially higher location conversion or override entry is displayed. After a location conversion or override entry has been displayed, press ENTER again to view the next entry. The display will automatically swap to the Base Record Maintenance Panel if the next entry is a base record entry or no location conversion or override records exists.

Note: When attempting to browse AAF type conversion records you must enter 'AAF' in the Conv Type field, and then hit ENTER or optionally put a filename in the Conv Code field.

SWAP SCREEN FUNCTION

This enables the user to swap to the Base Record Maintenance Panel. Enter a Function Code of **S** and press ENTER. Refer to ["Location Table - Base Records"](#) for more information.

REINSTATE RRA FUNCTION

This enables a logically deleted RA record to be reinstated as active. This is only valid on master location tables.

HELP SCREENS

When a short form error message is displayed on a panel, additional information can be provided by pressing the PF1 (or HELP) key. A more detailed long form description of the error message is displayed on the same panel. If more information is required, a help screen can be invoked by pressing the PF13 key. This provides detailed information to further explain the error message. To return to the previous panel, press the END (PF3) key.

LOCATION TABLE PARAMETERS FOR CONVERSION RECORDS

The following page explains all of the parameters used to define a location conversion record. The parameters are listed as presented on the sample panel.

Parameters	Definition
Conv Code =	Defines the external 1 to 39 character alias location code that will be converted into the base location code specified by "To Code=".
If "Conv Type= AAF", then this field defines the external 1 to 10 character AAR filename that will be converted into the ELIT filename specified by "To Code=".	
To Code=	Defines the 3 to 17 character base location code that the alias location code (specified by "Conv Code=") will be converted into
If "Conv Type= AAF", then this field defines the 1 to 10 character ELIT filename that the external AAR filename (specified by "Conv Code=") will be converted into.	
Conv Type =	Defines the type of conversion record that is represented. X12 = Represents an X12 conversion record AAR = Represents an AAR conversion record. AAF = Represents an AAR filename conversion record
Strip =	Defines the 'strip' or 'no-strip' character that is to be used by ELIT when processing incoming header records if "Conv Type= AAR or AAF S = Strip headers N = Do not strip headers

SAMPLE LOCATION TABLE ENTRIES FOR CONVERSION RECORDS

Figure 4: CHIP Location Table Sample Access Code Override Entries

Sample X12 Entry	
Conv Code= ABY08577	
To Code= AG6	
Conv Type= X12	
Strip=	
Sample AAR Entry (Obsolete)	
Conv Code= RAILCNO	
To Code= CNO	
Conv Type= AAR	
Strip= N	
Sample AAF Entry	
Conv Code= SWACO	
To Code= FRATERALTS	
Conv Type= AAF	
Strip= N	

LOCATION TABLE PARAMETERS FOR ACCESS CODE OVERRIDE RECORDS

The following page explains all of the parameters used to define an access code override record. The parameters are listed as presented on the sample panel.

All files that match a combination of the filename, source location code, and final destination location code will use the specified override access code when the file is billed.

Parameters	Definition
Filename =	Defines the 1 to 10 character filename that will be used to override an access code for billing purposes

File Source =	Defines the 3 to 17 character base source location code that will be used to override an access code for billing purposes
File Destination =	Defines the 3 to 17 character base final destination location code that will be used to override an access code for billing purposes
Access Code =	Defines the 6 character access code that will be used to override an existing access code for billing purposes

SAMPLE LOCATION TABLE ENTRIES FOR ACCESS CODE OVERRIDE RECORDS

Figure 5: CHIP Location Table Sample Access Code Override Entries

Sample Override Entry (Matches Filename Only)

```
Filename= EDI856ASN
File Source=
File Destination=
Access Code= XYZ123
```

Sample Override Entry (Matches Filename/Source)

```
Filename= EDI856ASN
File Source= ABC
File Destination=
Access Code= XYZ123
```

Sample Override Entry (Matches Filename/Destination)

```
Filename= EDI856ASN
File Source=
File Destination= BDS
Access Code= XYZ123
```

Sample Override Entry (Matches Filename/Source/Destination)

```
Filename= EDI856ASN
File Source= ABC
File Destination= BDS
Access Code= XYZ123
```

CARBON COPY AND REDIRECT RECORDS

OVERVIEW

The creation of a **Carbon Copy** record results in a duplicate file being delivered to the destination address specified in the record. As this may not always be suitable (files being copied to another VAN, for example), the requestor must be sure that the receiver of the copied file is capable of handling and processing the document.

The creation of a **Redirect** record results in a file being re-routed to a different destination other than the one to which the file was originally pointed. With a **Redirect** record, the transmission is routed only to the new site and not to the original destination. As with carbon copy records, one must be sure that the receiver is prepared for the transmission and is capable of processing the document.

CARBON COPY/REDIRECT RECORDS FIELDS

Destination: Required. Original destination of the file.

Carbon Copy To: Required (The destination to which the file or copy will be directed.)

Source Id: Optional (Source of the original transmission. Leave blank if the source is not a determining factor in creating the copy or redirect.)

Filename: Optional (Leave blank if all files are to be copied or redirected. Enter a specific ELIT filename if only one filename will be copied or redirected.)

Redirect (Y): Optional (Specify "Y" if the file is to be redirected. Leave blank for carbon copy records.)

Start Date: Required (The date that the files are to begin being copied or redirected.)

End Date: Required (The last date that the files will be copied or redirected.)

ADDITIONAL CONSIDERATION

Start Date: The ELIT Master Location Table daily update process normally runs at 2PM ET on weekdays unless the update job gets a special run. If a record is to start on the day that it is created and is entered into the Master Location Table prior to 2PM ET, the copies or redirects will begin at 2PM ET on that day. If entered after 2PM ET, the records will take effect at 2PM ET on the subsequent weekday (or on the following Monday if the record is created on a Friday, Saturday or Sunday).

If the record being created is to begin on a subsequent date, it will take effect at 00:01 ET on the 'Start Date' specified in the record.

Billing: A limitation exists today that requires that the site responsible for paying for the original transmission will also pay for any files that are copied.

EDI-Direct Source: If the original sender of the file is uploading an EDI-formatted document and is using an EDI-direct process to upload data into the ELIT Network (also known as "FROMDATA"), the source specified in the carbon copy or redirect record must be the sender ID in the data (and not the associated ELIT "base record"). The 'Carbon Copy To' site would be the associated base record destination to which the file is to be delivered.

An example of this concept is when other Value-Added Networks send transmissions into the ELIT Network.

RESTRICTED AUTHORIZATION RECORDS

OVERVIEW

Restricted Authorization records are required to allow for communicates with restricted locations; a restricted location is one that has the base record "Rid=" field set. There are two types of restricted ids, restricted sender id and restricted receiver id.

A Restricted Sender Id requires that all receivers be authorized via a Restricted Sender Authorization Record Type.

A Restricted Receiver Id requires that all senders be authorized via a Restricted Receiver Authorization Record Type.

Locations that are both a Restricted Sender Id and a Restricted Receiver Id require both types of authorization records.

Parameters	Definition
Receiver Id=	Defines the 1 to 17 character base location receiver id
Sender Id=	Defines the 1 to 17 character base location sender id
Record Rid Type=	Defines the type of Restricted Authorization Record. One of the following will be specified: "SNDR" if this is a Restricted Sender Id Authorization Record "RCVR" if this is a Restricted Receiver Id Authorization Record.
Record Status=	Displays the status as "active" or "deleted"(only on master tables) and the last update date

FILE TRACKING

The following information is intended for DXC Technology SMC sites only.

File-Tracking is an optional facility that allows sites to GENERATE and send tracking data and forward it to a centralized TRACKING region. The TRACKING region serves as a warehouse for all of the GENERATOR (or sending) ELIT regions. This TRACKING ELIT region will receive the \$TRACKING\$ files from the GENERATOR regions and unload them to the DB2 tracking data base where the information is made available via the Web.

Entries, or Events are generated when files are loaded, unloaded, delivered to an off-network site and for a number of other events. These \$TRACKING\$ files are housed on the buffer pool as any other file.

ELIT determines which type of event is to be recorded, such as a LOAD or UNLOAD by the VAR INFO= parameter of the Location table. The combined NETWORK and

FEEDBACK fields of this parameter determine if the site is an DXC Technology SMC site and which types of tracking events are to be GENERATED for the TRACKING region.

The DIAL= parameter also affects what events are to be recorded. If a LOAD event is completed and DIAL= NO is selected, the event is recorded as the file being MAILBOXED, rather than LOADED. In this example, only one event is recorded when the file is loaded into ELIT. Afterward, the data is periodically forwarded to the TRACKER region, where it is written to the DB2 database that warehouses the event records and makes them available for reporting purposes via the Web.

At the TRACKING site, the UNLOAD task distinguishes between normal user files and \$TRACKING\$ files, unloading those files to a DB2 database running under the local DB2 Subsystem. All DB2 related functions are performed under the control of the UNLOAD task. When an UNLOAD task is started, ELIT attempts to contact the DB2 Subsystem and allocate the PLAN that was bound at installation time. When the UNLOAD task ends, the PLAN is freed and a disconnect to DB2 is issued. Event records are periodically purged as determined by the ELIT Startup parameters.

RELATED FILE TRACKING INFORMATION

A Web client application is available for browsing and querying the database.

Note: THIS FEATURE CURRENTLY IN PILOT MODE AND IS UNAVAILABLE TO THE GENERAL PUBLIC. THIS PAGE WILL BE REVISED WHEN THIS OCCURS.

Refer to Appendix A, "[FILE-TRACKING EVENTS](#)" for information regarding ELIT tracking events. Refer to Appendix B, "[FILE-TRACKING EVENT CODES](#)" for information regarding ELIT event codes and their definitions.

Note: It is possible that at any given time that not all sites will have File-tracking capabilities. To learn if your locations(s) are involved, contact your local ELIT support.

THIRD PARTY AND ELIT NETWORKS

This section includes an overview of how ELIT can be set up to communicate with third-party networks.

COMMUNICATION WITH ASSOC OF AMERICAN RAILROADS

Description

ELIT can communicate with the Association of American Railroads (AAR) switcher. This interface requires ELIT to convert *THS headers to AAR type headers. The conversion is performed at the ELIT system that communicates directly with the AAR switcher using location table conversion records to convert *THS format headers and trailers to AAR format headers and trailers.

When ELIT sends to AAR, the *THS headers are used to create AAR headers. When receiving from AAR, ELIT takes information from the AAR headers to build the appropriate *THS headers. The AAR header is treated as the first data record in the file by ELIT and is passed to the recipient as part of the file.

A description of the fields in the AAR headers used in the conversion to and from *THS headers is provided below.

Term	Definition
System Identity	Five position alphabetic field. When sending to AAR, it is taken from the first five characters of the filename. When receiving from AAR, it is converted to a filename based on a location conversion record.
Origin Road Mark	Two to four characters identify the originating location. When sending to AAR, it is taken directly from the file's source location code. When receiving from AAR, it is converted to a location code for the originating railroad and is used as the file's source location code.
Destination Road Mark	Two to four characters identify destination. When sending to AAR, it is the file's destination location code converted to a valid AAR road mark. It is not used when receiving from AAR
Destination Subaddress	Four position alphabetic field (optional). When sending to AAR, it is taken directly from the first four characters of the destination user ID. When receiving from AAR, the first three characters are taken directly as the destination location code

Notes:

If the data set being loaded uses *P* type headers, the user must provide a destination subaddress by putting an @ character (must be preceded by at least one blank) in position 53 and the four character subaddress in positions 54 through 57 of the *P* record.

If the data being sent to a railroad contains imbedded AAR headers, the user must use a filename of TRANHEADER. When transmitting a file called TRANHEADER, ELIT discards the *THS headers and trailers and makes no attempt to build AAR headers.

Any location code that communicates with an AAR site must have a location conversion record to:

Convert AAR marks to location codes. Convert AAR system identity codes to filenames.

Indicate if railroad headers are to be stripped.

A default destination location code (location PL7) has been defined for files received from AAR that do not specify an ELIT location code

Location Table Entry

Location table entry X=07,07 should be defined in the location table entry for AAR locations. This will invoke the special processing within the TCP/IP interface to convert between AAR format headers and *THS format header records.

Contact your local ELIT Administrator for location table changes.

COMMUNICATION WITH VISTEON

Description

ELIT communicates with Visteon through an external VAN (Sterling) via the ANX network using the FTP protocol. At this time, X12 type data is the only format supported. Location FR2 is the Visteon Production system and location FR5 is the Visteon Education (test) system.

Sending Data to Visteon

Data is sent to Visteon when the destination FR2 or FR5 is specified. If EDI Direct is used, the EDI data must have a receiver ID of VISTN in the ISA record for file going to the Production (FR2) system. The data is immediately sent to Visteon over the ANX network (via Sterling).

The data must be compliant with Visteon X12 transactions. The ISA record must have VISTN as the receiver ID and your GSDB code as the sender ID. Likewise, the GS record must contain your GSDB code as the sender ID and a valid Visteon GSDB code as the receiver ID. (usually a plant or functional group) Refer to RELATED Visteon INFORMATION.

When sending to Visteon's Education system, use FR5 as the destination and a receiver ID of VISTE in the ISA record.

Receiving Data from Visteon

If your site is an FTP mailbox, the data will be queued to your mailbox. If you are a mainframe TSO user, the data is unloaded to a pre-defined ELIT filename table entry. That entry is a combination of the Visteon location code and your Visteon GSDB code. For example, if your Visteon GSDB code is A123B and you are communicating with the Visteon production system (FR2), the filename should be defined as FR2A123B.

Contact your local ELIT Administrator for location.

COMMUNICATION WITH VALUE ADDED NETWORKS (VAN)

Description

ELIT is able to electronically interconnect to several third-party Value Added Networks (VANs) to allow Electronic Data Interchange (EDI) documents to be exchanged between trading partners.

Preliminary Considerations

To communicate with a trading partner who is a customer of a VAN with which ELIT interconnects, the following initial requirements should be met:

The data the user and the trading partner wish to exchange must be in ANSI X12 (ISA or BG) format. ELIT only interconnects to VANs for EDI purposes if the data to be exchanged is in ANSI X12 format. If the data does not exist in ANSI X12 format, various translator packages are available to translate it into ANSI X12 format. Contact MFT Services at 866-214-0108, option 1, option 1, option 2 or mft.services@dxc.com for more information on ELIT MFT supported EDI translators.

The user and the trading partner must agree on the EDI sender and receiver IDs to be used for data exchange. These EDI IDs are used in ISA record fields ISA05, ISA06, ISA07, and ISA08 along with the appropriate BG record fields.

These EDI sender and receiver IDs must be registered with the trading partner's VAN and with MFT Services before EDI can begin. It is the trading partner's responsibility to register this information with the VAN. The user also must contact MFT Services at 866-214-0108, option 1, option 1, option 2 or ELIT MFT mft.services@dxc.com to register this information with ELIT MFT.

A special location table entry must be included in the ELIT Location Table when the VAN interconnect interface is to be used. This entry allows ELIT to accept files from third party VANs even in most error situations, such as the situation where EDI IDs in files being received are not defined in the ELIT location table. Files from other third-party VANs must be accepted under these conditions due to inter-VAN agreements. Disposition of these files when they are received is covered in the *ELIT/zOS Operators Guide, MGMN-OD971*.

Contact your local ELIT Administrator for location table requirements.

When these initial considerations have been satisfied, EDI documents can then transmit between the trading partner and the user.

Sending Data to a Trading Partner Using a VAN

Documents sent to the trading partner must always be in ANSI X12 format. If necessary an EDI translator can be used to translate the user's non-ANSI X12 document into ANSI X12 format.

The documents sent to the trading partner must have the user's EDI ID as the ISA sender ID (ISA record fields ISA05 and ISA06) or the BG sender ID and the trading partner's EDI ID as the ISA receiver ID (ISA record fields ISA07 and ISA08) or the BG receiver ID.

ELIT filenames normally do not have any meaning to the trading partner. Therefore, it should not be necessary for the ANSI X12 document sent to the trading partner to contain a filename. If, however, the trading partner wishes to have a filename within the document, ISA record fields ISA01 and ISA02 can be used to include a filename in

the same manner as specified in the preceding section. Filenames are not supported in BG-type documents.

Document transmission to the trading partner should be initiated by the user's submission of an ELIPXMIT job. This ELIPXMIT job stream should identify the user's ANSI X12 document as the file to be transmitted. This ELIPXMIT job should also identify the trading partner's ELIT location code as the final destination code where the data is to be sent. The filename the user specifies as part of this ELIPXMIT job is for the user's use only in identifying the transmission within ELIT MFT systems, but is not actually sent to the trading partner. The following ELIPXMIT job stream example would transmit an ANSI X12 ISA document EDI.SAMP to a trading partner with an ELIT location code of TP1.

```
//EDIJOB    JOB    ...
//JS010     EXEC   PGM=ELIPXMIT, PARM='VENDORXYZ, , TP1 '
//STEPLIB   DD     ...
//SYSMSG    DD     ...
//SYSUT1    DD     DSN=EDI.SAMP, DISP=SHR
```

Refer to the *ELIT_zOS Users Guide* section on "How To Use ELIPXMIT To Send Files" for more information.

The result of the execution of the ELIPXMIT job is to request ELIT to interconnect to the trading partner's VAN and to deliver the user's document to that VAN for ultimate transmission by that VAN to the trading partner.

Receiving Data from a Trading Partner Using a VAN

Documents received from a trading partner through a VAN are always in ANSI X12 (ISA or BG) format. An EDI translator can be employed if the user needs to process these documents in another format.

These ANSI X12 documents specify the user's EDI ID in the ISA receiver ID field (ISA fields ISA07 and ISA08) or in the appropriate BG fields. Through the use of location conversion records, this EDI ID results in the delivery of the document to the ELIT system of the user.

These ANSI X12 documents can also select which ELIT filename to use in unloading these documents when they reach the user's processing environment. If these documents do not specify an ELIT filename, one is generated for the user.

ISA record fields ISA01 and ISA02 are used to specify an ELIT filename within the ANSI X12 document. A filename entry is defined as being contained in ISA record field ISA02 if ISA record field ISA01 (the authorization information qualifier) contains a character **03** value.

Note: It is normally the application program running at the trading partner's site that places this filename in the document.

No such filename capability exists for BG-type documents.

If no filename is specified in the EDI document, ELIT will generate a filename according to the following rules:

1. The filename `EDIDATA` is generated if the trading partner's EDI sender ID is not translated into a 3 character ELIT location code.
2. The filename `EDIDATAxxx` is generated, where `xxx` is the translated ELIT location code of the trading partner's EDI sender ID.

For example, if the trading partner's EDI sender ID is ZZ*TRADEPARTNER and is translated into the ELIT location code TP1, then the generated filename for this document is EDIDATATP1.

Location Table Entry

When using a VAN interconnect, certain fields must be coded as described in the following sample location table entry. Contact ELIT Services for required location table changes.

Mailbag VANs

A Mailbag VAN is a Value Added Network (VAN) that uses the ANSI X12.56 Interconnect Mailbag Control Structure Standard to construct Mailbags, but does not have document level restart capability in the event of a TP line failure. Mailbag VANs retransmit the mailbag that was previously transmitted during a TP connection if that TP connection terminated in error.

Mailbag VANs provide the following:

- Clear identification of sender and receiver IDs.
- A capability to allow for logon and password information.
- Control information to validate the number of EDI documents and Mailbag acknowledgements received against the number indicated as being sent.
- Feedback from the receiving Mailbag VAN regarding the receipt, deliverability, and interchange syntax acceptability of received Mailbags.

All user data must be in ANSI X12 ISA Electronic Data Interchange (EDI) format. A Mailbag consists of an interconnect mailbag header record (IH), the EDI data to be transmitted, and the interconnect mailbag trailer record (IT). In addition, interconnect mailbag acknowledgement records (IA) can be included in a mailbag that contains EDI data or in its own mailbag. Acknowledgement records report on the status of previously sent or received mailbags.

Mailbag VANs Location Table Entries

When using a Mailbag VAN interconnect, certain fields must be coded in the location table entry. Contact your local ELIT Administrator for required location table changes.

APPENDIX A – FILE TRACKING EVENTS

ELIT RECORDED EVENTS at the TRACKING site.

*TRACKING EVENTS	RECORDED AT TRACKING LOCATION
------------------	-------------------------------

1. LOAD FAILED	NO
2. LOAD SUCCESSFUL	YES
3. SEND SUCCESSFUL	NO (YES IF DELIVERED OFFNET)
4. SEND FAILED / HELD	ES
5. RECEIVE SUCCESSFUL	NO (YES IF RECORDING LEVEL2)
6. RECEIVE FAILED	NO
7. HELD BY OPERATOR	YES
8. RELEASED BY OPERATOR	NO
9. MAILBOXED	YES
10. DELIVERED OFFNET	YES
11. PICKED UP	YES
12. UNLOADED	YES
13. BACKED UP	NO
14. UNLOAD FAILED / HELD	YES

APPENDIX B – FILE TRACKING EVENT CODES

ELIT EVENTS codes and their definitions.

*CODE	EVENT

A.	FILE LOADED
B.	FILE UPLOADED
C.	FILE RECEIVED
D.	FILE MAILBOXED, AWAITING PICKUP
I.	FILE CANCELED
J.	FILE PURGED
L.	FILE HELD
M.	FILE HELD
N.	FILE HELD
S.	FILE PICKED UP, AWAITING ACKNOWLEDGEMENT
T.	FILE DELIVERED OFF-NETWORK, AWAITING ACK
1.	FILE PICKED UP
2.	FILE DELIVERED TO OFF-NETWORK SITE
3.	FILE UNLOADED
4.	ACKNOWLEDGEMENT - TO PENDING STATUS (S & T)

Document Version History

Version No.	Version Date	Revised By	Affected Section & Description of Change
6.0.0	10/19/2007		Major reorganization. Splitting User's Guide into z/OS User's Guide and z/OS Administrator's Guide. This version contains the changes from D971 Revisions 1 – 4. Changes for NetSite. Change Ford to Visteon. Updated for JDE071-001. Updated for JDE071-017.
6.0.1	11/08/2007		Updated for JDE071-003 (added zlib for SSH)
6.0.2	01/09/2008		Changes for maintenance release 072. ACS related changes. Revised IPsw/OPsw parameters. Added new OPW2 parameter to specify password delimiter.
6.0.3	02/14/2008		Updated for JDE071-029 (added Trd), JDE081-009 (added Upasv) and JDE071-045 (added FTA Cluster definition).
6.0.4	05/28/2008		Updated for JDE081-021 (added PGP options).
6.0.5	11/27/2008		Updated doc to meet HP ENTERPRISE SERVICES/HP standards.
6.0.6	01/14/2009		Updated for JDE091-001 (added ftpto=).
6.0.7	10/15/2009		Updated for JDE091-041 (added na option).
6.0.8	01/14/2010		Updated to HP template format.
6.0.9	02/17/2010		Updated URL links.
6.0.10	04/01/2010		Updated for JDE101-009(added PROT P option). Updated for JDE101-002 (updated TRD parameter).
6.0.11	05/04/2010		Updated for maintenance release 10.1.
6.0.12	08/03/2010		Updated page 17 to document "rsp" parameter.
6.0.13	10/07/2010		Updated copyright statement.
6.0.14	03/06/2011		Updated for maintenance release 10.2.
6.0.15	02/09/2012		Added SSH Notes on Page 18.
6.0.16	03/15/2012		Updated for maintenance release 11.1 and new FTP/SSH parameter 'TRD' enhancement. Added PGP decryption options: pgpd, pgpdv.

6.0.17	05/10/2012		Update PSIP parameter information for SSH.
6.0.18	05/31/2012		Updated for maintenance release 11.2. Updates include addition of 'RID=' base field, expanded Restricted Authorization support, and removal of obsolete information.
6.0.19	08/02/2012		Updated for JDE112-042. Added idir FTP option for FTTPULL SSH jobs.
6.0.20	08/03/2012		Updated for JDE112-033. Added sshto=x parameter for SSH locations.
6.0.21	02/28/2013		Updated for maintenance release 12.1.
6.0.22	02/19/2014		Update PGP parameter information.
6.0.23	03/26/2015		Updated for maintenance release 14.1. Remove obsolete references to 'S38', 'VAX' and 'ASYN'. Clarify the Delim= parameter. Add documentation for &var variables. Add new variables \$fst/&fst.
			Clarified URL location parameters.
6.0.24	10/23/2015	Julie Noelke	Removed HP logo, change HP to HPE, HP Enterprise Services to Hewlett Packard Enterprise, @hp.com to @hpe.com, ELIT Services to MFT Services, updated copyright.
6.0.25	11/16/2015	Nancy Lamberti	Updated for maintenance release 15.1. Add TCP optional failover IP/port.
6.0.26	01/07/2016	Julie Noelke	Updated to new HPE corporate template.
6.0.27	03/17/2016	Marc Nurmi	Added "soap" option to section 3.9.
6.0.28	5/25/2017	Julie Noelke	Updated copyright to DXC, removed HPE styles and references. Changed to DXC where appropriate.
6.0.29	03/13/2019	Greg Friess	Added "mbih" option to section 3.9.
6.0.30	05/30/2019	Greg Friess	Added 'semn' option to section 3.9..
6.0.31	05/18/2021	Nancy Lamberti	Updated for maintenance release 18.1. Update terminology to match what is used on Central. Add new TCP/ELIT security protocol field. Add new TCP/ELIT enforce IP match option. Fix formatting issues. Update 'Max#Ses' and 'Var Info'.
6.0.32	08/30/2021	Julie Biafore	Updated to new DXC template.
6.0.33	12/21/2021	Nancy Lamberti	Minor change to 'Var Info'.