



Before you start: close Nuke, NukeStudio and Hiero. If they are open the installation may fail or be left halfway through.

Automatic installation

Extract the whole `.zip` into any folder. The installer and the `LGA_ToolPack-Layout` folder have to stay together.

Windows

- Double-click `installer_win.bat`.

macOS

- Open Terminal in the folder where you extracted the `.zip`.
- Run:

```
bash installer_mac.sh
```

- The leading `bash` is deliberate: it works even if the `.sh` travelled inside the `.zip` without its executable permission, which fails with *Permission denied*.

What the installer does

- Checks that no Foundry applications are running.
- Copies the pack to `~/ .nuke/LGA_ToolPack-Layout` (on Windows, `%USERPROFILE%\ .nuke`). If it cannot find the `.nuke` folder, it lets you enter another path.
- If a previous version was installed, it renames it to `LGA_ToolPack-Layout_backup` and leaves it there so you can roll back. It is removed automatically on the next install.
- Adds the required line to `init.py`, saving a numbered backup into `~/ .nuke/LGA_init_backups/` beforehand, named after the pack that made it.

Manual installation

If you would rather do it by hand, or the installer fails:

- Copy the `LGA_ToolPack-Layout` folder into `~/ .nuke` (`%USERPROFILE%\ .nuke` on Windows), so that you end up with `~/ .nuke/LGA_ToolPack-Layout/` holding `menu.py`, `py/` and everything else.
- With a text editor, add this line to the `init.py` file inside the `.nuke` folder:

```
nuke.pluginAddPath('./LGA_ToolPack-Layout')
```

Enabling and disabling tools

Before opening Nuke for the first time you can edit the `Enabled.default.ini` shipped inside the pack. They all default to `True`; the ones you switch to `False` are hidden from the menu and skip loading altogether.

The first time you open Nuke that configuration is copied to your user folder, at `%APPDATA%\LGA_ToolPack-Layout\Enabled.ini` (on macOS, under `~/Library/Application Support`). From then on the file inside the pack is no longer the place to change it: use the **TPL > Enable Tools** menu, and updates will not overwrite it.

Full documentation for every tool, and updates, at github.com/legandrop/LGA_ToolPack-Layout-for-Nuke